EarthStick 1.3.3 User Guide

A printable copy of this guide is available as EarthStick_User_Guide.pdf.



The whole setup on one page.

Purpose

EarthStick gives a Thrustmaster TCA Sidestick Airbus Edition direct control of the ArcGIS Earth camera. The goal is free movement inside a functioning map: imagery, labels, roads, GIS layers, and offline content remain part of the environment while you fly the camera.

The defining behavior is **neutral = hover**. When the movement controls return to neutral, EarthStick stops moving the camera.

New in 1.3.3: your **height, heading and map zoom** on screen, even in full-screen mode (see *The readout* below).

New in 1.3.2: the World Gates pack v19 - each city's welcome sign and site stars float up in the sky, far away, where they stay clear of the gates.

New in 1.3.1: a **round-the-world tour** through the World Gates, with welcome signs and one-click site beacons in every city; a larger crosshair; and a **one-click start** from the taskbar (see *One-click start* below).

New in 1.3: **World Gates** - golden rings in the sky; fly through one and you arrive somewhere else on Earth (see *World Gates* below).

New in 1.2: **trigger-click**. A red crosshair sits in the middle of the ArcGIS Earth window. Put an object under it and pull the trigger to open the object's information box (popup) without touching the mouse.

Requirements

- Windows 11
- ArcGIS Earth desktop
- ArcGIS Earth Automation API enabled
- Python 3 from python.org; tested with Python 3.14.5 (the standard install includes Tkinter, which draws the crosshair)
- Thrustmaster TCA Sidestick Airbus Edition connected by USB
- Thrustmaster driver/control panel recommended
- `EarthStick.py` and `EarthStick.bat` in the same folder

No third-party Python packages are required.

Controller check

First download and install the Thrustmaster driver (TCA Sidestick X Airbus Edition), then plug the joystick in by USB.

Before running EarthStick:

1. Press `Win + R`.
2. Run `joy.cpl`.
3. Select the T.A320 controller.
4. Confirm the stick X/Y axes move and return to center.
5. Confirm twist/rudder responds.
6. Confirm Slider 0 travels through its range.
7. Confirm POV up/down responds.
8. Confirm Button 4, Button 3 and the trigger (Button 1) respond.

The tested controller normally appears as `T.A320 Pilot`.

ArcGIS Earth setup


1. Open ArcGIS Earth desktop.
2. Open Settings.
3. Under Advanced, enable **Automation API**.

4. Use the default local API address `http://localhost:8000`.

Start EarthStick

1. Download `EarthStick_v1.3.3.zip` and extract it. It contains a folder named `EarthStick_v1.3.3` holding `EarthStick.py`, `EarthStick.bat`, the one-click start files `Fly_ArcGIS_Earth.bat` and `Make_Taskbar_Shortcut.bat`, a `Gates` folder with the World Gates pack and a `City_Beacons` folder.
2. Open ArcGIS Earth first, with the Automation API enabled.
3. Open the `EarthStick_v1.3.3` folder and double-click `EarthStick.bat`. A console window titled **EarthStick 1.3.3** opens.
4. EarthStick reports the detected joystick and Slider 0 source. If the joystick is not plugged in, it says so and waits until it is.
5. It then shows `Waiting for ArcGIS Earth Automation API at http://localhost:8000 ...`. If ArcGIS Earth is not ready, `Still waiting:` lines explain why.
6. Wait for `ArcGIS Earth: connected`, followed by `Trigger-click: ready`. The red crosshair appears in the middle of the ArcGIS Earth window.
7. Return the stick to neutral before beginning.

What each file in the folder does



Controls


Control	Action
Stick forward	Fly forward
Stick back	Reverse
Stick left/right	Strafe left/right
Twist/RZ	Change heading
Slider 0	Travel speed
POV up/down	Camera tilt
Red Button 4	Hold to descend / zoom in
Black Button 3	Hold to climb / zoom out
Trigger (Button 1)	Click the object under the red crosshair
Neutral	Stop and hover

Flying technique

For precise inspection, lower the throttle, approach the target, release the stick, and hover. Use strafe and twist independently to inspect the target from different positions without being forced into forward motion.

For long-distance movement, climb to a high altitude and increase the throttle. The maximum travel rate scales with altitude. Descend again when you reach the destination.

The readout: height, heading and zoom (1.3.3)




On the right of the ArcGIS Earth window, just above the globe button, EarthStick shows two lines while you fly:

- **Top line - height** in feet above sea level (the same number as ArcGIS Earth's eye alt, which disappears in full-screen mode).
- **Bottom line - heading and zoom:** the compass point and degrees you are facing, then **≈ Z** and the web map zoom level that shows the ground at about the same detail from your height. Handy for knowing when your TPKX maps (for example Z17 or Z20) are at their sharpest.

The readout lets mouse clicks pass through, follows the window, and hides while ArcGIS Earth is minimized. To turn it off, open `EarthStick.py` in Notepad and change `SHOW_READOUT = True` to `SHOW_READOUT = False`.

Trigger-click: opening and closing information boxes




The red crosshair (right) and a camera object (left). Fly until the camera sits under the crosshair, hover, then pull the trigger.

1. Fly until the object (a beacon, a camera, a parcel, a point) sits under the red crosshair.
2. Let go of the stick so the camera hovers.
3. Pull the trigger once. EarthStick moves the Windows mouse pointer onto the object, clicks it, and puts the pointer back where it was. The object's information box opens.
4. **To close the box,** aim the crosshair at open map, away from the box, and pull the trigger again.

Tips:

- One pull = one click. A second pull within 0.8 seconds is ignored, so a bouncy trigger can never turn into a double-click (a double-click makes ArcGIS Earth zoom in).
- If another window is in front, the first click brings ArcGIS Earth to the front and EarthStick then clicks the object.
- The crosshair follows the ArcGIS Earth window if you move or resize it, and hides while ArcGIS Earth is minimized. Mouse clicks pass straight through it.
- If the crosshair cannot be shown, the console says `Trigger-click: unavailable` and EarthStick flies normally.
- If the crosshair sits off the true centre on your screen, the `CENTER_OFFSET_X` / `CENTER_OFFSET_Y` settings near the top of `EarthStick.py` nudge it by screen pixels.

World Gates: flying through wormholes



The Atlanta hub: eight gates in a circle around Hartsfield-Jackson, all at the same height.

A gate is a golden ring floating in the sky. Fly through it and EarthStick moves you to its destination in an instant. You arrive still flying, facing the landmark.


Fly your first trip

1. Open the **World Gates** file in ArcGIS Earth: drag `Gates\World_Gates_JAX_ATL_v19.kmz` (in the EarthStick folder) onto the map, so you can see the rings.
2. Start EarthStick. The console lists the gates it armed: `Wormholes: 22 gate(s) armed: ATL, JAX, NYC, ...`
3. Fly to a ring, line up on its **gold** side (from the red side nothing happens), match the altitude shown under its name using **eye alt** at the bottom of ArcGIS Earth, and fly through the middle.
4. The view jumps to the destination and the console says `Wormhole: through the ... gate.` You arrive still flying, already facing the landmark.

The World Gates pack (included)

- **Jacksonville:** one gate, **ATL**, over Jacksonville International (eye alt 1,500 ft), facing north-west toward Atlanta.
- **Atlanta hub:** you arrive in the middle of a 3 km circle of eight gates around Hartsfield-Jackson, all at eye alt 2,530 ft (1,500 ft above the airport). Turn and pick: NYC (north-west), London (north), Paris (north-east), Rome (east), JAX - home (south-east), Rio (south), Sydney (south-west), Tokyo (west).
- **Destinations:** you arrive about 1.7 km from the Statue of Liberty, Tower Bridge, the Eiffel Tower, the Colosseum, Tokyo Tower, the Sydney Opera House or Christ the Redeemer, facing it. The **ATL** gate behind you takes you back to the hub to connect home or onward.
- **Round-the-world tour (1.3.1):** about 2 km beyond each landmark is a gate to the next city: New York > London > Paris > Rome > Tokyo > Sydney > Rio, and Rio's onward gate is its ATL gate. Fly in, pass the landmark, and carry on through the next gate.

Welcome signs and site beacons (1.3.1)




Coming out of a gate in London.

- **Welcome sign:** "Welcome to ..." floats ahead of you, up in the sky about 6 km away (at Atlanta, above the ring of gates).
- **Site stars:** below it, five gold stars in two rows (about 4 km away, still in the sky) name the city's famous sites (Atlanta and Jacksonville too). Each name is drawn in its beacon's colour: red, blue, green, magenta, orange.
- **Beacon on:** aim the crosshair at a star and pull the trigger. A short information box opens and a beacon in that colour shoots up over the site (3 km tall), with its name at the bottom. Pull

the trigger on open map to close the box, then fly to the beacon. Clicking the same star again does not add a second beacon.


- **Beacon off:** untick it under **My Drawings** on the left of ArcGIS Earth.
- Signs, stars and ring names only show within about 4 miles, so far-away views stay clean. Beacons use ArcGIS Earth's Automation API, the same setting EarthStick needs.



Two beacons up in Paris.

City beacons: straight to a city (1.3.1)

The `City_Beacons` folder holds nine red beacons (Go to Jacksonville, Go to Atlanta, Go to New York ... Go to Rio de Janeiro). Drag them onto ArcGIS Earth. Double-click one in the Data list and ArcGIS Earth flies you there, skipping the gates. You arrive straight above the beacon, so nudge the view to see its line.



Each gate's name sits beside its own ring, with the eye alt to fly at underneath.

Rules of the gates

- **Gold side only.** Each ring has a gold front and a red back. Fly in from the gold side; from the red side, from below, from above or beside it, nothing happens.
- **Match the altitude.** The number under each name is the **eye alt** (shown at the bottom of ArcGIS Earth, measured from sea level) of the ring's centre. Rings are 450 m (about 1,500 ft) across, so within a few hundred feet is fine.
- **Keep moving.** A gate fires while the joystick is moving the camera. Hovering or moving the map with the mouse does not trigger it.
- **One trip per pass.** After a jump, gates rest for 2 seconds.
- **Any speed works.** EarthStick checks the whole path between its updates, so even a fast pass cannot skip through a ring.

Turning gates on and off

EarthStick reads the gate files in the **Gates** folder beside `EarthStick.py` **when it starts**. ArcGIS Earth cannot tell EarthStick which layers are switched on, so the folder is the switch:

- **On:** put a gate file (`.kmz`) in the Gates folder, open the same file in ArcGIS Earth so you can see the rings, and restart EarthStick.
- **Off:** move the file out of the Gates folder and restart EarthStick. With an empty or missing Gates folder, EarthStick flies exactly as 1.2.
- After adding or removing a gate file, always **restart EarthStick** - it only reads the folder at startup.

Several gate files can be used at once. A gate's partner is looked up in its own file first, so two files may reuse names such as ATL or JAX.

One-click start (1.3.1)

Start ArcGIS Earth and EarthStick with one click from the taskbar.

1. In the EarthStick folder, double-click `Make_Taskbar_Shortcut.bat` once. It looks for ArcGIS Earth (the first time can take a minute), remembers where it is in `ArcGIS_Earth_path.txt`, and puts an **ArcGIS Earth Flight** shortcut with the ArcGIS Earth icon on your desktop.
2. Right-click the shortcut > **Show more options** > **Pin to taskbar**. You can then delete the desktop copy.

Clicking it starts ArcGIS Earth (unless it is already open), then EarthStick. EarthStick waits until ArcGIS Earth is ready, so the order takes care of itself. Double-clicking `Fly_ArcGIS_Earth.bat` does the same.

If it says it cannot find ArcGIS Earth: right-click your normal ArcGIS Earth shortcut > **Properties**, copy the **Target** (it ends in `.exe`), paste it as the only line of a text file named `ArcGIS_Earth_path.txt` in the EarthStick folder, and run it again.

Making your own gates

Gate files are ordinary KMZ files with the ring drawn in gold and the gate details stored inside. For now they are made with the `make_gate_kmz.py` script in the ArcGIS Earth Unlocked toolbox (for advanced users); a simpler way to make gates is planned. A gate can lead to a partner gate (a two-way route) or to a fixed spot with no way back (a one-way "trap door" - fly home the long way).

Using the mouse while EarthStick is running

When the joystick is idle, EarthStick periodically re-reads the ArcGIS Earth camera. You can reposition the map with normal ArcGIS Earth controls, then return to the joystick. When movement begins, EarthStick synchronizes from the current camera state.

Automatic recovery

ArcGIS Earth API interruption

If the Automation API disappears, EarthStick stops writing camera movement and waits. It does not keep advancing a hidden local camera. When the API returns, EarthStick reads the live camera again before flight resumes.

Joystick disconnect

If the sidestick is unplugged, EarthStick remains running and waits for it to return. Reconnect the joystick. EarthStick re-detects it, even if Windows assigns a different joystick ID, then reads the live ArcGIS Earth camera before movement resumes.

Stop EarthStick

Press `Ctrl+C` in the EarthStick console or close the console window. After `Ctrl+C` the console shows `Stopped.` and waits for a key press before closing.

Self-test

From a command prompt in the EarthStick folder:

```
py -3 EarthStick.py --selftest
```

(If the `py` launcher is not installed, use `python` instead of `py -3`.) The self-test needs no joystick and no ArcGIS Earth.

A successful run prints:

```
EarthStick self-test PASS
```

Important scope note

EarthStick moves the ArcGIS Earth **map camera**. It is not an aircraft controller or certified navigation system. Always validate the underlying map, imagery, GIS layers, coordinates, and offline packages for the intended use.