

JDUN | 15m ORB | Combined

TradingView Pine Script v6 indicator — complete technical documentation

A 15-minute opening-range breakout indicator built from Jaydon's two webinars, with the GD context layer merged on top. It marks the session levels, waits out the opening range, validates the candle that breaks it, and enters the pullback into the fib golden pocket with R-multiple targets and a hard daily trade cap.

This document describes exactly what the script does, how each stage works, what fires when, and every input — written against the code as it actually stands, not against intent.

File	JDUN-ORB-Combined.pine
Language	Pine Script v6 (//@version=6), overlay indicator
Repository	JinxedAgain/AI_Claude, branch claude/15m-orb-jinxed-indicator-egbxsn
Intended chart	5-minute (enforced by the Signal Timeframe lock)
Opening range	15 minutes, independent of chart timeframe
Inputs	67, across 10 groups
Alert conditions	10 (8 trade, 2 context-only)
Order routing	Alert names match the prior script, so PickMyTrade webhooks carry over

This is an indicator, not a strategy

It draws levels and fires `alertcondition()` signals. It places no orders itself and has no TradingView strategy tester behind it. The backtest table is the script's own bar-close simulation — see "Backtest table: how R is scored" for exactly what it does and does not model.

1. The method it implements

Every rule below comes from Jaydon's two webinars. The script follows them in his order — this sequence is the spine of the whole indicator, and each stage maps to a named section in the source.

1. Before the open, mark the levels: pre-market high/low, previous day high/low, Asia high/low, VWAP, point of control.
2. Let the first 15 minutes form the opening range. No trades in that window — "9:30 to 9:45 equals no trades. Let the market show you its hand."
3. Wait for a 5-minute candle to CLOSE beyond the range. Never mid-candle.
4. That candle must be a trend-setting candle: full body, minimal wick, rising volume. A big candle on weak volume is an "anomaly" — someone is lying — and is skipped.
5. Draw a fib across that candle. Enter the pullback into the 0.5-0.618 golden pocket, ideally where it stacks with one of the marked levels.
6. If the move is too aggressive to retrace that far, use the two-bar setup instead: a shallower pullback measured across both candles.
7. Stop goes beyond the trend-setting candle. Hard stop, never mental.
8. Trim ~70% at 1R and move the stop to break-even. Rest at 1.5R and 2R.
9. Two trades a day maximum. Two losses and the day is over.
10. Trade the first 1-2 hours. Flat before the close.

His numbers, as the shipped defaults. Targets are R-multiples off the actual stop distance (1R / 1.5R / 2R), not ATR — that is how he sizes every trade he describes. The alert window is 09:30-15:30, the whole session, though his own guidance favours the first one to two hours. Max stop is 40 points ("40-50 acceptable, 100 too wide"). All three are inputs.

2. Architecture: what came from where

This file is a merge of two earlier scripts. Knowing which half you are looking at matters, because only one of them trades.

The trade engine — from JDUN-ORB.pine

Opening range, trend-setting candle, golden pocket and two-bar entry, R-multiple targets, break-even stop, two-trade daily cap, and the R-denominated backtest table. This is the only thing that opens a position, and it is carried over unchanged.

The context layer — from USE-15m-ORB-Jinxed.pine (its GD merge)

The fast/slow EMA pair, the EMA-cross-on-volume signals, and the alert-window background shading. **None of these open a position. They have no TP and no SL.** The EMA cross has its own two alerts.

Deliberately not carried over

- **The fluxchart state-machine engine** from the Jinxed script (Sensitivity, Dynamic/ATR take-profits, the retest counter). It fires on the same alert names as the JDUN engine — Buy / Sell / Take Profit 1-3 / Stop Loss — so

running both would send two conflicting orders to one webhook. The Jinxed script's own Jay mode was already a reimplementaion of the rules the JDUN engine implements here, so no behaviour was lost.

- **The volume profile.** That was the blue box drawn beside the opening range. It is gone; every level on the chart is now a line.

3. The trade lifecycle, stage by stage

What follows is the actual order of operations on every bar.

Stage 0 — Session levels (continuous)

Six reference prices are tracked and rebuilt each day. They gate nothing by default, but they feed the optional stacked-level filter.

Level	How it is built	Default window
PM high / low	Running extremes across the pre-market window	04:00-09:30
Previous day high / low	Yesterday's session extremes, frozen on the first bar of the new session	09:30-16:00
Asia high / low	Running extremes across the Asia window (crosses midnight; Pine handles it)	18:00-03:00
VWAP	<code>ta.vwap(hlc3)</code> — resets automatically each trading day	session
Point of control	Price bucket with the most volume so far today. A running max keeps this O(1) per bar instead of rescanning the map.	session, 4-tick buckets
ORB midline	The 50% of the opening range. He calls it "the hidden gem".	derived

All session windows are read in one timezone, set by **Timezone for all session times** (default America/New_York), so the times you type are the times you mean. DST is handled.

Stage 1 — Opening range

On the first bar of the regular session the script stamps the session open, then accumulates the high and low for **Opening range length** minutes (default 15 — three 5-minute candles). When that window closes the range locks and hunting begins. Nothing can arm or trade while the range is still forming.

```
newSession    = inRTH and not inRTH[1]
orbBuilding   = inRTH and (time - sessOpen) < orbMins * 60000
orbMid        = (orbH + orbL) / 2.0
```

Stage 2 — The trend-setting candle (arming)

A setup is armed when a candle CLOSES beyond the locked range AND passes all three quality tests. Fail any one and there is no setup at all — the script keeps waiting.

Test	Rule	Input
Body	Body must be at least 50% of the candle's high-to-low range. His "full body, no or minimal wick".	Minimum body % of range

Test	Rule	Input
Volume	Volume above its 20-bar average AND higher than the previous bar. Rising volume means buyers are bidding aggressively, not merely that there are more of them.	Require rising volume
Anomaly veto	A candle larger than 1.5x ATR on BELOW-average volume is rejected. Size and participation disagree, so the move is a trap.	Reject anomalies

On a valid break the script records the candle's high and low (these become both the stop and the fib anchors), stamps the bar index, and measures the golden pocket:

```

r = high - low
long : zoneHi = high - 0.500 * r    zoneLo = high - 0.618 * r
short: zoneLo = low  + 0.500 * r    zoneHi  = low  + 0.618 * r

```

One setup per excursion — a bug worth knowing about

An armedRun latch allows only ONE arming per trip outside the range. Without it the script re-armed on EVERY bar that stayed beyond the level, pushing setBar forward each time; since the entry requires bar_index > setBar, the pullback test could then never pass and no entry would ever fire in a sustained trend. That was the "only one signal in the whole backtest" symptom. The latch clears when price closes back inside the range, so a genuine second break later in the day can still arm afresh.

Stage 3 — The entry zone

Three entry models are selectable. Golden Pocket is the default and his primary method.

Entry model	What triggers it
Golden Pocket	Price pulls back into the 0.5-0.618 fib of the trend-setting candle.
Level Retest	The simpler first-webinar version: price comes back and touches the broken range level itself.
Either	Whichever happens first.

The two-bar fallback

For aggressive trends that never retrace to 0.5. If the bar immediately after the trend-setting candle extends the move in the same direction on passing volume, the zone is re-measured across BOTH candles and made shallower — 0.236 to 0.382 by default. In his words: "the only reason you trade a two bar is in the cases of aggressive trends where you dont retest the 50%."

Why the entry cannot fire on the arming candle

The zone is measured INSIDE the trend-setting candle, so the entry test requires bar_index > setBar. Without that guard the entry would trigger on the arming candle itself instead of waiting for the pullback he actually trades.

Expiry

A setup is discarded when it goes stale (**Setup valid for N bars**, default 15) or is invalidated by price closing back inside the range, or when the session ends.

Stage 4 — Execution timing: what waits for a candle and what does not

This is the part most worth understanding, because it determines when alerts reach your broker.

Event	Timing	Why
Arming	Confirmed bar close, always	His non-negotiable rule. A wick through the range is not a break.
Entry (Golden Pocket / two-bar)	Real time, on touch (default)	The zone test reads the bar's RUNNING high and low, which only widen as the candle forms. Once touched it is true and stays true through the close, so firing early cannot repaint — the bar-close answer is identical, the alert just arrives sooner.
Entry (Level Retest)	Confirmed bar close, always	It tests close > orbH, and the close moves every tick. Firing early WOULD repaint: an alert would go out for a trade the script then discards.
TP1 / TP2 / TP3 / SL	Real time, on touch	An exit should not wait for a candle to finish.
Close All / Flatten	Real time	A safety net; it fires after hours by design.

Set the TradingView alert to "Once Per Bar", not "Once Per Bar Close"

A TradingView alert permanently captures the trigger frequency chosen when it was created. On "Once Per Bar Close" the platform holds every one of these signals until the candle finishes, and none of the real-time behaviour above applies. This affects the TP and SL alerts too.

The entry bar and same-bar targets

On any bar after the entry, the full high and low are the right thing to test. On the entry bar itself the high and low cover ground price crossed BEFORE the fill, so testing them would credit moves the trade never had. The script therefore tests close on the entry bar — which in real time IS the live price, tick by tick, and on a historical bar equals the entry price, making it inert. So a target reached seconds after a real-time fill is reported at once, and nothing before the fill can ever be credited.

Stage 5 — Risk and targets

The stop is placed beyond the trend-setting candle, padded by **Stop padding** (default 2 ticks). Risk is the distance from the live price to that stop, and every target is a multiple of it.

```
candSL = long ? tcLo - stopPad*tick : tcHi + stopPad*tick
riskPts = |entry - candSL|
TP1 = entry +/- 1.0 * riskPts      TP2 = entry +/- 1.5 * riskPts
TP3 = entry +/- 2.0 * riskPts      (all three are inputs)
```

- **Max stop distance** (default 40 points) rejects the setup outright if the stop is wider. His guidance: 20-30 points on NQ is ideal, 40-50 acceptable, 100 far too wide. Set 0 to disable.
- **TP2 = high/low of day** is an optional alternative target — his stated primary target is a new high or low of day. It never sits closer than 1R, because a HOD already behind price is not a target.
- **Require a stacked key level** is his highest-probability condition: the fib zone lining up with a marked level. When on, the entry must also be within **Stacked level distance** of PM H/L, previous day H/L, Asia H/L, VWAP, POC or the ORB midline. It is a strict filter — expect noticeably fewer trades. Off by default, but always reported on the dashboard.

Stage 6 — Exits, and the break-even step

TP1, TP2 and TP3 are each tested independently against their own price, so one candle running through all three fires all three. **Stop to break-even after TP1** is on by default, and it is the single most misread behaviour in the script:

```
if not tp1Done and hiTest >= tp1Px - buf
    tp1Hit := true
    tp1Done := true
    if beAfterTP1
        slPx := entryPx           // the live stop is now your entry
```

The break-even stop only watches price AFTER it moved

The candle that reaches TP1 has, on a long, run up from below the entry. Testing the freshly-raised stop against that whole candle matches its own low, so a stop fired on every TP1 — reading downstream as take profit followed instantly by flatten. The stop is now judged only on price seen since the move: tick by tick in real time, and on a historical bar only if the candle CLOSED back through break-even, which is a genuine reversal.

After TP1, a stop-out is a break-even exit, not a 1R loss

The moment TP1 lands the live stop becomes your entry price. If price then comes back, the Stop Loss alert fires at entry — you keep what you trimmed at TP1 and give back nothing. On the chart the dashed There is ONE stop line and it moves with the stop. At TP1 it relocates, turns orange and is renamed, so what is drawn is always the stop that is actually live, and a stop-out after that lands on it marked BE rather than SL. Where it lands is set by Break-even offset: at 0 it sits exactly on the entry, and the entry line is dropped because the two would otherwise render as one line of alternating blue and orange dashes. Above 0 the stop sits that share of R into profit, the mark reads BE+, and both lines are kept because they no longer coincide.

Flatten

Anything still open when the **Flatten after** window ends — or when the session ends — gets a single Close All alert, once per day. The end time is your hard flat-by deadline; leave the start time early, only the end matters.

Stage 7 — Daily limits

Two hard caps, both reset at each new session: **Max trades per day** (default 2) and **Max losses per day** (default 2). A loss counts only when the trade is stopped out without ever reaching TP1. "You are a day trader, not a trade-every-day trader." — "Two full-size losses and I am done. I do not care if the next setup is the best one of the year."

Entries are additionally gated by the **Alert window** (default 09:30-15:30) and by the Signal Timeframe lock.

4. Alerts and order routing

Ten alert conditions populate TradingView's Condition dropdown. The first eight are the trade engine. The last two are the EMA-cross heads-up and are **not** trade signals — do not point an order webhook at them unless you mean to.

Alert name	Fires when	Gated by
Buy / Sell	Either direction enters	window + timeframe
Buy	Long entry	window + timeframe
Sell	Short entry	window + timeframe
Take Profit 1	Price touches TP1	timeframe
Take Profit 2	Price touches TP2 (after TP1)	timeframe
Take Profit 3	Price touches TP3 (after TP2)	timeframe
Stop Loss	The live stop is hit and it is still the ORIGINAL stop — a real loss	timeframe
Break Even	The live stop is hit after TP1 moved it — a break-even or BE+ exit	timeframe
Stop Loss / Break Even	Either of the two above. For a single flatten webhook — do not also use the separate pair, or every stop sends two orders	timeframe
Close All / Flatten	Position still open past the flatten deadline	timeframe
EMA Cross Buy (volume)	Context only — no position, no TP, no SL	session + timeframe
EMA Cross Sell (volume)	Context only — no position, no TP, no SL	session + timeframe

Prices in the alert message

Five hidden plots carry the live levels into the alert payload. Reference them in the message body with TradingView placeholder syntax:

```
{{plot("Entry")}}    {{plot("SL")}}  
{{plot("TP 1")}}    {{plot("TP 2")}}    {{plot("TP 3")}}
```

They are `display.data_window` plots — visible in the Data Window, invisible on the chart.

The Signal Timeframe lock

A TradingView alert permanently captures the chart timeframe it was created on. **Lock alerts to signal timeframe** (on by default) stops an alert accidentally created on the wrong chart from ever firing. The default Signal Timeframe is 5 minutes — he executes on the 5-minute and refuses to go lower. The dashboard's last-but-one row reads WRONG TF in red whenever the chart does not match.

The TP/SL buffer

TP/SL buffer (default 1 tick) fires exit alerts that many ticks early, so a market order fills near the intended price rather than chasing through it.

5. Chart anatomy

Everything the script can draw, and what each element means.

Level lines

Every reference level is a full line running from the open of a PREVIOUS session to the live candle, with its name and price at the right-hand end so nothing needs scrolling. How far left it reaches is **Extend levels back (sessions)** — 1 (default) starts the line at yesterday's open, 0 starts it at today's. Width and style are shared across the whole set by **Level line width** (default 1) and **Level line style**; at width 1 Dotted reads lighter still than solid.

Drawing	Colour	Meaning
ORB high / low	green / red, solid	The locked opening range. Own width input.
ORB Mid	grey	The 50% of the range.
PM High / PM Low	orange	Pre-market extremes.
Prev Day High / Low	blue	Yesterday's session extremes.
Asia High / Low	purple	Overnight extremes.
POC	red	Session point of control.
VWAP	blue, continuous	Plotted across all bars, not a stub — it moves, so a stub would be meaningless. Label only.
Golden pocket pair	yellow	The 0.5 and 0.618 of the trend-setting candle. Visible only while a setup is armed; gone the moment the entry fires or the setup expires.
EMA fast / slow	teal / grey	Context layer. Gates nothing in the trade engine.

Trade lines

On every entry, five horizontal lines are drawn at Entry, SL, TP1, TP2 and TP3. They extend rightward for the rest of that trading day and then freeze, so past trades keep their levels — you can see every target including the ones price never reached. Each carries its name (ENTRY, SL, TP 1, TP 2, TP 3) at its right-hand end. Old sets are never deleted; Pine drops the oldest once the drawing budget is reached, which keeps roughly the last hundred trades visible.

Markers

Marker	Where	Meaning
BUY flag	below bar	Long entry.
SELL flag	above bar	Short entry.
BUY X / SELL X	above / below bar	The redundant entry mark — the same entry drawn a second time on the opposite side of the bar. Two independent draws off one signal, so if the flag is hidden behind another drawing or clipped at the pane edge, the X still shows.

Marker	Where	Meaning
TP 1 / TP 2 / TP 3 X	on the target price	That target was reached; the mark sits on the level it hit. When two or three land on ONE candle their levels are only 0.5R apart, so separate marks and names just cluster — the group gets ONE X past the end of the wick and a single stacked block of names above it, TP 1 nearest the candle and TP 2, TP 3 above it (below, for a short), in the order price passed through them. Every target still fires its own alert on touch.
SL X	on the stop price	Stopped out for a real loss, at the original stop.
BE X	on the stop price	Stopped out at break-even, after TP1 had already pulled the stop up. Drawn in the orange of the break-even line it sits on, so the chart never calls a scratch a loss.
BE+ X	on the stop price	The same, but with a break-even offset set, so the stop sat in profit and that exit banked a gain rather than scratching.
CLOSE X	at the exit price	Forced flatten.
EMA+ / EMA-	below / above bar	EMA cross on above-average volume. Context only.

Exit marks sit on the level they hit

They are plotted with `location.absolute`, at the value of the price they fired on, rather than floating above or below the candle. An exit mark therefore lands on its own line. Entry flags are the exception and still sit beside the bar, since an entry has no level of its own.

6. The two tables

Dashboard (live state)

Row	Shows
State	RANGE FORMING -> WAITING -> ARMED LONG/SHORT -> LONG/SHORT
Trades / Losses	Today's count against both daily caps; turns orange when either is hit
Setup	Golden pocket, or Two-bar when the fallback re-measured the zone
Entry zone	The live zone bounds
Stacked level	YES when price is sitting on a marked level — reported even when the filter is off
Risk if taken	Stop distance in points for the armed setup; reads TOO WIDE in red past the max
Entry / SL	The open trade's entry and its CURRENT stop (so it shows break-even after TP1)
Signal TF	OK, or WRONG TF in red
EMA trend	UP / DOWN / flat from the context layer

Backtest table: how R is scored

A bar-close simulation of this engine over the loaded chart, denominated in R. Rows: Signals, Closed, Wins, Losses, Win rate, Profit factor, Total R, Avg R per trade, and TP1/TP2/TP3 hit counts.

The scoring is position-weighted, which matters. A trade that trimmed at TP1 and then stopped at break-even is NOT a zero — the trimmed portion was banked, and scoring it flat would understate results badly:

```
stopped with nothing taken off    -1.0
otherwise, per portion:
  the trim at TP1                  trimPct * tp1R
  half the rest, if TP2 reached    ((1-trimPct)*0.5) * tp2R
  half the rest, if TP3 reached    ((1-trimPct)*0.5) * tp3R
anything still open at the end came back to break-even and adds nothing
```

Trim fraction at TP1 (default 0.7) drives that weighting. He states 60-75%. It affects the table only — it changes no alert and no signal. Each portion only earns its multiple if its own target was actually reached, so a trade that took TP1 and TP2 and then came back is scored on the TP3 portion returning flat, not on the whole remainder exiting at TP2.

What the backtest does not model

It is not a record of live fills. If a TP and the SL are both touched inside one candle it credits the TP, because intrabar order is not knowable from OHLC. It assumes fills at the exact level with no slippage and no commission. It does not include the EMA cross signals, which are not trades. Treat it as a shape check on the rules, not as expected P&L.

7. Full input reference

67 inputs across 10 groups. Defaults shown are as shipped.

Session & Opening Range

Setting	Default	What it does
Timezone for all session times	America/New_York	Every session field in the script is read in this timezone. Handles DST.
Regular session	0930-1600	The trading session that defines the day.
Pre-market window	0400-0930	He marks pre-market from 4:00am, not 8:00 — he calls this out explicitly.
Asia session	1800-0300	Crosses midnight, which Pine handles.
Opening range length (minutes)	15	The first three 5-minute candles. Nothing trades until this closes.

Entry

Setting	Default	What it does
Entry model	Golden Pocket	Golden Pocket / Level Retest / Either.
Two-bar setup fallback	true	Shallower zone across both candles for aggressive trends.
Two-bar zone start / end	0.236 / 0.382	The shallower retracement band used by the fallback.
Fire entries in real time (on touch)	true	Entry alert fires the instant price enters the zone. Off = wait for bar close.
Setup valid for N bars	15	How long the armed zone stays live before being discarded.
Require a stacked key level	false	Entry must also sit on a marked level. Strict — far fewer trades.
Stacked level distance (points)	10.0	How close counts as stacked.

Trend-Setting Candle

Setting	Default	What it does
Minimum body % of range	50	A wick more than half the candle invalidates it.
Require rising volume	true	Above the average AND above the previous bar.
Volume average length	20	Bars in the volume average.
Reject anomalies	true	Large candle on below-average volume is a trap.
Anomaly size (x ATR)	1.5	How large before the anomaly test applies.

Risk & Targets

Setting	Default	What it does
TP1 / TP2 / TP3 (R)	1.0 / 1.5 / 2.0	Targets as multiples of the actual stop distance.
Trim fraction at TP1	0.7	Backtest weighting only. He states 60-75%.
TP2 = high/low of day instead	false	Use a new HOD/LOD as TP2, never closer than 1R.
Stop to break-even after TP1	true	The live stop becomes your entry once TP1 lands.
Break-even offset (% of R)	10.0	How far PAST break-even the stop goes. 0 is a true break-even. Above that it moves into profit by that share of the trade's own risk, so it scales with the stop instead of being a fixed number of points.
Stop padding (ticks)	2	How far beyond the trend-setting candle the stop sits.
Max stop distance (points)	40.0	Reject the setup if the stop is wider. 0 disables.

Daily Limits

Setting	Default	What it does
Max trades per day	2	His cap. "One good trade a day, two max."
Max losses per day	2	Circuit breaker. A loss = stopped out without reaching TP1.

Alerts

Setting	Default	What it does
Alert window	0930-1530	The hours an entry may fire. The default runs the whole session; his own guidance favours the first one to two hours.
TP/SL buffer (ticks)	1	Fire exits this many ticks early so the order fills near the level.
Shade the alert window	false	Tints the background while the window is open.
Lock alerts to signal timeframe	true	Stops an alert made on the wrong chart from ever firing.
Signal timeframe (minutes)	5	He executes on the 5-minute and refuses to go lower.
Flatten after	0930-1530	End time is your hard flat-by deadline.

Levels

Setting	Default	What it does
PM / Prev day / Asia / VWAP / POC	all true	Which reference levels to draw.
POC bucket size (ticks)	4	How coarsely prices are grouped when finding the POC.
ORB midline	true	The 50% of the range — "the hidden gem".

Setting	Default	What it does
Level line width	1	Shared by every reference level. 1 is the thinnest Pine draws.
Level line style	Solid	Solid / Dashed / Dotted. Dotted reads lighter than a width-1 solid.
Extend levels back (sessions)	1	How far LEFT every level reaches. 1 = yesterday's open.
Label every level	true	Name and price at the right-hand end.

Visuals

Setting	Default	What it does
Opening range lines	true	The green/red range lines, with their own width input.
Entry zone while live	true	The yellow golden-pocket pair while a setup is armed.
Entry / SL / TP lines on every trade	true	Five lines per trade, kept for past trades too.
Redundant entry X marker	true	Second entry mark on the opposite side of the bar.
Name each trade line at its right end	true	ENTRY / SL / TP 1-3 at the end of each dashed line.
Target stack clearance (x ATR)	0.35	How far past the end of the wick the stacked target names sit when one candle takes more than one target. In ATR, so the gap looks the same on any symbol.
Label the live trade levels	true	TP/SL with prices at the right edge while a trade is open.
Dashboard / Backtest table	true	The two panels, each with a position dropdown.

EMA Cross + Volume (context only)

Setting	Default	What it does
Enable EMA cross signals	true	EMA+ / EMA- labels and their two alerts. Not trades.
Fast / Slow EMA	10 / 20	10/20, 9/21 and 8/20 all behave similarly.
Cross which EMA	Fast	Both = close through the fast AND already the right side of the slow.
Volume must exceed avg by	1.2	120% of the average. Raise it for fewer signals.
Skip first N bars of session	4	4 bars on a 5-min chart skips the noisy first 20 minutes.
Only during alert window	false	Off means crosses fire all session.

8. Limitations and things to watch

- **It is an indicator, not a strategy.** No orders are placed by the script and there is no TradingView strategy tester behind it. Everything downstream depends on your alert and webhook configuration.
- **"Once Per Bar" is mandatory** for the real-time entry and exit behaviour. On "Once Per Bar Close" every signal waits for the candle.
- **Intrabar order is unknowable.** If a TP and the SL are both touched inside one candle, the backtest credits the TP. Live, whichever your broker fills first is what you get.
- **No slippage or commission** anywhere in the R accounting.
- **Level Retest cannot go real time** by construction — it tests the close.
- **The daily-loss circuit breaker counts only full losses.** A trade that reached TP1 and then stopped at break-even is not a loss, so it does not count toward the cap.
- **Drawing budget.** Lines and labels are capped at 500 each. Trade lines are never deleted, so on a long history Pine drops the oldest — roughly the last hundred trades stay visible.
- **The chart must be finer than the opening range.** Run it on 5-minute as intended.

9. Version history

Change	What it did
Combined build	Merged the JDUN trade engine with the GD context layer. Dropped the second trade engine and the volume-profile box.
Level extension	Every reference level became a full line from a previous session's open to the live candle, replacing the 3-bar stub.
Real-time entry	Entries fire on touch rather than at bar close, with Level Retest excluded. Entry-bar TP/SL now measured from the live price.
Entry redundancy	Second X marker per entry. Fixed a bug where SL and TP3 marks never drew, because pos was zeroed by the close block before plotshape evaluated it.
Trade-line names	ENTRY / SL / TP 1-3 at the right-hand end of each dashed line.
Thinner levels	Width and style inputs for the reference levels and the ORB lines.
Break-even stop drawn	The SL line splits into a red "initial" segment and an orange "BE" segment at TP1, so a break-even exit lands on a visible line.

Generated from JDUN-ORB-Combined.pine as committed on branch claude/15m-orb-jinxed-indicator-egbxsn. Where this document and the source disagree, the source is correct.