

Zurich ServiceNow AI Platform Capabilities

Last updated: January 16, 2026

Some examples and graphics depicted herein are provided for illustration only. No real association or connection to ServiceNow products or services is intended or should be inferred.

This PDF was created from content on docs.servicenow.com. The web site is updated frequently. For the most current ServiceNow product documentation, go to docs.servicenow.com.

Company Headquarters

2225 Lawson Lane
Santa Clara, CA 95054
United States
(408)501-8550

Configuring Unified Map — Admin settings

Administrators can configure general Unified Map settings to control the initial content and appearance of maps for all users in a workspace.

Activating Unified Map

To activate Unified Map, set up the CMDB Workspace ServiceNow Store app and then enable the `sn_sm_scoped_app.sa.unified_map.enabled` system property.

For more information, see [Set up CMDB Workspace](#).

Unified Map settings that admins can configure

These workspace-specific configuration settings affect all users of the CMDB Unified Map page. The settings do not affect other copies of the Unified Map template.

- [Create or manage a shared preset](#)
- [Configure how many nodes can appear on a map](#)
- [Configure the default or maximum number of levels on maps](#)
- [Configure endpoint de-duplication on maps](#)
- [Configure CIs to appear based on life cycle stage value](#)
- [Configure how to display related items on the map](#)
- [Configure which attributes to display in the Attributes panel](#)
- [Configure display of connections to a referenced class](#)
- [Create a class profile of visible layers for classes](#)
- [Create or manage a shared preset](#)

How configuration settings for Unified Map are stored

See [How configuration settings for Unified Map are stored](#).

Unified Map settings that non-admin users can configure

Non-admin users can customize some aspects of their personal experience with Unified Map, but can't configure instance-wide workspace-specific settings. Non-admin users can control which elements appear on the map, isolate and analyze relationships between CIs, and simplify the map to isolate issues.

For more information, see [Controlling Unified Map contents and appearance](#).

- [Create or manage a shared preset](#)

Admins can save a set of Unified Map map filter settings (layer, CI class, relationship type, and other CI attribute settings) as a shared preset that any user can apply to their map view.

- [Configure how many nodes can appear on a map](#)

Configure the maximum number of nodes that can be loaded when a map in this workspace opens. These are general settings that only sn_cmdb_admin can configure.

- [Configure the default or maximum number of levels on maps](#)

Configure the default or maximum number of levels on maps. These are general settings that only sn_cmdb_admin can configure.

- [Configure endpoint de-duplication on maps](#)

Configure how duplicate edges are displayed on maps. These are general settings that only sn_cmdb_admin can configure.

- [Configure CIs to appear based on life cycle stage value](#)

By default, only CIs for which Life cycle stage is **Operational** or empty appear on maps. You can configure the map to display CIs with other Life cycle stage values. These are general settings that only sn_cmdb_admin can configure.

- [Configure how to display related items on the map](#)

Add related items categories, specify which information should appear on cards on the Unified Map **Related items** panel, and specify how

related items (events) appear on the timeline and on badges. These are general settings that only `sn_cmdb_admin` can configure.

- [Configure which attributes to display in the Attributes panel](#)

Each class has a unique set of extended attributes that appear in the bottom section of the **Attributes** panel for a CI. For any class, you can specify which extended attributes should be displayed. These are general settings that only `sn_cmdb_admin` can configure.

- [Configure display of connections to a referenced class](#)

Configure how to display connections to a referenced class and from a referencing class on Unified Map. A reference connects two CIs from differing classes that aren't connected by a relationship. These are general settings that only `sn_cmdb_admin` can configure.

- [Create a class profile of visible layers for classes](#)

Configure a class profile that specifies which layers should appear for a particular class: application, service instance, business, or infrastructure. For example, you can configure that the mapped application service (service instance) `[cmdb_ci_service_discovered]` class should display only Service Mapping data and not infrastructure elements.

- [How configuration settings for Unified Map are stored](#)

General configuration settings that control Unified Map are collected in a configuration identifier. A configuration identifier is a set of properties and table-driven configurations that specify the appearance and content of an instance of a UX application. The CMDB Workspace UX application contains Unified Map.

Related concepts

- [Configuration identifiers framework](#)
- [How configuration settings for Unified Map are stored](#)

Create or manage a shared preset

Admins can save a set of Unified Map map filter settings (layer, CI class, relationship type, and other CI attribute settings) as a shared preset that any user can apply to their map view.

Before you begin

Role required: sn_cmdb_config_admin

About this task

Follow this procedure to save specified filter settings as a shared preset. The workspace-specific filter criteria in a shared preset are available for all users of the current CMDB Unified Map page. Shared presets defined in one workspace are not available in other workspaces.

Configuration settings for shared presets are saved in the **Unified Map shared presets** profile in the configuration identifier that is applied to the workspace.

- When a user applies a shared preset or a user preset, all filter settings are overridden. Filter attributes from a shared preset or a user preset that do not apply to the current map are listed in the **Unused filter attributes** section of the filter panel. The order of filter-setting precedence from the various sources is as follows:
 - 1: user presets
 - 2: shared presets
 - 3: shared presets that are defined in a **Unified Map shared presets** profile
 - 4: class profile (Class profiles contain only layer settings and are defined in the **Node Map Profiles** related list.)
- You can include a shared preset in a node map profile. Layer settings in the shared preset will override the layer settings defined in the class profile.
- A shared preset defined in a profile will be applied when the map opens. If the user has explicitly defined a shared preset or a user preset, then the preset takes precedence as outlined above.

- An individual user can apply a shared preset and then save it as a user preset. For more information, see [Create or manage a user preset](#).
- Unused filter criteria in the current filter are saved with a preset.

Procedure

1. While working in a map, select the Map filter icon  and then select or clear criteria in any filter category.
Only attributes of elements currently on the map are listed as filter criteria. Attributes that do not apply to the current elements are listed in the **Unused filter attributes** list.
2. Select the Manage presets icon , and in the Manage shared presets list, select **Create shared preset**.
3. Enter a preset name and then select **Save**.
4. Close the Map filter panel.

Result

The new shared preset is listed in the **Unified map shared presets** related list on the Configuration Identifier form. In addition, shared presets used in a map profile are listed in the **Node Map Profiles** related list. For more information, see [How configuration settings for Unified Map are stored](#)

What to do next

To apply a preset:

1. While working in a map, select the open filter panel icon 
2. Select the View preset list icon  and then select the preset.

To update a preset or save an updated version as a new preset:

1. While working in a map, select the open filter panel icon 

2. Apply the preset that you want to update and then make the desired changes.
3. Select the Manage presets icon  and then select **Update preset** or **Update shared preset**.
4. Select one of the following actions:
 - Select **Update preset** to update the current preset with the current filter settings.
 - Select **Save as new preset** and then enter a new name.
5. Select **Save**.

To delete a preset:

1. While working in a map, select the open filter panel icon .
2. Apply the preset that you want to delete.
3. Select the Manage presets icon  and then select **Delete preset** or **Delete shared preset**.
4. Select **Yes**.

To apply the home CI's default filter settings

Select **Reset filter**.

Related tasks

- [Use filters to specify which nodes should appear on a map](#)
- [Create or manage a user preset](#)
- [Create a class profile of visible layers for classes](#)

Configure how many nodes can appear on a map

Configure the maximum number of nodes that can be loaded when a map in this workspace opens. These are general settings that only `sn_cmdb_admin` can configure.

Before you begin

Set the application scope in your instance to **CMDB Workspace**.

Role required: `sn_cmdb_admin`

About this task

Admins can set the maximum node count using the `unifiedmap.map_search.max_nodes` property in the workspace-specific `[sn_cmdb_ws_config_property]` table.

These workspace-specific configuration settings affect all users of the CMDB Unified Map page. The settings do not affect other copies of the Unified Map template.

Procedure

1. Navigate to **All** and then, in the filter box in the main navigation bar, enter `sn_cmdb_ws_config_property.list`.
2. Select the `unifiedmap.map_search.max_nodes` property.
3. Select **New** or select the configuration identifier to update and then fill in the form.

Workspace Config Property table

Settings that configure the maximum number of nodes that can appear on a map.

Field	Description
Config identifier	Unique name of the configuration identifier that

Field	Description
	specifies the settings for the current workspace. Note: The base system includes a configuration identifier named Default that specifies the default settings for Unified Map.
Name	The name of the property that you are updating: unifiedmap.map_search.max_nodes.
Value	Maximum count of nodes that are loaded when a map in this workspace opens.
UX application	The top-level UX Application ID to which this configuration applies. This is the application ID of your workspace. This value is referenced from the record associated with the Config identifier setting.

4. Select **Submit** or **Update**.

The updated settings appear in the appropriate related list on the Configuration identifier form, as described in [Configuring Unified Map — Admin settings](#).

Configure the default or maximum number of levels on maps

Configure the default or maximum number of levels on maps. These are general settings that only `sn_cmdb_admin` can configure.

Before you begin

Set the application scope in your instance to **CMDB Workspace**.

Role required: `sn_cmdb_admin`

About this task

Admins can set default and maximum levels using the `unifiedmap.map_search_filter.default_levels` or `unifiedmap.map_search_filter.max_levels` property in the workspace-specific `[sn_cmdb_ws_config_property]` table.

These workspace-specific configuration settings affect all users of the CMDB Unified Map page. The settings do not affect other copies of the Unified Map template. Non-admin users can customize some aspects of their personal experience with Unified Map, but can't configure instance-wide workspace-specific settings.

Procedure

1. Navigate to **All** and then, in the filter box in the main navigation bar, enter `sn_cmdb_ws_config_property.list`.
2. Select the `unifiedmap.map_search_filter.default_levels` or `unifiedmap.map_search_filter.max_levels` property, as needed.
3. Select **New** or select the configuration identifier to update and then fill in the form.

Workspace Config Property table

Settings that configure the maximum number of nodes that can appear on a map.

Field	Description
Config identifier	Unique name of the configuration identifier that specifies the settings for the current workspace. Note: The base system includes a configuration identifier named Default that specifies the default settings for Unified Map.
Name	The name of the property that you are updating: unifiedmap.map_search.max_nodes.
Value	Maximum count of nodes that are loaded when a map in this workspace opens.
UX application	The top-level UX Application ID to which this configuration applies. This is the application ID of your workspace. This value is referenced from the record associated with the Config identifier setting.

4. Select **Submit** or **Update**.

The updated settings appear in the appropriate related list on the Configuration identifier form, as described in [Configuring Unified Map — Admin settings](#).

Configure endpoint de-duplication on maps

Configure how duplicate edges are displayed on maps. These are general settings that only `sn_cmdb_admin` can configure.

Before you begin

Set the application scope in your instance to **CMDB Workspace**.

Role required: `sn_cmdb_admin`

About this task

These workspace-specific configuration settings affect all users of the CMDB Unified Map page. The settings do not affect other copies of the Unified Map template. Non-admin users can customize some aspects of their personal experience with Unified Map, but can't configure instance-wide workspace-specific settings. Non-admin users can customize some aspects of their personal experience with Unified Map, but can't configure instance-wide workspace-specific settings.

Note: This property setting is typically not altered for Unified Map.

Procedure

1. Navigate to **All** and then, in the filter box in the main navigation bar, enter `sn_cmdb_ws_config_property.list`.
2. Select the `unifiedmap.map_search_filter.endpoint_deduplication_fields` property.
3. Select **New** or select the configuration identifier to update and then fill in the form.

Workspace Config Property table

Settings that configure endpoint de-duplication.

Field	Description
Config identifier	Unique name of the configuration identifier that specifies the settings for the current workspace. Note: The base system includes a configuration identifier named Default that specifies the default settings for Unified Map.
Name	The name of the property that you are updating: unifiedmap.map_search_filter.endpoint_deduplication_fields.
Value	The default value of <code>sourceId,targetId,_label,endpoint_s</code> means: Collapse the edges (show only one connection between edges on the map) whenever multiple endpoints between source CI and target CI result in the same labeled edges. Note: This setting is typically not changed for Unified Map.
UX application	The top-level UX Application ID to which this configuration applies. This is the application ID of your workspace. This value

Field	Description
	is referenced from the record associated with the Config identifier setting.

4. Select **Submit** or **Update**.

The updated settings appear in the appropriate related list on the Configuration identifier form, as described in [Configuring Unified Map — Admin settings](#).

Configure CIs to appear based on life cycle stage value

By default, only CIs for which Life cycle stage is **Operational** or empty appear on maps. You can configure the map to display CIs with other Life cycle stage values. These are general settings that only `sn_cmdb_admin` can configure.

Before you begin

Set the application scope in your instance to **CMDB Workspace**.

Role required: `sn_cmdb_admin`

About this task

- By default, non-operational CIs are filtered out and do not appear on maps.
- Search results don't include CIs that are filtered out based on operational state.
- The **Open Map** button (for viewing details) on the CI form isn't available for CIs that are filtered out based on operational state.

These workspace-specific configuration settings affect all users of the CMDB Unified Map page. The settings do not affect other copies of the Unified Map template. Non-admin users can customize some aspects of their personal experience with Unified Map, but can't configure instance-wide workspace-specific settings.

Procedure

1. Navigate to **All** and then, in the **Filter** box in the main navigation bar, enter `sn_cmdb_ws_operational_lifecycle_for_unified_map.list` to open the Operational life cycle modes table.
2. Select the list of selected live cycle stage values.

For Unified Map, the default list of selected live cycle stage values is named **CMDB Workspace Unified Map View**.

- a. Unlock the **Life cycle list** field and then select the Edit multiple



- b. In the Edit Members pop-up, move the life cycle stage values for CIs that should appear on maps into the **Selected life cycle stages** list and then select **Save**.
- c. On the record form, select **Update** or **Save**.
 - The updated settings appear in the appropriate related list on the Configuration identifier form, as described in [Configuring Unified Map — Admin settings](#). The updated list of life cycle stage values is added to the **CMDB Workspace Unified Map View** life cycle mode on the **Operational life cycle modes** related list for the affected configuration identifier.
 - You can also perform this operation from the **Operational life cycle modes** related list.

Configure how to display related items on the map

Add related items categories, specify which information should appear on cards on the Unified Map **Related items** panel, and specify how related items (events) appear on the timeline and on badges. These are general settings that only `sn_cmdb_admin` can configure.

Before you begin

Set the application scope in your instance to **CMDB Workspace**.

Role required: sn_cmdb_admin

About this task

These workspace-specific configuration settings affect all users of the CMDb Unified Map page. The settings do not affect other copies of the Unified Map template. Configuration settings that non-admin users can specify are described in [Configure the Related items panel](#).

Related items are grouped by category in the **Related items** panel. Related items also appear for CI badges on the map and timeline.

The [sn_cmdb_ws_node_map_related_item] table contains the settings that determine which related items and associated details appear. By default, common categories of related items, such as active incidents and other events for example, are configured to appear. You add or modify records to globally manage related items on maps.

Procedure

1. Navigate to **All** and then, in the search box on the main navigation bar, enter `sn_cmdb_ws_node_map_related_item.list` to open the Node Map Related Item table.
2. Select an existing record or select **New** and then fill in the form.

Node Map Related Item table — general section

Settings that configure how categories appear.

Field	Description
Name	The category label that appears on the Related items panel for a selected CI.
Table	Tables from which records for the category are retrieved.
Order	Order that the category appears within all related items categories.

Field	Description
	The list of related items categories is sorted in ascending order. The category with the smallest order number appears at the top of the list.
Active	Enables the appearance of the related item category.
Reference field	Reference attribute in the specified Table that references the CIs for the category. Typically set to Configuration Item [cmdb_ci] .

3. Select the Related fields and conditions tab and then fill in the settings.

Related fields and conditions tab

Settings that configure how data appears on cards.

Number field	Numeric attribute from the specified table that uniquely identifies each record in the category. This attribute is used in the record link that appears on each card when drilling down the related item category.
Title field	Attribute from the specified table that appears as the title of each card when drilling down the category in the panel.
Fields	Set of attributes from the specified table that appears on each card when drilling down the related item category. For example, when drilling down

	alerts, the set of attributes that appears on each alert card.
Sort fields	Order of appearance of the fields specified in the Fields setting.
Footer field	Attribute from the specified table that appears at the bottom of individual cards when drilling down the related item category, regardless of the sort order specified in the Sort fields setting.
Conditions	Conditions to apply to the specified table that retrieve the set of records for the category.

4. Select the Badge and timeline configuration tab and then fill in the settings.

Badge and timeline configuration tab

Settings that configure badge and timeline operation.

Badge and timeline icon	Icon that appears on CI badges and on the timeline for the specified related item.
Badge and timeline highlight field	Highlight configuration for applying colors to timeline and map icons.
Date field	The date field to position the event on the timeline.
End date field	Optional end date field to use for a range on the timeline.

5. Select **Submit** or **Update**.

The updated settings appear in the appropriate related list on the Configuration identifier form, as described in [Configuring Unified Map — Admin settings](#).

Related tasks

- [View related items for a CI](#)

Related concepts

- [Viewing related items on the Unified Map timeline](#)

Configure which attributes to display in the Attributes panel

Each class has a unique set of extended attributes that appear in the bottom section of the **Attributes** panel for a CI. For any class, you can specify which extended attributes should be displayed. These are general settings that only `sn_cmdb_admin` can configure.


Before you begin

Set the application scope in your instance to **CMDB Workspace**.

Role required: `sn_cmdb_admin`

About this task

In the base system, extended attributes are preconfigured for many common classes. You can modify the default settings and configure settings for additional classes. This example shows where base attributes (A) and extended attributes (B) appear in the Attributes panel. For more information on the Attributes panel, see [View the attributes of a CI or a relationship](#)



These workspace-specific configuration settings affect all users of the CMDB Unified Map page. The settings do not affect other copies of the

Unified Map template. Non-admin users can customize some aspects of their personal experience with Unified Map, but can't configure instance-wide workspace-specific settings.

Procedure

1. Navigate to **All** and then, in the search box on the main navigation bar, enter `sn_cmdb_ws_node_map_table_attributes.list`.
2. In the Table Attributes table, select the configuration identifier to update or select **New** and then fill in the form:

Table Attributes form

Settings that specify which extended attributes to display on the Attributes panel.

Field	Description
Config identifier	Unique name of the configuration identifier that specifies the settings for the current workspace. Note: The base system includes a configuration identifier named Default that specifies the default settings for Unified Map.
CMDB Class Name	The class that this configuration applies to.
Display attributes	List of attributes that appear as extended attributes on the Attributes panel for CIs in the class that is specified by CMDB Class Name .

Field	Description
	You can select from attributes for the class. Unlock the field to add attributes to the Selected list.
UX application	The top-level UX Application ID to which this configuration applies. This is the application ID of your workspace. This value is referenced from the record associated with the Config identifier setting.
Active	Option to set the profile as available for use.
Follow hierarchy	If selected, use the following process to determine which attributes to display. - Start with the attributes specified in Display attributes. - Move up the class hierarchy and add each parent's display attributes until encountering a parent where Follow hierarchy is deselected. - Add that parent's display attributes and then stop collecting display attributes. For nodes that have highlight colors defined: If a display attribute value appears more than once, use the highlight

Field	Description
	color for the least specific CMDB layer. The setting provides the following options: • Follow hierarchy selected: A derived CI class uses its own display attributes and inherits display attributes from parents. • Follow hierarchy not selected: A derived CI class displays only attributes that are specified in its Display attributes setting.

3. Select **Submit** or **Update**.

The updated settings appear in the appropriate related list on the Configuration identifier form, as described in [Configuring Unified Map — Admin settings](#).

Related tasks

- [View the attributes of a CI or a relationship](#)

Configure display of connections to a referenced class

Configure how to display connections to a referenced class and from a referencing class on Unified Map. A reference connects two CIs from differing classes that aren't connected by a relationship. These are general settings that only `sn_cmdb_admin` can configure.

Before you begin

Set the application scope in your instance to **CMDB Workspace**.

Role required: `sn_cmdb_admin`

About this task

These workspace-specific configuration settings affect all users of the CMDB Unified Map page. The settings do not affect other copies of the Unified Map template. Non-admin users can customize some aspects of their personal experience with Unified Map, but can't configure instance-wide workspace-specific settings.

References connect CIs from two classes that don't have a direct relationship connection between them. On the map, any two CIs from the referenced class and from the referencing class appear connected by a dotted line. The relationship type is **Reference**. There are several preconfigured map references that you can modify, and you can also add map references.

For example, you want the map to display references to records in the File System table for Windows Server CI records. In that case, Server ABC (referencing CI) shows connections to the C:\ and D:\ file systems (referenced CIs).

Procedure

1. Navigate to **All** and then, in the filter box on the main navigation bar, enter `sn_cmdb_ws_node_map_reference.list`.
2. On the Node Map References table, select an existing record or select **New** and then fill in the form.

Node Map References table

Settings that configure how to display referenced-class and referencing-class connections.

Field	Description
CI class	The referencing class that this configuration applies to.
Referenced CI class	Class that the specified Reference field references.
Reference field	Attribute in the specified CI class that contains the reference.

Field	Description
Show Reverse	Creates a map reference for the reverse reference between the specified CI class and Referenced CI class .
Active	Enables the configuration so that the connection appears on maps — the map displays referenced CIs.

3. Select **Submit** or **Update**.
The updated settings appear in the appropriate related list on the Configuration identifier form, as described in [Configuring Unified Map — Admin settings](#).

Create a class profile of visible layers for classes

Configure a class profile that specifies which layers should appear for a particular class: application, service instance, business, or infrastructure. For example, you can configure that the mapped application service (service instance) [cmdb_ci_service_discovered] class should display only Service Mapping data and not infrastructure elements.

Before you begin

Set the application scope in your instance to **CMDB Workspace**.

Role required: sn_cmdb_admin

About this task

These workspace-specific configuration settings affect all users of the CMDB Unified Map page. The settings do not affect other copies of the Unified Map template. Non-admin users can customize some aspects of their personal experience with Unified Map, but can't configure instance-wide workspace-specific settings.

Class profiles let you configure the **Layers** filter. Several common classes such as the mapped application service (service instance) [cmdb_ci_service_discovered] class are preconfigured with class profiles.

Class profiles are applied when no filter preset is used for the current map. This typically happens when you load a map without a filter preset or when you set the filter preset to **Default view**.

Procedure

1. Navigate to **All** and then, in the search box on the main navigation bar, enter `sn_cmdb_ws_node_map_profiles.list`.
The Node Map Profiles table lists all classes for which the **Layers** property is set.
2. Select an existing record or select **New** and then fill in the form.

Node Map Profiles table

Settings that configure map filters and map orientation for a class.

Field	Description
Config identifier	Unique name of the configuration identifier that specifies the settings for the current workspace. Note: The base system includes a configuration identifier named Default that specifies the default settings for Unified Map.
Layers	Layers value to apply when the map opens with a home node that is in the class specified by the CMDB CI class setting. • Application, • Service instance (formerly application service) • Business

Field	Description
	Infrastructure On the map display, in the Layers category, the listed filter values are selected and values that are not in the list are deselected.
CMDB CI class	Class of CI that this profile applies to. Whenever a map opens with a home node of the specified class, the Layers values are applied.
Orientation	- Vertical layout: Displays nodes in a vertical tree pattern: upstream relationships top and downstream bottom. This is the default layout for displaying mapped application services and service instances. In the toolbox, select the Vertical layout icon . - Force layout: Displays nodes in a clustered arrangement around the home node, regardless of upstream or downstream relationships. In the toolbox, select the Force layout icon .
UX application	The top-level UX Application ID to which this configuration applies. This is the application ID of your workspace. This value

Field	Description
	is referenced from the record associated with the Config identifier setting.
Active	Option to set the profile as available for use.

3. Select **Submit** or **Update**.
The updated settings appear in the appropriate related list on the Configuration identifier form, as described in [Configuring Unified Map — Admin settings](#).

Related tasks

- [Create or manage a user preset](#)

How configuration settings for Unified Map are stored

General configuration settings that control Unified Map are collected in a configuration identifier. A configuration identifier is a set of properties and table-driven configurations that specify the appearance and content of an instance of a UX application. The CMDB Workspace UX application contains Unified Map.

Important: Because each configuration identifier is unique to an instance of a UX application, the settings for one UX application do not affect the user experience of any other UX application. This means that your admin settings for this instance of Unified Map will not affect Unified Map users in another instance.

Viewing Unified Map configuration settings

The configuration identifier form displays all configurations settings for Unified Map. To view the configuration identifier, navigate to **All** and then, in the filter box in the main navigation bar, enter `sn_cmdb_ws_config_identifier.list`.

On the form, each related list displays property settings or a table of configuration settings.

The base system includes a configuration identifier named **Default** that specifies all default settings.

<

≡

Config identifier

Default

🔗

⚙️

⋮

Update

Delete

↑

↓

A configuration identifier is a set of properties and table-driven configurations that specifies the appearance and content of a UX application. If property settings or table entries in a custom configuration identifier are missing, then the values in the default configuration identifier are used.

* Name

Default

Description

This default configuration identifier is used for any workspace where a custom configuration identifier is not in use.

UX Application

Application

CMDB Workspace

ⓘ

Default

☒

Update

Delete

Workspace Config Properties (4)

Node Map Profiles (2)

Node Map References (20)

Node Map Related Items (5)

Operational life cycle modes (1)

Table Attributes (30)

Unified map shared presets (3)

≡

🔍

Name

Search

⚙️

—

Actions on selected rows...

Config Identifier = Default

☐	🔍	Name ▲	Value	UX Application
		unifiedmap.map_search.max_nodes	250	(empty)
		unifiedmap.map_search_filter.default_levels	3	(empty)
		unifiedmap.map_search_filter.endpoint_de...	sourceId,targetId_label,endpoints	(empty)
		unifiedmap.map_search_filter.max_levels	25	(empty)

Defining custom settings for your CMDB Workspace instance

To create a custom configuration identifier for your workspace, modify the default settings and then save the updates with a new name.

Note: When a custom configuration identifier doesn't specify a particular property setting or table entry, the value in the default configuration identifier is used.