

Zurich ServiceNow AI Platform Capabilities

Last updated: January 16, 2026

Some examples and graphics depicted herein are provided for illustration only. No real association or connection to ServiceNow products or services is intended or should be inferred.

This PDF was created from content on docs.servicenow.com. The web site is updated frequently. For the most current ServiceNow product documentation, go to docs.servicenow.com.

Company Headquarters

2225 Lawson Lane
Santa Clara, CA 95054
United States
(408)501-8550

Service Graph Connector for Jamf

Use the Service Graph Connector for Jamf to pull data from Jamf into your ServiceNow instance.

The Service Graph Connector for Jamf pulls data from computers, disks, networks, and software applications into the ServiceNow® Configuration Management Database (CMDB) application.

Request apps on the Store

Visit the [ServiceNow Store](#) website to view all the available apps and for information about submitting requests to the store. For cumulative release notes information for all released apps, see the [ServiceNow Store version history release notes](#).

Supported versions

Supported ServiceNow versions:

- Xanadu
- Yokohama
- Zurich

Use cases

The following are examples on how you can use the Service Graph Connector for different ServiceNow® applications:

- [IT Operations Management \(ITOM\) Visibility](#)
 - Detailed hardware and software inventory tracking for macOS hardware and apps. The tracking can be done with or without Software Asset Management (SAM).
 - Detailed hardware and software inventory tracking for hardware and apps for both iPhones and iPads. The tracking can be done with or without Software Asset Management (SAM).
 - Compliance tracking for mobile devices and end-user computers.

- Duplicate data detection on imports to improve performance of nightly imports.
- [Software Asset Management \(SAM\)](#) and [IT Asset Management \(ITAM\)](#)
 - Software package and installation tracking.
 - License reclamation by detecting removed software.
 - Software Usage tracking.
- [IT Service Management \(ITSM\)](#)
 - Incidents, problems, and changes on discovered configuration items (CI).
 - Automatic ownership assignment based on top users.

Configuring a connection for the connector

You can configure a connection for the connector by using the SGC Central view in the CMDB Workspace. The view enables you to discover and install connectors, and then effectively manage the full life cycle of creating, editing, monitoring, and debugging connections. To configure the connector using SGC Central, see [Configure Service Graph Connector for Jamf using SGC Central](#).

Important: Unless there are configuration issues, use the SGC Central view in the CMDB Workspace to configure the connection for the connector, as the guided setup method is being deprecated.

CMDB integrations dashboard

The Integration Commons for CMDB store app provides a dashboard with a central view of the status, processing results, and processing errors of all installed integrations. You can see metrics for all integration runs. You can filter the view to a specific CMDB integration, a specific time duration, or a specific integration run. For more details about monitoring Jamf integrations in the CMDB Integrations Dashboard, see [Using the CMDB Integrations Dashboard](#).

Data mapping

Data from the Jamf data source is mapped and transformed into the ServiceNow CMDB Configuration Item (CI) class definitions using the

Robust Transform Engine (RTE). Data is inserted into the ServiceNow CMDB using the Identification and Reconciliation Engine (IRE).

When you complete setting up the connection, you can configure the integration to periodically pull data from Jamf.

The delta data synchronization feature is available in Jamf version 2.14 and higher. You can configure the `is_delta_enabled_for_computers` and `is_delta_enabled_for_mobiles` connection properties for synchronizing only delta data from a Jamf instance. See [Configuring data synchronization in Service Graph Connector for Jamf](#).

The following data sources are included for the Jamf application:

SG-Jamf Computers

Imports data from computers and loads the imported data in the SG-Jamf Computers [sn_jamf_integrate_sg_jamf_computers] staging table.

SG-Jamf Lookup Mac Software Bundle Ids

Imports data from software applications installed on macOS devices and loads the imported data in the SG-Jamf Lookup Mac Software Bundle Ids [sn_cmdb_int_util_mac_software_bundleid_lookup] staging table.

Note: To view the publisher information for applications installed on macOS devices, run the SG-Jamf Lookup Mac Software Bundle Ids data source before running the SG-Jamf Computers or SG-Jamf Mobile Devices data sources.

SG-Jamf Mobile Devices

Imports data from mobile devices and loads the imported data in the SG-Jamf Mobile Devices [sn_jamf_integrate_sg_jamf_mobile_devices] staging table.

SG-Jamf Remove Computers Software

Removes the imported computer software data that were later deleted from the source and updates the information in the SG-Jamf Remove Computers Software [sn_jamf_integrate_jamf_remove_software] staging table.

SG-Jamf Remove Mobile Software

Removes the imported mobile software data that were later deleted from the source and updates the information in the SG-Jamf Remove Mobile Software [sn_jamf_integrate_remove_mobile_software] staging table.

SG-Jamf Software Usage

Imports the software usage details from the Jamf environment to track which software data is being used infrequently, hasn't been used recently enough, or isn't being used at all and loads the imported data in the SG-Jamf Software Usage [sn_jamf_integrate_jamf_software_usage] staging table. Based on the software usage information, you can add a reclamation rule to aggregate usage records and to identify unused software devices. See [Software reclamation rules](#).

Note: The SG-Jamf Software Usage data source is available only when the Software Asset Management Professional plugin (com.snc.samp) is activated on your ServiceNow instance. See [Request Software Asset Management](#).

The imported data is then inserted into the following target tables:

- CI Relationship [cmdb_rel_ci]
- Computer [cmdb_ci_computer]
- Disk [cmdb_ci_disk]
- Handheld Computing device [cmdb_ci_handheld_computing]
- IP Address [cmdb_ci_ip_address]
- Network Adapter [cmdb_ci_network_adapter]
- Printer [cmdb_ci_printer]
- Serial Number [cmdb_serial_number]
- Software Installation [cmdb_sam_sw_install] (If the SAM application is installed.)
- Software Instance [cmdb_software_instance] (If the SAM application is not installed.)

- Software [cmdb_ci_spkg] (If the SAM application is not installed.)
- Software Usage [samp_sw_usage]

Note: For the Computer [cmdb_ci_computer] and Handheld Computing device [cmdb_ci_handheld_computing] data sources, if you created multiple Jamf instances and want to know where the CIs originated from, you can identify the origins from the **Key** and **Value** columns. Additionally, you can view the Jamf Extension Attributes [sn_jamf_integrate_extension_attribute] and Most recent discovery [last_discovered] fields in both data sources. If you want to configure multiple instances, follow the steps in [Configure Service Graph Connector for Jamf using the guided setup](#) in step 4.

For more information on where data is saved when pulling data from a Jamf application, see [CMDB classes targeted in Service Graph Connector for Jamf](#).

You can use the IntegrationHub ETL app to view the data maps. See [IntegrationHub ETL](#) for more information.

Related concepts

- [Service Graph Connectors](#)

Configure Service Graph Connector for Jamf using SGC Central

Use the playbook available with the SGC Central application to set up the Service Graph Connector for Jamf for pulling in Jamf data into the CMDB.

Before you begin

Install Service Graph Connector for Jamf version 2.13.0 or later from the ServiceNow Store. For ServiceNow Store installation steps, see [Install a ServiceNow Store application](#).

When using client credentials for authentication, obtain the OAuth credentials from your Jamf administrator. Make a note of the following details:

- Application (client) ID
- Client Secret

If using Client Credentials authentication in Jamf Pro, you need to use the API Roles and Clients functionality. For more details, refer to the [API Roles and Clients](#) section in the Jamf documentation. When creating a new API client in the Jamf environment, the **Access token lifetime** field on the form for creating a client enables setting how long the token remains valid. The default is 60 seconds, but due to ServiceNow AI Platform limitations, the value must be set to more than 60 seconds. Setting the token lifetime to 3600 seconds (1 hour) helps prevent potential issues.

Role required: SGC-Admin (sn_cmdb_int_util.sgc_admin)

Note: The admin user role is required to run background scripts and to provide table-level access to the SGC-Admin user.

About this task

The playbook experience for onboarding connectors is activated with SGC Central in the CMDB Workspace. To configure the SGC Central application, see [Configuring SGC Central](#) and for more information on how to interact with a playbook, see [Interact with Playbook](#).

Procedure

1. Navigate to **Workspaces > CMDB Workspace**.
2. In the CMDB Workspace, select **SGC Central**.
3. On the Overview page, select **Create connection**.

Tip: Alternatively, you can select **Create connection** on the All connections page.
4. On the Create connection window, select the Jamf connector type and then select **Create connection**.
5. Complete the initial prerequisites when setting up a connection for the first time using a connector.

Note: This step is required only during the first-time setup. See [Perform initial setup tasks when creating a connection in SGC Central](#).

6. Determine the type of authentication for the Jamf connection.
 - a. In the **Setup** stage of the playbook, select the **Select alias template** activity.
If needed, expand the **Setup** stage to select an activity.
 - b. Select an alias template for the connection.
 - **SG-Jamf OAuth Connection:** Select when using OAuth or client credentials for authentication.
 - **SG-Jamf Basic Connection:** Select when using Basic authentication or Bearer token.
 - c. Select **Continue**.
7. Enter connection details and test the API connection for importing data.
 - a. In the **Setup** stage of the playbook, select the **Configure and test connection** activity.
 - b. On the form, fill in the fields.
 - When the **SG-Jamf OAuth Connection** template is selected, fill in the details as shown in the following table.

OAuth connection information

Field	Description
Connection Name	Name to identify the Jamf connection record.
Connection URL	Base URL to connect to the Jamf API.

Field	Description
	Note: This field is automatically set to the URL to connect to the application. Leave the field value as is.
OAuth Client ID	Application (client) ID of your Jamf client application as noted in the Before you begin section. Note: Verify that the Jamf client has read privileges for the Computers and Mobile Devices categories in Jamf.
OAuth Client Secret	Client Secret of your Jamf client application as noted in the Before you begin section.
Use MID Server	Option to use a MID Server. Note: Use of a MID Server is optional.
Mid Selection	Name of the MID Server used by the connector. This field appears only when the Use MID Server check box is selected.

- When the **SG-Jamf Basic Connection** template is selected, fill in the details as shown in the following table.

Basic connection information

Field	Description
Connection Name	Name to identify the Jamf connection record.
Connection Host	Target host value used by the connection. Note: Update the Host field with your Jamf base URL or IP address. For example, <code>demo.jamfhost.com</code> or <code>127.0.0.1</code> .
User Name	User name that is used to authenticate the HTTP or HTTPS request when this Basic authentication profile is enabled. Note: Verify that the Jamf user has read privileges for the Computers and Mobile Devices categories in Jamf.
Password	Password that is used to authenticate the HTTP or HTTPS request when this Basic authentication profile is enabled.
Use MID Server	Option to use a MID Server. Note: Use of a MID Server is optional.

Field	Description
Mid Selection	Name of the MID Server used by the connector. This field appears only when the Use MID Server check box is selected.

- c. Select **Create and test connection**.
 - d. Once the connection test is complete, select **Continue**.
8. (Optional) Set configuration properties for the connection to access Jamf resources.

Note: To skip this step, select **Continue** for the **Set configuration properties** activity. If you skip this step, the default values of the properties are considered.

- a. In the **Setup** stage of the playbook, select the **Set configuration properties** activity.
- b. Set the fields for configuration properties as described in the following table.

Configuration properties

Field	Description
Import managed application records only	Option to limit the import to managed application records only. Note: If the Import managed application records only check box is cleared, the default behavior is to import all application records.

Field	Description
Use JAMF Pro API	Option to enable the use of the Jamf Pro API for querying computer records. Note: When the Use JAMF Pro API check box is selected, the connector uses the Jamf Pro API, which offers pagination of response data and improved performance over the Jamf Classic API.

c. Select **Continue**.

9. Configure the import schedule to import data at regular intervals.

a. In the **Setup** stage of the playbook, select the **Configure import schedule** activity.

b. Select **Configure import schedule**.

c. Select the **Active** check box, and then fill in the run schedule and time details.

For more information, see [Schedule a data import](#).

d. Select **Save**.

e. Repeat steps from [9.b](#) to [9.d](#) for each job displayed on the page.

f. Select **Continue**.

10. In the **Setup** stage of the playbook, select the **Confirm connection creation** activity to verify whether the connection was created.

What to do next

Select **View all connections** to review the connection details. The configured connection appears in the Installed connections list.

Related concepts

- [Service Graph Connector for Jamf](#)
- [Accessing the connection details of Service Graph Connector for Jamf](#)

Related reference

- [CMDB classes targeted in Service Graph Connector for Jamf](#)

Configure Service Graph Connector for Jamf using the guided setup

Set up authentication credentials and scheduled jobs to import Jamf data into your Configuration Management Database (CMDB).

Before you begin

Important: Unless there are configuration issues, use the SGC Central view in the CMDB Workspace to configure the connection for the connector, as the guided setup method is being deprecated.

To use this Service Graph Connector, you need a subscription to a Subscription Unit that is based in the IT Operations Management (ITOM) Visibility application or in the ITOM Discovery application. As defined in the section titled "Managed IT Resource Types" in [ServiceNow Subscription Unit Overview](#) for your subscription, for managed IT resources that are created or modified in the CMDB by this Service Graph Connector, but that aren't yet managed by [ITOM Visibility](#) or [ITOM Discovery](#), these resources will increase Subscription Unit consumption from that application. Review your current Subscription Unit consumption within ITOM Visibility or ITOM Discovery to ensure available capacity.

Dependencies and requirements:

- The [Integration Commons for CMDB](#) store app, which is automatically installed.
- The CMDB CI class models store app, which is automatically installed. See [CMDB CI Class Models](#).

- ITOM Licensing plugin (com.snc.itom.license). An unlicensed plugin that contains computation logic for SU consumption as necessary. For more information, see [Request Discovery](#).
- Jamf Classic API version 10.x.

When using client credentials for authentication, obtain the OAuth credentials from your Jamf administrator. Make a note of the following details:

- Application (client) ID
- Client Secret

If using Client Credentials authentication in Jamf Pro, you need to utilize the API Roles and Clients functionality. For more details, refer to the [API Roles and Clients](#) section in the Jamf documentation. When creating a new API client in the Jamf environment, the **Access token lifetime** field on the form for creating a client enables setting how long the token remains valid. The default is 60 seconds, but due to ServiceNow AI Platform limitations, the value must be set to more than 60 seconds. Setting the token lifetime to 3600 seconds (1 hour) helps prevent potential issues.

Role required: SGC-Admin (sn_cmdb_int_util.sgc_admin)

Note: The admin user role is required to run background scripts and to provide table-level access to the SGC-Admin user.

Procedure

1. Navigate to **All > Service Graph Connectors > Jamf > Setup**.
2. On the Getting Started page, select **Get started**.
3. Set configuration properties.
 - a. On the Service Graph Connector for Jamf page, in the Set configuration properties section, select **Configure JSON data size limit**.
 - b. For the Configure JSON data size limit task, select **Configure**.
 - c. Select the **Global** application scope from the application picker.

- d. Set the `com.glide.transform.json.max-partial-length` system property value.
 - To create a system property, select **New** and enter `com.glide.transform.json.max-partial-length` as the name and `65536` as the value of the property.
 - If the `com.glide.transform.json.max-partial-length` property already exists, verify that its value is set to `65536`.
 - e. Set the Configure JSON data size limit task to complete by selecting **Mark as Complete**.
4. Configure the authentication credentials and HTTP connection for sending requests to the Jamf API.
- a. Enter Basic or Bearer token authentication details.

Important: Skip this step if using Client credentials for authentication, and instead go to step 4.c.
 - a. For the Configure Jamf authentication: Basic or Bearer token authentication task, select **Configure**.
 - b. On the form, fill in the fields.

Basic Auth Credentials form

Field	Description
Name	Descriptive name of this authentication configuration.
User name	User name that is used to authenticate the HTTP or HTTPS request when this Basic authentication profile is enabled.

Field	Description
	Note: Verify that the Jamf user has read privileges for the Computers and Mobile Devices categories in Jamf.
Password	Password that is used to authenticate the HTTP or HTTPS request when this Basic authentication profile is enabled.

c. Select **Update**.

d. Set the Configure Jamf authentication: Basic or Bearer token authentication task to complete by selecting **Mark as Complete**.

b. Configure the Jamf HTTP connection.

Important: Skip this step if using Client credentials for authentication, and instead go to step [4.c](#).

a. For the Configure Jamf HTTP connection task, select **Configure**.

b. On the form, fill in the fields.

HTTP(s) Connection form

Field	Description
Name	Name of the connection.
Credential	Credential value used by this connection.

Field	Description
Connection alias	Connection value that is used to refer to the connection.
Active	Option to activate the HTTP connection.
Domain	Domain that contains the connection.
URL builder	Option to enable the system to build the connection URL.
Connection URL	Connection URL for the connection. You can either manually enter a URL or use the URL builder to build the connection string. Note: You can't modify the Connection URL field if you select the URL builder check box.
Mutual authentication	Option to set the connection with mutual authentication. This field appears only when the URL builder check box is selected.
Protocol	Underlying protocol used by the connection. This field appears only when the URL builder check box is selected. Note: Update the Protocol field if you are using anything other than <code>https</code>.

Field	Description
Use MID server	Option to select a MID Server that sends this HTTP connection. Using a MID Server is not compatible with mutual authentication.
Connection timeout	Number of milliseconds the system waits for a successful host connection. If a successful connection doesn't occur during this time, the connection request times out. Leave this field empty to use the system default connection timeout value.
Host	Target host value used by the connection. This field appears only when the URL builder check box is selected. Note: Update the Host field with your Jamf base URL or IP address. For example, <code>demo.jamfhost.com</code> or <code>127.0.0.1</code> .
Override default port	Target value port that is used by the connection. This field appears only when the URL builder check box is selected.
Base path	Base path for HTTPS connection. This field appears only when the URL builder check box is selected.

Field	Description
	Note: To use the Jamf Pro API, the Base path field must be empty. Therefore, clear any value in the Base path field.

- c. Select **Update**.
- d. Set the Configure Jamf HTTP connection task to complete by selecting **Mark as Complete**.
- c. Configure the client authentication credentials.

Important: Skip this step if using basic token for authentication, and instead go to step 4.a.

 - a. For the Configure Jamf authentication: Client credentials task, select **Configure**.
 - b. Select **Edit** for the SG-Jamf OAuth Connection, the default connection.
 - c. In the Connection Information section of the Edit Connection window, fill in the fields.

Connection Information

Field	Description
Connection Name	Name to identify the Jamf connection record. SG-Jamf OAuth Connection is the default credential alias name and is read-only.
Connection URL	Base URL to connect to the Jamf API.

Field	Description
	Note: This field is automatically set to the URL to connect to the application. Leave the field value as is.

- d. (Optional) If a MID Server is required for the Jamf server connection, select the **Use MID Server** check box. Then, select the MID Server-related fields accordingly.
- e. In the Credential Information section of the Edit Connection window, fill in the fields.

Credential Information

Field	Description
OAuth Client ID	Application (client) ID of your Jamf client application as noted in the Before you begin section. Note: Verify that the Jamf client has read privileges for the Computers and Mobile Devices categories in Jamf.
OAuth Client Secret	Client Secret of your Jamf client application as noted in the Before you begin section.

- d. Test the connection.
 - a. For the Test connection task, select **Configure**.
 - b. Review the properties in the Service Graph Connection Properties related list.

Note: The properties in the Service Graph Connection Properties related list of the connection record are modifiable. Be sure to complete the guided setup, review the property descriptions, and follow the instructions carefully before making any changes to them.

- For Basic authentication, set the `auth_type` property value to `basic` (applicable only for Jamf versions lower than 10.35. Note that Jamf no longer supports Basic authentication, and it will be disabled for all instances starting with Jamf version 11.5).
- For Bearer token authentication, set the `auth_type` property value to `bearer` (available in Jamf version 10.35 or higher).
- For Client credentials (OAuth 2.0) authentication, set the `auth_type` property value to `oauth` (available in Jamf version 10.49 or higher).
- If no authentication type is selected, the connector defaults to Bearer token authentication.

- c. Test the connection by selecting the **Test Load 20 Records** related link.

Testing the connection might take a few moments. The page is refreshed to show the test results.

Note: The connection is successful if the **HTTP Status** is **200**. If there is anything displayed in the **Error Code** and **Error Message** fields, then the connection failed and further troubleshooting is required. Do not select **Load All Records** during this setup.

- d. Set the Test the connection task to complete by selecting **Mark as Complete**.

5. (Optional) Add multiple instances.

Note: If you don't need to add multiple instances, you can skip this step.

- a. In the Add Multiple Instances section of the Service Graph Connector for Jamf page, select **Get Started**.
- b. Enable creating data sources for the new Jamf connection.
 - a. Ensure that you have edit permissions for the Datasource [sys_data_source] table.
 - b. For the Update data source Access task, select **Configure**.
 - c. To edit the record, select the **Global** application scope from the application picker.
 - d. In the Application Access related list of the Data Source form that opens in a new tab, select the **Can create**, **Can update**, and **Can delete** check boxes.
 - e. Select **Update**.
 - f. Select the back icon (<) to return to the guided setup page.
 - g. From the application picker, select the **Service Graph Connector for Jamf** application scope.
 - h. Set the Update data source Access task to complete by selecting **Mark as Complete**
- c. Enable creating a scheduled data import job for the new Jamf connection.
 - a. Ensure that you have edit permissions for the Scheduled data import [scheduled_import_set] table.
 - b. For the Update scheduled data import access task, select **Configure**.
 - c. To edit the record, select the **Global** application scope from the application picker.
 - d. In the Application Access related list of the Scheduled Data Import form that opens in a new tab, select the **Can create**, **Can update**, and **Can delete** check boxes.

- e. Select **Update**.
- f. Select the back icon (<) to return to the guided setup page.
- g. From the application picker, select the **Service Graph Connector for Jamf** application scope.
- h. Set the Update scheduled data import access task to complete by selecting **Mark as Complete**.
- d. Select authentication type for new connection.

Note: From the application picker, select the **Service Graph Connector for Jamf** application scope.

- a. For the Select authentication type for new connection task, select **Configure**.
- b. Select **sn_jamf_integrate.auth_type** from the **Name** column.
- c. Set the sn_jamf_integrate.auth_type property to one of the following values:
 - **basic**: Basic authentication that uses a user name and password.
 - **bearer**: Bearer token authentication that uses a user name and password to retrieve a bearer token.
 - **oauth**: Client credentials authentication that uses a client ID and client secret to authenticate via OAuth 2.0.
- d. Navigate back to the guided setup.
- e. Set the Select authentication type for new connection task to complete by selecting **Mark as Complete**.
- e. Add another connection.

Note: Verify that the **Service Graph Connector for Jamf** application scope is selected in the application picker.

- a. For the Add another connection task, select **Configure**.
- b. In the Workflow Studio, select **Add Connection**.

- c. On the form, based on the authentication type fill in the fields.

Note:

- For Basic or Bearer token authentication-based connection, don't include `https://` in the **Connection Host** field. Example connection host value: `test.jamfcloud.com`.
- For Client credentials authentication-based connection, include `https://` in the **Connection URL** field. Example connection URL value: `https://test.jamfcloud.com`.

- d. Depending on the authentication type, select the button to create the connection.

- e. Navigate back to the guided setup.

- f. Set the Add another connection task to complete by selecting **Mark as Complete**.

- f. When using the Jamf Pro API, the Jamf Pro 10.35 or higher version, or both, specify the Jamf Pro version and API.

- a. For the Select JAMF Pro version and API task, select **Configure**.

- b. In the **Use JAMF Pro API** column, for the connection you created, modify the value from **false** to **true** to use the Jamf Pro API instead of the Classic API.

- c. Update the **Jamf Pro 10.35 or higher** column value to **true** when using the Jamf Pro 10.35 or higher version.

Note: With the **Jamf Pro 10.35 or higher** column value set to **true**, the Bearer Token authentication is used to authenticate the Jamf API. Else, the basic authentication is used.

- d. Set the Select JAMF Pro version and API task to complete by selecting **Mark as Complete**.

- g. Test the new connections.

- a. For the Test new connections task, select **Configure**.
- b. Select the name of the connection you want to test.
- c. To validate the data source configuration, select **Test Load 20 Records**.

Note: If any of the tests have an error code or message or error sign, the connection failed and further troubleshooting is required.

- d. Set the Test new connections task to complete by selecting **Mark as Complete**.

6. Set up the scheduled import jobs.

- a. For the Configure scheduled jobs task in the Set up scheduled import jobs section, select **Configure**.
- b. Select the scheduled job that you want to activate.

Note: By default, the SG-Jamf Mobile Devices scheduled job is automatically set as **Active** and runs the SG-Jamf Computer scheduled job as a parent.

- c. On the Scheduled Data Import form, verify the field values for the scheduled job and select the **Active** check box to activate the scheduled job.

For more information, see [Schedule a data import](#).

- d. Select **Update**.
- e. Repeat the steps [6.b](#) to [6.d](#) for each scheduled job for data import.
- f. Set the Configure scheduled jobs task to complete by selecting **Mark as Complete** in the guided setup.

CMDB classes targeted in Service Graph Connector for Jamf

When you complete setting up the connection, you can configure the integration to periodically pull data from Jamf. The data is saved in tables that extend from the Configuration item [cmdb_ci] table.

Computer [cmdb_ci_computer]

The following attributes in the Computer [cmdb_ci_computer] table are populated by collected data:

Attribute label	Attribute name
MAC Address	mac_address
Name	name
Serial number	serial_number
CPU core count	cpu_core_count
CPU count	cpu_count
CPU name	cpu_name
CPU speed (MHz)	cpu_speed
CPU type	cpu_type
DNS Domain	dns_domain
Fully qualified domain name	fqdn
Most recent discovery	last_discovered
OS Service Pack	os_service_pack
OS Version	os_version
RAM (MB)	ram

Attribute label	Attribute name
Model ID	model_id
Assigned to	assigned_to
Manufacturer	manufacturer
Operating System	os

Relationships created for Computer

Parent class	Relationship type	Child class
Computer [cmdb_ci_computer]	Owns::Owned by	Network Adapter [cmdb_ci_network_adapter]
Computer [cmdb_ci_computer]	Owns::Owned by	IP Address [cmdb_ci_ip_address]
Computer [cmdb_ci_computer]	Contains::Contained by	Disk [cmdb_ci_disk]
Computer [cmdb_ci_computer]	Reference	Key Value [cmdb_key_value]
Computer [cmdb_ci_computer]	Reference	SG-Jamf Extension Attributes [sn_jamf_integrate_extension_attributes]

Disk [cmdb_ci_disk]

The following attributes in the Disk [cmdb_ci_disk] table are populated by collected data:

Attribute label	Attribute name
Manufacturer	manufacturer
Computer	computer

Attribute label	Attribute name
Model ID	model_id
Name	name
Serial number	serial_number
Most recent discovery	last_discovered
Size bytes	size_bytes

Relationship created for Disk

Parent class	Relationship type	Child class
Disk [cmdb_ci_disk]	Reference	Computer [cmdb_ci_computer]

Handheld Computing Device [cmdb_ci_handheld_computing]

The following attributes in the Handheld Computing Device [cmdb_ci_handheld_computing] table are populated by collected data:

Attribute label	Attribute name
Description	short_description
Carrier	carrier
Name	name
Serial number	serial_number
Disk space (GB)	disk_space
ICCID	iccid
IMEI	imei
MEID	meid

Attribute label	Attribute name
Operating System	os
OS Version	os_version
Phone Number	phone_number
Root Access	root_access
Manufacturer	manufacturer
Assigned to	assigned_to
Model ID	model_id

Relationships created for Handheld Computing Device

Parent class	Relationship type	Child class
Handheld Computing Device [cmdb_ci_handheld_computing]	Owns::Owned by	Network Adapter [cmdb_ci_network_adapter]
Handheld Computing Device [cmdb_ci_handheld_computing]	Owns::Owned by	IP Address [cmdb_ci_ip_address]
Handheld Computing Device [cmdb_ci_handheld_computing]	Reference	Key Value [cmdb_key_value]
Handheld Computing Device [cmdb_ci_handheld_computing]	Reference	SG-Jamf Extension Attributes [sn_jamf_integrate_extension_attributes]

IP Address [cmdb_ci_ip_address]

The following attributes in the IP Address [cmdb_ci_ip_address] table are populated by collected data:

Attribute label	Attribute name
IP Address	ip_address
IP version	ip_version
Most recent discovery	last_discovered
Name	name
Nic	nic

Relationship created for IP Address

Parent class	Relationship type	Child class
IP Address [cmdb_ci_ip_address]	Reference	Network Adapter [cmdb_ci_network_adapter]

Key Value [cmdb_key_value]

The following attributes in the Key Value [cmdb_key_value] table are populated by collected data:

Attribute label	Attribute name
Key	key
Value	value

Network Adapter [cmdb_ci_network_adapter]

The following attributes in the Network Adapter [cmdb_ci_network_adapter] table are populated by collected data:

Attribute label	Attribute name
MAC Address	mac_address
Name	name
Discovery Source	discovery_source
Most recent discovery	last_discovered

Relationships created for Network Adapter

Parent class	Relationship type	Child class
Network Adapter [cmdb_ci_network_adapter]	Reference	Computer [cmdb_ci_computer]
Network Adapter [cmdb_ci_network_adapter]	Reference	Handheld Computing Device [cmdb_ci_handheld_computing]

Printer [cmdb_ci_printer]

The following attributes in the Printer [cmdb_ci_printer] table are populated by collected data:

Attribute label	Attribute name
Name	name
IP Address	ip_address
Most recent discovery	last_discovered

Serial Number [cmdb_serial_number]

The following attributes in the Serial Number [cmdb_serial_number] table are populated by collected data:

Attribute label	Attribute name
Serial Number	serial_number
Serial Number Type	serial_number_type
Valid	valid

Relationships created for Serial Number

Parent class	Relationship type	Child class
Serial Number [cmdb_serial_number]	Reference	Computer [cmdb_ci_computer]
Serial Number [cmdb_serial_number]	Reference	Handheld Computing Device [cmdb_ci_handheld_computing]

SG-Jamf Extension Attributes [sn_jamf_integrate_extension_attributes]

The following attributes in the SG-Jamf Extension Attributes [sn_jamf_integrate_extension_attributes] table are populated by collected data:

Attribute label	Attribute name
Id	id
Extension Attributes	extension_attributes

Software [cmdb_ci_spkg]

The following attributes in the Software [cmdb_ci_spkg] table are populated by collected data Software Asset Management (SAM) application isn't installed:

Attribute label	Attribute name
Version	version
Manufacturer	manufacturer
Key	key
Name	name

Relationship created for Software

Parent class	Relationship type	Child class
Software [cmdb_ci_spkg]	Reference	Software Instance [cmdb_software_instance]

Software Installation [cmdb_sam_sw_install]

The following attributes in the Software Installation [cmdb_sam_sw_install] table are populated by collected data when the SAM application is installed:

Attribute label	Attribute name
Discovery source	discovery_source
Display name	display_name
Installed on	installed_on
Last scanned	last_scanned
Publisher	publisher
Version	version

Relationship created for Software Installation

Parent class	Relationship type	Child class
Software Installation [cmdb_sam_sw_install]	Reference	Server [cmdb_ci_server]

Software Instance [cmdb_software_instance]

The following attributes in the Software Instance [cmdb_software_instance] table are populated by collected data when the SAM application isn't installed:

Attribute label	Attribute name
Name	name
Installed on	installed_on

Relationships created for Software Instance

Parent class	Relationship type	Child class
Software Instance [cmdb_software_instance]	Reference	Handheld Computing Device [cmdb_ci_handheld_computing]
Software Instance [cmdb_software_instance]	Reference	Computer [cmdb_ci_computer]

Accessing the connection details of Service Graph Connector for Jamf

You can access the connection details of the Service Graph Connector for Jamf in a single view using the common connection framework (CCF) included within the Integration Commons for CMDB (sn_cmdb_int_util) store app.

With the CCF, you can access all the connections used by the Service Graph Connector for Jamf. The connection details include the connection alias, connection properties, data sources, and scheduled data imports associated with a connection. You can also test the connection. For more information, see [Accessing the connection details of Service Graph Connectors](#).

Access the details of a Jamf connection

Access the details of a Jamf connection configured for the Service Graph Connector for Jamf.

Before you begin

Role required: admin

Procedure

1. Navigate to **All > Service Graph Connectors > Jamf > Connections**.
2. From the **Name** column of the Service Graph Connections list, select a connection.
3. On the Service Graph Connections page, view the connection details such as the connection name, alias, and data sources.
4. Select a related list to view further details of the connection.
5. (Optional) Select the **Test Connection** related link to test the connection.

Configuring data synchronization in Service Graph Connector for Jamf

You can configure the connection properties for synchronizing only delta data from a Jamf instance.

The delta data synchronization feature is available in Jamf version 2.14 and higher. The connector provides the ability to import only delta data from a Jamf instance. With delta synchronization enabled, the importing process of Jamf data is quicker because the connector imports only the changes in Jamf data. The **Last success import time** field of a data source displays the timestamp of the most recent successful pull run. The

delta pull period is calculated by subtracting the last successful run date and time from the current date and time that is Delta period = Current date timestamp - Last success import date timestamp.

The application includes the `is_delta_enabled_for_computers` and `is_delta_enabled_for_mobiles` connection properties to enable delta synchronization for computers and mobile devices, respectively. By default, the `is_delta_enabled_for_computers` and `is_delta_enabled_for_mobiles` properties are set to `false`. To enable delta data synchronization, set these properties to `true`.

Note:

- The `is_delta_enabled_for_computers` connection property is available only if the `use_jamf_pro_api` property is set to `true`.
- The `is_delta_enabled_for_mobiles` connection property is available only if the `use_jamf_mobile_pro_api` property is set to `true`.

See [Service Graph Connector for Jamf properties](#).

When you want to import full data from your Jamf instance, you must disable the `is_delta_enabled_for_computers` and `is_delta_enabled_for_mobiles` properties by setting these properties to `false`. See [Disable delta synchronization](#).

Note: When the full import of data is completed, set the `is_delta_enabled_for_computers` and `is_delta_enabled_for_mobiles` properties back to `true` to pull delta data later. If you leave the properties set to `false`, full data is imported with every pull, which takes considerable time.

Disable delta synchronization

Disable delta synchronization to import all the Jamf data.

Before you begin

Role required: admin

About this task

The delta data synchronization feature is available in Jamf version 2.14 and higher.

Procedure

1. Navigate to **All > Service Graph Connectors > Jamf > Connections**.
2. From the list of connections, open the connection for which you want to disable delta synchronization.

The connection properties are displayed in the Service Graph Connection Properties related list.

- To disable delta synchronization for computers, open the `is_delta_enabled_for_computers` property.
- To disable delta synchronization for mobile devices, open the `is_delta_enabled_for_mobiles` property.

3. In the **Value** field, enter `false`.
4. Select **Update**.

Service Graph Connector for Jamf properties

Service Graph Connector for Jamf properties control the behavior of the connector.

Connection properties

These connection properties are available for the Service Graph Connector for Jamf.

Note: To open the Service Graph Connection Properties `[sn_cmdb_int_util_service_graph_connection_property]` table for the connector, navigate to **All > Service Graph Connectors > Jamf > Connections**, and select the connection name. The connection properties are displayed in the Service Graph Connection Properties related list.

Connection properties for Service Graph Connector for Jamf

Property	Description
<code>auth_type</code>	Set the property to <code>basic</code> to use Basic authentication for the connection. This authentication

Property	Description
	type uses a user name and password. Set the property to <code>oauth</code> to use Client credentials (OAuth 2.0) authentication for the connection. This authentication type uses a client ID and client secret. The default Bearer token authentication type uses a user name and password to retrieve a token for subsequent connection requests. • Type: <code>basic</code> <code>bearer</code> <code>oauth</code> • Default value: <code>bearer</code> Note: • For an OOB default connection, any of the three authentication types can be used. • For additional connections (multi-instance), only the Basic and Bearer authentication types can be used. To use the Client credentials (OAuth 2.0) authentication type, follow the guided setup to configure client authentication credentials for the connection. See Configure Service Graph Connector for Jamf using the guided setup.

Property	Description
import_managed_apps_only	Set the property to <code>true</code> to import only managed application records. When the property is set to <code>false</code>, all application records are imported. • Type: <code>true</code> <code>false</code> • Default value: <code>false</code>
is_delta_enabled_for_computers	Set the property to <code>true</code> to enable the SG-Jamf Computers data source to pull only the changes (delta) between consecutive imports. When the property is set to <code>false</code>, a full import is performed with every pull. Note: This property is available only if the <code>use_jamf_pro_api</code> property is set to <code>true</code>. • Type: <code>true</code> <code>false</code> • Default value: <code>false</code> See Configuring data synchronization in Service Graph Connector for Jamf.
is_delta_enabled_for_mobiles	Set the property to <code>true</code> to enable the SG-Jamf Mobile Devices data source to pull only the changes

Property	Description
	(delta) between consecutive imports. When the property is set to <code>false</code>, a full import is performed with every pull. Note: This property is available only if the <code>use_jamf_mobile_pro_api</code> property is set to <code>true</code>. - Type: <code>true</code> <code>false</code> - Default value: <code>false</code> See Configuring data synchronization in Service Graph Connector for Jamf.
<code>use_jamf_mobile_pro_api</code>	Set the property to <code>true</code> to use the Jamf Pro API for querying Jamf mobile device records. Set the property to <code>false</code> to use the Jamf Classic API. Note: The Jamf Pro API is supported by Jamf version 11.4 and higher. The Jamf Pro API supports pagination of response data and provides performance improvement compared to the Jamf Classic API. - Type: <code>true</code> <code>false</code> - Default value: <code>null</code>

Property	Description
use_jamf_pro_api	Set the property to <code>false</code> to use the Jamf Classic API instead of the Jamf Pro API for querying Jamf mobile device records. When the property is set to <code>true</code>, the Jamf Pro API is used for querying Jamf mobile device records. Note: The Jamf Pro API is supported by Jamf version 11.4 and higher. The Jamf Pro API supports pagination of response data and provides performance improvement compared to the Jamf Classic API. • Type: <code>true</code> <code>false</code> • Default value: <code>true</code>