









Rewrite the Server Screen Flow into a Client Screen Flow

The tables below present the list of functionalities that need to be checked when starting to rewrite the server Screen Flows into client Screen Flows as well as how the configuration from the server mode should look in the client mode.


Process Builder Changes

Functionality	Example of Configuration in the Server Mode	How to Rewrite the Server Mode Configuration to the Client Mode
Check if the Business Controls used in your Screen Flow are supported in the client mode (for details, see Screen Flows Client Mode).	All the Business Controls are supported	If a Business Control is not supported in the client mode (see the list of Business Controls), it should be rewritten into the Standard Operation.
All the Operations of the View type should use the HTML Layout Editor: ▶ Convert only the Steps with UI elements ▶ If the UI Step contains a Sub Operation with UI elements, both the UI Step and Sub Operation should use the HTML Layout Editor ▶ If an Operation contains more than one UI Step, all the UI Steps should be converted (note that there should be only one UI Step in one routing path in the Step Navigation view)	1. The Step navigation configuration (the Operation with Steps, one Step contains the UI elements). 	2. The DISPLAY Step configuration in the Layout Editor (for server mode).
		2. The DISPLAY Step configuration should be converted to the HTML Layout Editor (for converting from server mode to client mode).





		
The User Inputs should be rewritten into the Screen Interface Outputs (the <code>data-flx-bind</code> tag should be used).	Function navigation configuration: An External Output configuration is an exemplary configuration and can be changed to the other one (e.g., a different Function type). 	Configuration example: 1. The Function navigation configuration: An External Output configuration is an exemplary configuration and can be changed to the other one (e.g., a different Function type). 
The User Outputs should be rewritten into the Screen Interface Inputs that can be inserted into the HTML Layout Editor.	Function navigation configuration: An External Input configuration is an exemplary configuration and can be changed to the other one (e.g., a different Function type). 	Configuration example: 1. The Function navigation configuration: An External Input configuration is an exemplary configuration and can be changed to the other one (e.g., a different Function type).  <pre><input type = "text" data-flx-bind = "Output1"/></pre> HTML Layout Editor Code



2. The **HTML Layout Editor:**



JavaScript Changes

Functionality	Example of Configuration in the Server Mode	How to Rewrite the Server Mode Configuration to the Client Mode
The JavaScript "Document Ready" event no longer ensures that a Screen is loaded.	When the JavaScript "Document Ready" event occurs, a Screen is already loaded. HTML Layout Editor Configuration  HTML Layout Editor Code	When the JavaScript "Document Ready" event occurs, a Screen is not loaded yet. In order to perform Screen modifications in the JavaScript use \$View.onLoaded event. HTML Layout Editor Configuration  HTML Layout Editor Code
Check if JavaScript variables are still needed after a View is unloaded.	Configuration example: 1. A Screen with a View that defines a JavaScript variable:  2. The user is moved from the previous Screen to the Screen that shows the value of the variable defined in the previous Screen: 	
	When a variable is defined in the scripts, it is removed when a	When a Screen is submitted, the page is not reloaded, so unused variables should be

	page is submitted. The variable does not exist, so it is not displayed on the screen.	removed manually (e.g., the <code>onViewsUnloading</code> event). Otherwise, the variable exists, so its value will be displayed on the screen.
If you use the <code>setTimeout</code> or <code>setInterval</code> functions, make sure that their execution is stopped when it is needed.	This code invokes the <code>myCallback</code> function every 2 seconds until postback occurs (e.g., the user goes to another Screen): <pre>setInterval(myCallback, 2000);</pre>	This code invokes the <code>myCallback</code> function every 2 seconds until the user stays in the Screen Flows client mode context (e.g., it will be still invoked when the user goes to another Screen, but the execution will be stopped when going to the Portal Home page): <pre>setInterval(myCallback, 2000);</pre> If you want to stop the interval execution when going to another Screen, you should clear the interval manually. This is an example of how to do this: <pre>var intervalId = setInterval(myCallback, 2000); \$View.onUnloading(function() { clearInterval(intervalId); });</pre>