vobiz endpoints

Created	@March 16, 2026 8:52 PM
Class	vobiz

Introduction

A Call object is created when an outbound call is initiated or when an inbound call is received. You can use a Call object to interact with ongoing calls, retrieve details about completed calls, and transfer ongoing calls, thereby building custom call flows.

Base URL `https://api.vobiz.ai/api`

Endpoint `https://api.vobiz.ai/api/v1/Account/{auth_id}/Call/`

Authentication

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token

Example Request Headers

X-Auth-ID: {Auth_ID}

X-Auth-Token: YOUR_AUTH_TOKEN

Content-Type: application/json

The Call Object

The Call object contains all information about a voice call, including metadata, status, duration, and billing details.

A
 Call object is created when an outbound call is initiated or when an

inbound call is received. You can use the Call object to interact with ongoing calls, retrieve details about completed calls, and transfer ongoing calls, thereby building custom call flows.

Note: Call objects are automatically created for both inbound and outbound calls. Each call has a unique `call_uuid` that can be used to retrieve call details or perform operations on the call.

Attributes

Call Object Attributes

Parameter	Type	Description
`answer_time` optional	string	The timestamp when the call was answered. Timezone: Local timezone as set in the Vobiz console. Format: yyyy-MM-dd HH:mm:ss
`bill_duration` optional	integer	The duration of the call in seconds.
`billed_duration` optional	integer	The billed duration of the call in seconds. May differ from bill_duration depending on the billing interval of the destination.
`call_direction` optional	string	Direction of the call — either outbound or inbound.
`call_duration` optional	integer	Duration of the call in seconds.
`call_uuid` optional	string	Unique identifier for the call.
`end_time` optional	string	The timestamp when the call ended. Timezone: Local timezone as set in the Vobiz console. Format: yyyy-MM-dd HH:mm:ss
`from_number` optional	string	Caller ID used to initiate the call.
`hangup_cause_code` optional	integer	Integer code for the hangup cause. See hangup causes
`hangup_cause_name` optional	string	Reason the call was hung up. See hangup causes
`hangup_source` optional	string	Entity that triggered the hangup. Possible sources: Caller, Callee, Vobiz, API Request, Answer XML, Error, Unknown. See hangup causes

Parameter	Type	Description
`initiation_time` optional	string	The timestamp when the call was initiated. Timezone: Local timezone as set in the Vobiz console. Format: yyyy-MM-dd HH:mm:ss
`parent_call_uuid` optional	string	UUID of the A-leg of the call.
`resource_uri` optional	string	URI of the requested resource.
`source_ip` optional	string	IP address from which the call request originated. Useful for monitoring misuse or unauthorized access.
`stir_verification` optional	string	STIR/SHAKEN attestation info: Outbound: Attestation assigned by Vobiz. Inbound: Attestation received on the inbound call to your Vobiz number. Possible values: Verified: Call is from a verified caller (Attestation A). Not Verified: Caller is not verified or uncertain (Attestation B or C). Not Applicable: STIR/SHAKEN doesn't apply (e.g. non-US calls, cloud calls). Read more about STIR/SHAKEN
`to_number` optional	string	Number to which the call was initiated.
`total_amount` optional	string	Total amount charged for the call.
`total_rate` optional	string	Per-minute rate based on the destination number.

Call Operations

Make an Outbound Call

Initiate an outbound call to a PSTN number or a SIP endpoint, and make simultaneous bulk calls.

POST `https://api.vobiz.ai/api/v1/Account/{auth_id}/Call/`

This method lets you initiate an outbound call to a PSTN number or a SIP endpoint, and make simultaneous bulk calls.

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Tip: Use `<` to separate multiple destinations (max 1000). Example: `14157654321<14153464321<sip:john1234@api.vobiz.ai`

Required Parameters

Request Parameters

Parameter	Type	Description
`from` required	string	The caller ID phone number in E.164 format (e.g., 14157654321).
`to` required	string	Destination number(s) or SIP URI(s). Use < to separate multiple destinations (max 1000). Examples: 14157654321, sip:john1234@api.vobiz.ai
`answer_url` required	string	URL called when the call is answered. Must return valid XML.

Callback Parameters

Request Parameters

Parameter	Type	Description
`answer_method` optional	string	HTTP verb for answer_url. Default is POST.
`ring_url` optional	string	Optional URL notified when the call starts ringing.
`ring_method` optional	string	HTTP verb for ring_url. Default is POST.
`hangup_url` optional	string	Optional URL notified when the call is hung up.
`hangup_method` optional	string	HTTP verb for hangup_url. Default is POST.
`fallback_url` optional	string	Invoked if answer_url fails after 3 retries or 60s timeout.

Parameter	Type	Description
`fallback_method` optional	string	HTTP verb for fallback_url. Default is POST.

Machine Detection Parameters

Note: For detailed machine detection documentation, see the Machine Detection page.

Request Parameters

Parameter	Type	Description
`machine_detection` optional	string	Detect machine on answer. Values: true, hangup.
`machine_detection_time` optional	integer	Time in ms to detect machine. Default: 5000. Allowed: 2000–10000.
`machine_detection_url` optional	string	Callback URL for asynchronous machine detection.
`machine_detection_method` optional	string	HTTP verb for machine_detection_url. Default: POST.
`machine_detection_maximum_speech_length` optional	integer	Max speech duration in ms. Default: 5000. Allowed: 1000–6000.
`machine_detection_initial_silence` optional	integer	Max silence after answer (ms). Default: 4500. Allowed: 2000–10000.
`machine_detection_maximum_words` optional	integer	Max number of sentences. Default: 3. Allowed: 2–10.
`machine_detection_initial_greeting` optional	integer	Max greeting length (ms). Default: 1500. Allowed: 1000–5000.

Advanced Parameters

Request Parameters

Parameter	Type	Description
`caller_name` optional	string	Sets caller name (up to 50 characters). Defaults to caller's name.
`send_digits` optional	string	Sends DTMF digits after call is connected. Use w (0.5s wait) or W (1s wait). Example: 1w2W3 or 123@1000 (1000ms tone).
`send_on_preanswer` optional	boolean	If true, sends send_digits during pre-answer. Default: false.
`time_limit` optional	integer	Max duration of call in seconds (after answered). Default: 14400 (4 hours). Calls ≥ 86400s are disconnected at 24h.
`hangup_on_ring` optional	integer	Max duration (in seconds) from start of ringing to hangup.

Request Example

Request Body

```
{
  "from": "14155551234",
  "to": "14155555678",
  "answer_url": "https://example.com/answer",
  "answer_method": "POST",
  "ring_timeout": "30",
  "time_limit": "3600",
  "hangup_url": "https://example.com/hangup",
  "hangup_method": "POST",
  "caller_name": "John Doe",
  "machine_detection": "false"
}
```

cURL Example

```
curl -X POST https://api.vobiz.ai/api/v1/Account/{Auth_ID}/Call/ \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
  -d '{
    "from": "14155551234",
    "to": "14155555678",
    "answer_url": "https://example.com/answer",
```

```
    "answer_method": "POST"
  }'
```

Response Example

Success Response (201 Created)

```
{
  "api_id": "97ceeb52-58b6-11e1-86da-77300b68f8bb",
  "message": "call fired",
  "call_uuid": "9834029e-58b6-11e1-b8b7-a5bd0e4e126f"
}
```

Note: The `call_uuid` is the unique identifier for the call.

Parameters Sent to Callback URLs

For every voice call you make and receive, the system sends a status update to your configured callback URLs. You can read and store this information for analysis, and change the flow of ongoing calls based on the values received.

Parameters Sent to ring_url

Parameter	Type	Description
`From` optional	string	The from number used as the caller ID to initiate the call.
`To` optional	string	The destination that's called.
`RequestUUID` optional	string	An identifier that can uniquely identify a request.
`ALegRequestUUID` optional	string	Identifies the first leg of the call in case there are multiple legs.
`CallUUID` optional	string	The unique identifier for the call.
`Direction` optional	string	The direction of the call. This will have the value "outbound".
`Event` optional	string	The event that triggered this notification. This will have the value "Ring".
`CallStatus` optional	string	The status of the call. This will have the value "ringing".

Parameter	Type	Description
`SessionStart` optional	string	A timestamp that indicates when early media started. Format: YYYY-MM-DD HH:mm:ss.sssss Timezone: UTC
`STIRAttestation` optional	string	Gives details about the attestation assigned to the call by Vobiz.

Parameters Sent to answer_url and fallback_url

Parameter	Type	Description
`From` optional	string	The from number used as the caller ID to initiate the call.
`To` optional	string	The destination that's called.
`CallerName` optional	string	The name of the caller, if the call was made from a SIP endpoint.
`RequestUUID` optional	string	An identifier that can uniquely identify a call.
`ALegRequestUUID` optional	string	Identifies the first leg of the call in case there are multiple legs.
`CallUUID` optional	string	The unique identifier for the call.
`Direction` optional	string	The direction of the call. This will have the value "outbound".
`ALegUUID` optional	string	A unique identifier for the A leg of the call.
`Event` optional	string	The event that triggered this notification. This will have the value "StartApp".
`STIRVerification` optional	string	Attestation details. Possible values: Verified, Not Verified, Not Applicable.
`CallStatus` optional	string	The status of the call. This will have the value "in-progress".
`SessionStart` optional	string	Timestamp when early media started. Format: YYYY-MM-DD HH:mm:ss.sssss Timezone: UTC
`STIRAttestation` optional	string	Details about the attestation assigned to the call by Vobiz.

Parameters Sent to hangup_url

Parameter	Type	Description
`From` optional	string	The from number used as the caller ID to initiate the call.
`To` optional	string	The destination that's called.
`RequestUUID` optional	string	An identifier that can uniquely identify a call.
`ALegRequestUUID` optional	string	Identifies the first leg of the call in case there are multiple legs.
`CallUUID` optional	string	The unique identifier for the call.
`Direction` optional	string	The direction of the call. This will be "outbound".
`ALegUUID` optional	string	A unique identifier for the A leg of the call.
`Event` optional	string	The event that triggered this notification. This will have the value "Hangup".
`stir_verification` optional	string	Attestation details. Possible values: Verified, Not Verified, Not Applicable.
`CallStatus` optional	string	The status of the call. This will have the value "completed".
`StartTime` optional	string	Timestamp when the call was initiated. Timezone: Local. Format: yyyy-MM-dd HH:mm:ss
`AnswerTime` optional	string	Timestamp when the call was answered. Timezone: Local. Format: yyyy-MM-dd HH:mm:ss
`SessionStart` optional	string	Timestamp when early media started. Format: YYYY-MM-DD HH:mm:ss.sssss Timezone: UTC
`EndTime` optional	string	Timestamp when the call ended. Timezone: Local. Format: yyyy-MM-dd HH:mm:ss
`STIRAttestation` optional	string	Details about the attestation assigned to the call by Vobiz.

Machine Detection

Detect answering machines on outbound calls with synchronous or asynchronous detection modes.

Important: Not a Separate Endpoint

Machine detection is **NOT a separate API endpoint**. It is configured as parameters when making a call using `POST https://api.vobiz.ai/api/v1/Account/{auth_id}/Call/`. This page documents the machine detection parameters and callback format.

Machine detection allows you to identify when an answering machine picks up your outbound call instead of a human. You can configure Vobiz to either hang up automatically or continue the call when a machine is detected.

Note: Machine detection is only supported on outbound calls initiated via the Make Call API. Set the `machine_detection` parameter to enable this feature.

How It Works

Synchronous Machine Detection

When you set `machine_detection=true` or `machine_detection=hangup` when making a call, Vobiz analyzes the audio after the call is answered to determine if a machine answered.

Machine Detection Parameters

Parameter	Type	Description
`machine_detection` optional	string	Set to "true" to continue the call or "hangup" to automatically hang up when a machine is detected.
`machine_detection_time` optional	integer	Time in milliseconds to analyze audio. Default: 5000. Range: 2000–10000.
`machine_detection_maximum_speech_length` optional	integer	Maximum speech duration in milliseconds. Default: 5000. Range: 1000–6000.

Parameter	Type	Description
`machine_detection_initial_silence` optional	integer	Maximum silence after answer in milliseconds. Default: 4500. Range: 2000–10000.
`machine_detection_maximum_words` optional	integer	Maximum number of sentences. Default: 3. Range: 2–10.
`machine_detection_initial_greeting` optional	integer	Maximum greeting length in milliseconds. Default: 1500. Range: 1000–5000.

Asynchronous Machine Detection

You can take action on detecting an answering machine during a call by setting the `machine_detection_url` parameter when firing an outbound call API. Vobiz will detect an answering machine in the background and invoke the machine_detection_url with detection results.

Request Parameters

Parameter	Type	Description
`machine_detection_url` optional	string	Callback URL invoked when machine detection completes. Vobiz sends detection results to this URL.
`machine_detection_method` optional	string	HTTP method used to invoke machine_detection_url. Default: POST.

Benefit:
Asynchronous detection allows your application to handle the call immediately while detection happens in the background, providing better user experience.

Parameters Sent to machine_detection_url

When machine detection completes, Vobiz sends these parameters to your machine_detection_url:

Parameter	Type	Description
`From` optional	string	The from number used to initiate the call.
`Machine` optional	boolean	Set to true if a machine is detected.
`To` optional	string	The destination of the call.
`RequestUUID` optional	string	An identifier that can uniquely identify a call.
`ALegRequestUUID` optional	string	Identifies the first leg of the call in case there are multiple legs.
`CallUUID` optional	string	The identifier used to identify the call.
`IfMachine` optional	string	This parameter can be either "continue" or "hangup" depending on the machine_detection parameter set while initiating the call.
`Direction` optional	string	The direction of the call. This will be "outbound" since we support machine detection only on outbound calls.
`ALegUUID` optional	string	A unique identifier for the A leg of the call.
`Event` optional	string	The event that triggered this notification. This will have the value "MachineDetection".
`CallStatus` optional	string	The status of the call. This will have the value "in-progress".

Example Callback Response

JSON Sent to machine_detection_url

```
{
  "From": "+12025550000",
  "Machine": true,
  "To": "+12025551111",
  "RequestUUID": "9834029e-58b6-11e1-b8b7-a5bd0e4e126f",
  "ALegRequestUUID": "9834029e-58b6-11e1-b8b7-a5bd0e4e126f",
  "CallUUID": "97ceeb52-58b6-11e1-86da-77300b68f8bb",
  "IfMachine": "continue",
  "Direction": "outbound",
  "ALegUUID": "97ceeb52-58b6-11e1-86da-77300b68f8bb",
  "Event": "MachineDetection",
  "CallStatus": "in-progress"
}
```

Transfer a Call

Transfer an in-progress call to a different URL for new call flow instructions.

This
 endpoint allows you to redirect an active call to a new XML URL. The new URL should return XML instructions that define the next steps for the call. This is useful for implementing features like call forwarding, IVR navigation, or dynamic call routing.

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Note:
 The call must be in an active state (in-progress) to be transferred. You can transfer both call legs independently using their respective UUIDs.

Important:
 Transfer operations interrupt the current call flow and immediately execute the XML returned from the new URL. Ensure your transfer URL is accessible and returns valid XML.

HTTP Request

POST `https://api.vobiz.ai/api/v1/Account/{auth_id}/Call/{call_uuid}/`

Path Parameters

`auth_id` stringRequired

Your Vobiz account ID (e.g., {Auth_ID})

`call_uuid` stringRequired

Unique identifier of the call to transfer

Request Parameters

Request Parameters

Parameter	Type	Description
`legs` optional	string	Specifies which leg(s) of the call to transfer. Values: "aleg" (caller), "bleg" (callee), or "both". Default: "aleg".
`aleg_url` optional	string	URL to transfer the A leg (caller) to. Must return valid XML with call instructions.
`aleg_method` optional	string	HTTP method to request the aleg_url. Values: "GET" or "POST". Default: "POST".
`bleg_url` optional	string	URL to transfer the B leg (callee) to. Must return valid XML with call instructions.
`bleg_method` optional	string	HTTP method to request the bleg_url. Values: "GET" or "POST". Default: "POST".

Transfer Leg Options:

- `aleg` Transfers only the caller (A leg) to the new URL
- `bleg` Transfers only the callee (B leg) to the new URL
- `both` Transfers both legs to their respective URLs (requires both aleg_url and bleg_url)

Response

Returns a success message confirming the call transfer request has been initiated.

Response - 202 Accepted

```
{
  "api_id": "uuid-here",
  "message": "call transferred",
  "call_uuid": "call-uuid-here"
}
```

Response Fields

`api_id` - Unique identifier for this API request

`message` - Confirmation message indicating the transfer status

Example Request

Transfer A Leg (Caller) Only

Request Body

```
{
  "legs": "aleg",
  "aleg_url": "https://yourdomain.com/transfer_instructions/",
  "aleg_method": "POST"
}
```

Transfer Both Legs

Request Body

```
{
  "legs": "both",
  "aleg_url": "https://example.com/transfer/aleg",
  "aleg_method": "POST",
  "bleg_url": "https://example.com/transfer/bleg",
  "bleg_method": "POST"
}
```

cURL Example

cURL Request

```
curl -X POST https://api.vobiz.ai/api/v1/Account/{auth_id}/Call/{call_uuid}/ \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
  -d '{
    "legs": "both",
    "aleg_url": "https://example.com/transfer/aleg",
    "aleg_method": "POST",
    "bleg_url": "https://example.com/transfer/bleg",
    "bleg_method": "POST"
  }'
```

Use Cases

- Implement call forwarding based on IVR input
- Route calls to different departments dynamically
- Play announcements or collect additional information mid-call
- Implement warm transfer scenarios with hold music
- Change call behavior based on external triggers or events

XML Response Example: Your transfer URL should return XML instructions like:

```
<Response>
  <Speak>Please hold while we transfer your call.</Speak>
  <Dial>
    <Number>+14156667890</Number>
  </Dial>
</Response>
```

Hang Up a Call

Terminate an active call by hanging up one or both call legs.

This endpoint allows you to programmatically terminate an in-progress call. You can hang up the caller (A leg), the callee (B leg), or both legs simultaneously. The call will be terminated immediately and final CDR will be generated.

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Warning: This permanently terminates the call. This action cannot be undone.

Important: Hanging up a call will trigger the hangup_url callback if configured when the call was initiated. This allows you to perform cleanup operations or logging.

HTTP Request

DELETE `https://api.vobiz.ai/api/v1/Account/{auth_id}/Call/{call_uuid}/`

Path Parameters

`auth_id` stringRequired

Your Vobiz account ID (e.g., {Auth_ID})

`call_uuid` stringRequired

Unique identifier of the call to hang up

Request Parameters

No Request Body Required: This endpoint does not require any request body parameters. Simply send a DELETE request to the endpoint URL.

Response

Returns a success message confirming the call hangup request has been processed.

Response - 204 No Content

`No Content`

After Hangup: The call's final CDR will show `hangup_source` as "API" and the `hangup_cause_code` will indicate a programmatic termination (typically code 16: NORMAL_CLEARING).

Example Request

cURL Example

Request

```
curl -X DELETE https://api.vobiz.ai/api/v1/Account/{auth_id}/Call/{call_uuid}/ \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
```

Use Cases

- Terminate abandoned or idle calls to prevent billing
- Implement time-based call limits for compliance
- End calls based on external triggers (e.g., fraud detection)
- Implement emergency call termination features
- Clean up stale call sessions during maintenance

Tip: To retrieve the final call details after hanging up, use the Retrieve a Call endpoint with the call UUID. The CDR will include final duration and billing information.

Retrieve a Live Call

Get real-time information about a currently active call, including call state and live metrics.

This endpoint retrieves detailed information about an in-progress call. Unlike the standard Retrieve a Call endpoint which returns finalized CDRs, this endpoint provides real-time status for active calls including current state, call flow position, and live duration metrics.

Note: This endpoint only returns data for calls that are currently in progress. For completed calls, use the Retrieve a Call endpoint instead.

Use Case: Monitor active calls in real-time, implement live dashboards, or check call status before performing operations like transfer or hangup.

HTTP Request

GET `/api/v1/account/{accountId}/call/{callUuid}/?status=live`

Path Parameters

`accountId` stringRequired

Your Vobiz account ID

`callUuid` stringRequired

Unique identifier of the live call to retrieve

Query Parameters

Request Parameters

Parameter	Type	Description
`status` required	string	Must be set to "live" to retrieve real-time call information.

Important: The `status=live` query parameter is required. Without it, the endpoint will return the finalized CDR (if the call has ended) or a 404 error (if the call UUID doesn't exist).

Response

Returns live call information including current status, call legs, and real-time metrics.

Response - 200 OK


```
{
  "api_id": "c8b427f6-58ce-11e1-86da-adf28403fe48",
  "calls": [
    {
      "answer_time": "2014-10-15 09:03:43",
      "bill_duration": null,
      "billed_duration": null,
      "call_direction": "outbound",
      "call_duration": 180,
      "call_state": "ACTIVE",
      "call_uuid": "97ceeb52-58b6-11e1-86da-77300b68f8bb",
      "conference_uuid": null,
      "end_time": null,
      "from_number": "+14156667777",
      "initiation_time": "2014-10-15 09:03:38",
      "parent_call_uuid": null,
      "hangup_cause_code": null,
      "hangup_cause_name": null,
      "hangup_source": null,
      "resource_uri": "/v1/Account/MA2025RK4E639VJFZAGV/Call/97ceeb52-58b6-11e1-86da-
77300b68f8bb/",
      "to_number": "+14156667778",
      "total_amount": null,
      "total_rate": null,
      "stir_verification": "verified",
      "stir_attestation": "A",
      "source_ip": "1.1.1.1"
    }
  ]
}
```


Live Call Specific Fields

`call_state` - Current state of the call (e.g., "ACTIVE", "RINGING", "EARLY")

`call_duration` - Live call duration in seconds since answer_time

`end_time` - Will be null for active calls

`billed_duration` - Will be null until call ends

`total_amount` - Will be null until call ends and billing is calculated

`hangup_*` - All hangup-related fields will be null for active calls

Call State Values:

- `RINGING` - Call is ringing, not yet answered
- `EARLY` - Early media state (e.g., ringback tone playing)
- `ACTIVE` - Call is connected and in progress
- `HELD` - Call is on hold

Example Request

Retrieve Live Call Status

Request

```
GET /api/v1/account/MA2025RK4E639VJFZAGV/call/97ceeb52-58b6-11e1-86da-77300b68f8bb/?status=live
```

```
Headers:
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
Content-Type: application/json
```

Use Cases

- Build real-time call monitoring dashboards
- Check call state before performing transfer or hangup operations
- Monitor ongoing call duration for time-based triggers
- Verify call connectivity and troubleshoot issues in real-time
- Display live call information to supervisors or agents
- Implement call timers and duration alerts

Tip: Poll this endpoint periodically to monitor live call metrics. Use the `call_duration` field to calculate current call costs in real-time by multiplying with the rate from Pricing.

Error Response: If the call is not currently live or has already ended, you'll receive a 404 error. In that case, use the standard Retrieve a Call endpoint to get the finalized CDR.

Retrieve All Live Calls

Get a list of all ongoing call UUIDs for your account.

This
 endpoint returns an array of call UUIDs for all calls that are currently in progress on your account. This is useful for getting a quick overview of active calls without fetching full call details.

Use Case:
 Use this endpoint to monitor the number of concurrent calls on your account or to get a list of call UUIDs for batch operations.

HTTP Request

GET `/api/v1/account/{accountId}/call/?status=live`

Path Parameters

`accountId` stringRequired

Your Vobiz account ID

Query Parameters

`status` stringRequired

Must be set to "live" to retrieve ongoing calls

Important: The `status=live` query parameter is required to filter for active calls only.

Response

Returns an array of call UUIDs for all ongoing calls.

Response - 200 OK

```
{
  "api_id": "c9527676-5839-11e1-86da-6ff39efcb949",
  "calls": [
    "eac94337-b1cd-499b-82d1-b39bca50dc31",
    "0a70a7fb-168e-4944-a846-4f3f4d2f96f1"
  ]
}
```

Response Fields

`api_id` - Unique identifier for this API request

`calls` - Array of call UUIDs for all active calls

Example Request

Retrieve All Active Calls

Request

```
GET /api/v1/account/MA2025RK4E639VJFZAGV/call/?status=live
```

```
Headers:
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
Content-Type: application/json
```

Use Cases

- Monitor concurrent call volume in real-time
- Build live dashboards showing active call count
- Implement call capacity alerts and monitoring
- Get call UUIDs for batch operations (transfer, hangup)
- Audit active calls for compliance or troubleshooting

Next Step: Once you have the call UUIDs, you can use them with other endpoints like Retrieve a Live Call to get detailed information about each active call.

Retrieve a Queued Call

Get details of a specific call that is currently queued and waiting to be connected.

This endpoint retrieves information about a call that has been initiated but is not yet connected. Queued calls are waiting for the destination to answer or for resources to become available.

What is a Queued Call?
A call is in the "queued" state when it has been initiated via the API but hasn't been answered yet. This includes calls waiting for the destination to ring or answer.

Use Case: Monitor calls that are waiting to be connected, track queue times, or cancel calls before they connect if needed.

HTTP Request

GET `/api/v1/account/{accountId}/call/{callUuid}/?status=queued`

Path Parameters

`accountId` stringRequired

Your Vobiz account ID

`callUuid` stringRequired

Unique identifier of the queued call

Query Parameters

`status` stringRequired

Must be set to "queued" to retrieve queued call details

Important: If the call is no longer queued (connected or ended), this endpoint will return a 404 error. Use the standard Retrieve a Call endpoint for completed calls.

Response

Returns the queued call object with basic call information.

Response - 200 OK

```
{
  "direction": "outbound",
  "from": "15856338537",
  "call_status": "queued",
  "api_id": "45223222-74f8-11e1-8ea7-12313806be9a",
  "to": "14154290945",
  "caller_name": "+15856338537",
  "call_uuid": "6653422-91b6-4716-9fad-9463daaeeec2",
  "request_uuid": "6653422-91b6-4716-9fad-9463daaeeec2"
}
```

Response Fields

`api_id` - Unique identifier for this API request

`call_status` - Always "queued" for this endpoint

`call_uuid` - Unique identifier for the call

`request_uuid` - Request identifier

`direction` - Call direction ("outbound" or "inbound")

`from` - Source phone number

`to` - Destination phone number

`caller_name` - Caller ID name

Example Request

Retrieve Queued Call Status

Request

```
GET /api/v1/account/MA2025RK4E639VJFZAGV/call/6653422-91b6-4716-9fad-9463daaeeec2/?status=queued
```

```
Headers:
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
Content-Type: application/json
```

Use Cases

- Monitor calls waiting to be connected
- Track queue times and identify slow connections
- Verify call details before connection completes
- Cancel queued calls if needed using the hangup endpoint
- Debug call initiation issues

Tip: Combine this with the Retrieve All Queued Calls endpoint to monitor all pending calls on your account at once.

Retrieve All Queued Calls

Get a list of all call UUIDs for calls that are currently queued and waiting to connect.

This endpoint returns an array of call UUIDs for all calls currently in the queued state. The maximum number of results returned per API call is 20.

What are Queued Calls?
Calls are in the "queued" state when they have been initiated but are waiting to be connected. This includes calls waiting for the destination to answer or for available resources.

Use Case: Monitor queue depth, identify calls stuck in queue, or perform bulk operations on pending calls.

HTTP Request

GET `/api/v1/account/{accountId}/call/?status=queued`

Path Parameters

`accountId` stringRequired

Your Vobiz account ID

Query Parameters

`status` stringRequired

Must be set to "queued" to retrieve queued calls

Limit:
This endpoint returns a maximum of 20 call UUIDs per request. If you have more than 20 queued calls, you may need to poll this endpoint periodically.

Response

Returns an array of call UUIDs for all queued calls.

Response - 200 OK

```
{
  "api_id": "c9527676-5839-11e1-86da-6ff39efcb949",
  "calls": [
    "eac94337-b1cd-499b-82d1-b39bca50dc31",
    "0a70a7fb-168e-4944-a846-4f3f4d2f96f1"
  ]
}
```

Response Fields

`api_id` - Unique identifier for this API request

`calls` - Array of call UUIDs for all queued calls (max 20)

Example Request

Retrieve All Queued Calls

Request

```
GET /api/v1/account/MA2025RK4E639VJFZAGV/call/?status=queued
```

```
Headers:
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
Content-Type: application/json
```

Use Cases

- Monitor queue depth and detect call backlogs
- Identify calls stuck in queue for troubleshooting
- Build queue management dashboards
- Cancel all queued calls in bulk during maintenance
- Track average time calls spend in queue

Tip: Use the returned call UUIDs with the Retrieve a Queued Call endpoint to get detailed information about each queued call, or use the Hang Up a Call endpoint to cancel them.

Record Calls

Record specific portions of active calls with automated transcription support.

The Record endpoint allows you to start and stop recording specific portions of an active call. You can create multiple recordings on the same call, customize audio formats, and enable automated transcription for compliance and quality assurance.

Important: Call recordings are powerful tools for compliance, training, and quality assurance. Always ensure you comply with local recording consent laws and inform participants when calls are being recorded.

Key Features

Multiple Recordings

Create multiple recordings on the same call to capture specific portions or conversations.

Format Options

Choose between MP3 and WAV formats. MP3 files are smaller and recommended for most use cases.

Auto Transcription

Enable automated transcription with turnaround time under 5 minutes for supported durations.

Channel Options

Record in mono or stereo. Stereo separates caller and callee into left/right channels.

Callbacks

Receive HTTP callbacks when recordings complete with URLs to download the audio files.

Time Limits

Set maximum recording durations to control file sizes and storage costs.

Available Operations

POST**Start Recording**
Start recording an active call with customizable format, transcription, and callback options.DELETE**Stop Recording**
Stop an active recording on a call. Optionally specify which recording to stop.

Common Use Cases

- ### Compliance & Legal

  Record calls for regulatory compliance, dispute resolution, and legal documentation.

- ### Quality Assurance

  Monitor customer service quality, agent performance, and adherence to scripts.

- **Training & Development**

  Use recorded calls for agent training, onboarding, and skill development programs.

- **Transcription & Analysis**

  Generate transcripts for sentiment analysis, keyword extraction, and call analytics.

- **Customer Records**

  Maintain detailed records of customer interactions for CRM integration and history.

Best Practices

Use MP3 Format

MP3 files are significantly smaller than WAV files, reducing storage costs and bandwidth usage. Use MP3 unless you specifically need uncompressed audio.

Set Reasonable Time Limits

Configure appropriate time limits to prevent unexpectedly large files and control costs. Default is 60 seconds, adjust based on your use case.

Transcription Limitations

Transcription is only available for English calls with duration between 500ms and 4 hours, and file size under 2GB. Factor these limits into your application design.

Use Stereo for Multi-Party

For calls with multiple participants, use stereo recording to separate speakers into different channels for easier analysis and transcription.

Legal Compliance

Always comply with local laws regarding call recording consent. Many jurisdictions require informing all parties that the call is being recorded.

Play Audio on Calls

Play audio files to users during active calls for notifications, music, and announcements.

The Play Audio endpoint allows you to play audio files to participants in an ongoing call. This is commonly used for playing hold music, automated notifications, IVR prompts, or announcements while maintaining the call connection.

Supported Formats: Vobiz supports .mp3 and .wav audio files. Audio files must be accessible via HTTP/HTTPS URLs.

Key Features

Multiple Audio Files

Play multiple audio files in sequence by providing comma-separated URLs.

Call Leg Selection

Choose which participants hear the audio: caller (A leg), callee (B leg), or both.

Loop Playback

Play audio indefinitely for hold music or continuous announcements.

Audio Mixing

Mix playback with call audio or mute call participants during playback.

Duration Control

Limit playback duration to control costs and user experience.

Stop Anytime

Stop audio playback programmatically when needed.

Available Operations

POST**Play Audio**
Play an audio file or multiple files during an active call.DELETE**Stop Audio**
Stop playing audio that is currently being played on a call.

Common Use Cases

- **Hold Music**

  Play music while customers wait on hold or during call transfers.

- **IVR Prompts**

  Play menu options, instructions, or navigation prompts in interactive voice systems.

- **Announcements**

  Deliver pre-recorded announcements, promotions, or important information.

- **Queue Notifications**

  Inform callers of their position in queue or estimated wait time.

- **Call Recording Disclaimer**

  Play legal disclaimers about call recording or monitoring.

Best Practices

Use MP3 for Efficiency

MP3 files stream faster and use less bandwidth than WAV files. Convert your audio to MP3 for better performance.

Host on CDN

Host your audio files on a CDN or reliable hosting service with HTTPS support for fast, secure delivery.

Optimize Audio Length

Keep audio files concise. Use the length parameter to limit playback duration and prevent lengthy hold times.

Mix Audio Thoughtfully

Set mix=false when playing important announcements to ensure participants hear them clearly without conversation interference.

Test Audio Quality

Always test your audio files on actual calls to ensure proper volume, clarity, and compatibility across different devices.

Speak Text on Calls

Convert text to speech and speak it during active calls using advanced TTS technology.

The Speak Text API uses Vobiz's text-to-speech (TTS) engine to convert written text into spoken audio during ongoing calls. This allows you to deliver dynamic messages, notifications, or instructions without pre-recording audio files. Support for 29 languages and multiple voices enables global reach.

Supported: 29 languages with both WOMAN and MAN voices (availability varies by language). Default is English (US) with WOMAN voice.

Key Features

29 Languages

Support for major global languages including English, Spanish, French, German, Chinese, Japanese, and more.

Multiple Voices

Choose between WOMAN and MAN voices for most languages (availability varies).

Dynamic Content

Generate speech on-the-fly without pre-recording, perfect for personalized messages.

Call Leg Selection

Choose which participants hear the speech: caller, callee, or both.

Loop Support

Repeat text indefinitely for continuous notifications or prompts.

Audio Mixing

Mix speech with call audio or mute participants during playback.

Available Operations

POST**Speak Text**
Convert text to speech and play it during an active call with language and voice options.DELETE**Stop Speaking**
Stop text-to-speech that is currently being spoken on a call.

Common Use Cases

- ### Dynamic IVR Menus

  Generate menu options and prompts based on customer data or time of day.

- ### Personalized Greetings

  Welcome callers by name or deliver customized messages based on caller ID.

- ### Queue Updates

  Announce queue position, wait times, or estimated callback times dynamically.

- ### Multi-Language Support

  Deliver messages in the caller's preferred language for global customer support.

- **Real-Time Notifications**

  Deliver account balances, order statuses, or appointment confirmations on-demand.

Best Practices

Keep Text Concise

Short, clear messages are easier to understand. Break long content into multiple segments if needed.

Use Proper Punctuation

Punctuation affects speech pacing and tone. Use periods, commas, and question marks for natural-sounding speech.

Test Different Voices

Try both WOMAN and MAN voices to find which works best for your use case and audience.

Choose Right Language

Match the language to your caller's preference for better user experience and comprehension.

Avoid Special Characters

Emojis and special symbols may not be pronounced correctly. Use plain text for best results.

DTMF

Send DTMF tones during active calls to automate interactions with IVR systems and other tone-based services.

DTMF (Dual-Tone Multi-Frequency) is the tone that's generated whenever a key is pressed in an active call. This resource allows you to send DTMF digits in an active call. The common use case for using this object is

to automate sending of specific digits to a receiver in an outbound call.

Use Case Example: Automatically navigate IVR menus, enter access codes, or provide automated responses to phone systems without manual input.

API Endpoint

Base URI `https://api.vobiz.ai/api/v1/Account/{auth_id}/Call/{call_uuid}/DTMF/`

Key Features

🎹

All DTMF Digits

Send any DTMF digit including 0-9, *, and # characters for complete IVR navigation.

🎯

Leg Selection

Choose which call leg (caller or callee) receives the DTMF tones for precise control.

⚡

Real-Time Sending

Send DTMF digits instantly during active calls for immediate interaction.

🤖

Automation Ready

Perfect for automated call flows, IVR navigation, and programmatic call control.

Common Use Cases

- ### IVR Menu Navigation

  Automatically navigate through IVR menus by sending the appropriate menu selections.

- ### Access Code Entry

Enter conference codes, PIN numbers, or access codes without manual input.

- **Automated Survey Responses**

  Submit automated responses to phone surveys or feedback systems.

- **Account Verification**

  Automatically enter account numbers or verification codes during calls.

- **Call Control**

  Send control codes to phone systems that accept DTMF commands.

Available Operations

POST**Send Digits on a Call**
Send DTMF digits to an active call. Specify the digits to send and which call leg should receive them.View Documentation →