vobiz endpoints 5

Created	@March 17, 2026 1:59 AM
Class	vobiz

SIP Trunk Service

Manage SIP trunks for enterprise voice communications. Create trunks with automatic SIP domain provisioning, configure authentication methods, and set up outbound routing for scalable telephony infrastructure.

What is a SIP Trunk?

A SIP trunk is a virtual connection that enables voice communication over IP networks. Each trunk serves as a dedicated voice gateway with its own authentication, rate limits, and routing configuration. Vobiz automatically provisions each trunk with a unique SIP domain and integrates it with Kamailio for robust SIP routing and authentication.

- **Auto-generated SIP domains:** Each trunk gets a unique domain like `trunkId.sip.vobiz.ai`
- **Flexible authentication:** Support for both username/password and IP-based authentication
- **Rate limiting:** Configure concurrent call limits and calls-per-second (CPS) throttling
- **Outbound routing:** Define origination URIs with priority-based failover and load balancing

Key Features

Dual Authentication

Choose between username/password credentials or IP whitelisting. Combine both methods for maximum security.

Intelligent Routing

Configure multiple origination URIs with priority-based failover and weight-based load balancing for resilient outbound calling.

Rate Limiting

Protect against traffic spikes with configurable concurrent call limits and calls-per-second (CPS) throttling.

Kamailio Integration

Seamless integration with Kamailio SIP proxy for robust routing, authentication, and load balancing infrastructure.

Trunk Management

The core trunk operations allow you to create, configure, and manage your SIP trunks. Each trunk acts as an independent voice gateway with its own configuration and rate limits.

The Trunk Object
Complete structure and attributes of a trunk**Create a Trunk**
Provision a new SIP trunk with auto-generated domain**Retrieve a Trunk**
Get details of a specific trunk by ID**Retrieve All Trunks**
List all trunks with pagination support**Update a Trunk**
Modify trunk configuration and rate limits**Delete a Trunk**
Permanently remove a trunk and its resources

Credentials

Credentials provide username/password authentication for your SIP trunk. You can create multiple credentials per trunk for different devices or use cases. Passwords are securely hashed and never returned in API responses after creation.

View Credentials Documentation

IP Access Control Lists

IP
 Access Control Lists (IP ACLs) enable IP-based authentication by whitelisting specific IPv4 addresses. Devices calling from whitelisted IPs can use the trunk without password authentication. This is ideal for
 PBX systems, SIP gateways, and carrier interconnections with static IP addresses.

View IP ACL Documentation

Origination URIs

Origination
 URIs define where outbound calls from your trunk should be routed. Configure multiple URIs with priority-based failover (lower priority tried first) and weight-based load balancing (higher weight receives more traffic). This enables resilient, distributed call routing with automatic failover.

View Origination URI Documentation

Authentication Methods

Username/Password

SIP
 digest authentication using credentials. Ideal for devices with dynamic
 IP addresses or mobile softphones. Kamailio validates credentials against the subscriber database.

Works from any IP address

Multiple credentials per trunk

Secure password hashing

IP Whitelisting

IP-based
authentication without passwords. Best for PBX systems, SIP gateways, and carrier connections with static IP addresses. Provides higher security for production deployments.

No password required

Enhanced security

Requires static IP addresses

SIP Call Log Error Statuses

When
reviewing your SIP call logs, you may encounter various error and failure statuses. Understanding these statuses is essential for troubleshooting SIP connections, routing issues, and endpoint configurations. The table below describes common `SIP` error logs and what they indicate:

Status Code	Description / Cause
`NORMAL_CLEARING`	The call was cleared normally by one of the parties hanging up. This is a standard end-of-call status.
`USER_BUSY`	The called party is busy (e.g., already on another call or declined the call).
`NO_ANSWER`	The called party did not answer the call within the specified timeout period.
`ORIGINATOR_CANCEL`	The caller (originator) hung up or cancelled the call before it could be answered.
`CALL_REJECTED`	The call was explicitly rejected, potentially due to blocking rules, spam filtering, or the destination refusing the connection.
`REJECTED`	A general rejection status, often occurring when the SIP endpoint refuses the incoming INVITE.
`INVALID_NUMBER`	The dialed number format is incorrect, invalid, or does not exist.
`UNALLOCATED_NUMBER`	The dialed number is formally valid but is not currently allocated or assigned to any active subscriber.

Status Code	Description / Cause
`SERVICE_UNAVAILABLE`	The destination service or endpoint is temporarily completely unavailable (e.g., SIP 503 error).
`SERVER_ERROR`	An internal server error occurred while attempting to process or route the SIP call.
`MEDIA_TIMEOUT`	The call was disconnected because no RTP media packets were received for an extended period, suggesting a firewall or network dropout issue.
`PROTOCOL_ERROR`	A fundamental SIP protocol violation or malformed SIP message occurred during call setup.
`NETWORK_OUT_OF_ORDER`	A severe network failure prevented the call from being routed to its destination.
`DESTINATION_OUT_OF_ORDER`	The specific destination endpoint or PBX cannot physically accept the call, often indicating an offline server.
`NORMAL_TEMPORARY_FAILURE`	A generic temporary failure in routing the call. Re-attempting the call might succeed.
`SWITCH_CONGESTION`	The telephone network or SIP switch is experiencing high traffic and cannot handle the required capacity at this moment.
`UNKNOWN`	An error occurred that could not be mapped to any standard SIP error or ISUP release cause code.

Getting Started

Quick Setup Guide

1. 1

   ### Create a Trunk

   Use the Create Trunk endpoint to provision a new SIP trunk. You'll receive a unique SIP domain and trunk ID.

2. 2

Configure Authentication

Add credentials for password authentication or configure IP ACLs for IP-based authentication.

3. 3

Set Up Routing

Configure origination URIs to define where outbound calls should be routed. Set priorities for failover and weights for load balancing.

4. 4

Test Your Trunk

Configure your SIP client with the trunk's domain and credentials, then make a test call to verify everything is working correctly.

The Trunk Object

Complete structure and attributes of a SIP Trunk object.

The Trunk object represents a SIP trunking connection in your account. A trunk provides the foundation for voice communication by managing authentication, rate limiting, and routing configuration. Each trunk can have multiple credentials, IP access control lists, and origination URIs to support various use cases.

Auto-Generated SIP Domain: When a trunk is created, Vobiz automatically generates a unique SIP domain in the format: `trunkId.sip.vobiz.ai`. This domain is used for inbound call routing to your trunk.

Attributes

Trunk Attributes

Parameter	Type	Description
`trunk_id` optional	string (UUID)	Unique identifier for the trunk. Automatically generated upon creation.
`account_id` optional	string	The account identifier that owns this trunk.
`name` optional	string	A descriptive name for the trunk. Required field. Maximum 255 characters.
`description` optional	string	Optional description providing additional context about the trunk's purpose or configuration.
`concurrent_calls_limit` optional	integer	Maximum number of simultaneous calls allowed on this trunk. Default: 10.
`cps_limit` optional	integer	Calls per second (CPS) rate limit to prevent flooding. Default: 5.
`enabled` optional	boolean	Whether the trunk is active and can handle calls. Default: true.
`created_at` optional	string (ISO 8601)	Timestamp when the trunk was created. Format: YYYY-MM-DDTHH:mm:ssZ (UTC timezone).
`updated_at` optional	string (ISO 8601)	Timestamp of the last update to the trunk. Format: YYYY-MM-DDTHH:mm:ssZ (UTC timezone).

Example

Trunk Object Response

A typical trunk object as returned by the API:

Trunk Object

```
{
  "trunk_id": "bfab10fb-cb97-488b-9c63-989c32980b0f",
  "account_id": "{Auth_ID}",
  "name": "Production Trunk",
  "description": "Main production SIP trunk for US East region",
```

```
  "concurrent_calls_limit": 100,
  "cps_limit": 10,
  "enabled": true,
  "created_at": "2025-01-15T10:30:45Z",
  "updated_at": "2025-01-20T14:22:10Z"
}
```

Rate Limiting: The `concurrent_calls_limit` and `cps_limit` protect your trunk from overload and help manage costs.

Timestamps: All timestamps are in UTC timezone following ISO 8601 format.

Create a Trunk

Create a new SIP trunk for voice communications.

This
 API allows you to create a new SIP trunk for handling voice traffic.
Each trunk can be configured with rate limits, authentication methods (credentials and IP ACLs), and origination URIs for outbound routing.

Auto-Generated Domain: Upon creation, Vobiz automatically generates a unique SIP domain for your trunk in the format: `trunk_id.sip.vobiz.ai`. This domain is used for routing inbound calls to your trunk.

HTTP Request

POST `https://api.vobiz.ai/api/v1/account/{account_id}/trunks`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Request Parameters

Request Parameters

Parameter	Type	Description
`name` required	string	A descriptive name for the trunk. Maximum 255 characters.
`trunk_status` optional	string	Status of the trunk. e.g. 'enabled', 'disabled'.
`secure` optional	boolean	Whether the trunk is secure (TLS/SRTP).
`trunk_direction` optional	string	Direction of calls. e.g. 'outbound', 'both'.
`trunk_domain` optional	string	The SIP domain for the trunk.
`concurrent_calls_limit` optional	integer	Maximum number of concurrent calls allowed.
`cps_limit` optional	integer	Calls per second limit.
`transport` optional	string	The transport protocol to be used. Can be "udp" or "tcp".
`ipacl_uuid` optional	string	UUID of the IP Access Control List to associate with this trunk.
`credential_uuid` optional	string	UUID of the Credential to associate with this trunk.
`primary_uri_uuid` optional	string	UUID of the primary Origination URI.
`fallback_uri_uuid` optional	string	UUID of the fallback Origination URI.
`inbound_destination` optional	string	The SIP URI to which inbound calls will be forwarded.

Response

Returns the complete trunk object including the auto-generated `trunk_id` UUID and timestamps.

Response - 201 Created

```
{
                "trunk_id": "aabbcc-dd-ee-ff-gg",
                "account_id": "MA_XYZ123",
                "name": "My SIP Trunk",
                "trunk_domain": "sip.example.com",
                "trunk_status": "active",
```

```
                "secure": false,
                "trunk_direction": "outbound",
                "concurrent_calls_limit": 10,
                "cps_limit": 5,
                "ipacl_uuid": "YOUR_IP_ACL_ID",
                "credential_uuid": "YOUR_CREDENTIAL_ID",
                "primary_uri_uuid": "YOUR_PRIMARY_URI_ID",
                "fallback_uri_uuid": "YOUR_FALLBACK_URI_ID",
                "transport": "udp",
                "created_at": "2025-11-03T14:09:12.08032875Z",
                "updated_at": "2025-11-03T14:09:12.08032875Z"
              }
```

Examples

cURL - Basic Trunk

cURL Request

```
curl -X POST https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks \
                  -H "X-Auth-ID: YOUR_AUTH_ID" \
                  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
                  -H "Content-Type: application/json" \
                  -d '{
                    "name": "My SIP Trunk",
                    "trunk_status": "enabled",
                    "secure": false,
                    "trunk_direction": "outbound",
                    "trunk_domain": "sip.example.com",
                    "concurrent_calls_limit": 10,
                    "cps_limit": 5,
                    "transport": "udp",
                    "ipacl_uuid": "{ipAclId}",
                    "credential_uuid": "{credentialId}",
                    "primary_uri_uuid": "{primaryUriId}",
                    "fallback_uri_uuid": "{fallbackUriId}",
                    "inbound_destination": "sip:user@host.com"
                  }'
```

Next Steps:

- Save the `trunk_id` for all future operations
- Add credentials or IP ACLs for authentication
- Configure origination URIs for outbound call routing
- Test the trunk with a sample call before production use

Retrieve a Trunk

Get details of a specific SIP trunk by ID.

This API retrieves the complete details of a specific trunk using its unique trunk_id. Use this endpoint to verify trunk configuration, check rate limits, or confirm the trunk's enabled status.

HTTP Request

GET `https://api.vobiz.ai/api/v1/account/{account_id}/trunks/{trunk_id}`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Response

Returns the complete trunk object with all attributes.

Response - 200 OK

```
{
                "trunk_id": "22fed784-4ed9-4caf-8bbd-7738ca37f275",
                "account_id": "{Auth_ID}",
                "name": "US Primary",
                "trunk_domain": "22fed784.sip.vobiz.ai",
                "trunk_status": "active",
                "secure": false,
                "trunk_direction": "both",
                "concurrent_calls_limit": 20,
                "cps_limit": 10,
                "ipacl_uuid": "ip-acl-uuid-123",
                "credential_uuid": "cred-uuid-123",
                "primary_uri_uuid": "uri-uuid-123",
                "fallback_uri_uuid": "uri-uuid-456",
                "description": "Primary outbound trunk",
                "inbound_destination": "5hj19p4hixv.sip.livekit.cloud",
                "transport": "udp",
                "created_at": "2025-10-17T11:17:46.06043Z",
                "updated_at": "2025-10-27T11:31:21.799571Z"
            }
```

Examples

cURL

cURL Request

```
curl -X GET https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks/bfab10fb-cb97-488b-9c63-989c32980b0f \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
```

Error Response (404): If the trunk_id doesn't exist or doesn't belong to your account, you'll receive a 404 Not Found error.

Retrieve All Trunks

List all SIP trunks for your account with pagination support.

This API retrieves a paginated list of all trunks associated with your account. Use this endpoint to view all your trunk configurations, monitor resource usage, and manage multiple trunks.

HTTP Request

GET `https://api.vobiz.ai/api/v1/account/{account_id}/trunks`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Query Parameters

Request Parameters

Parameter	Type	Description
`limit` optional	integer	Number of results per page. Default: 20. Maximum: 100.

Parameter	Type	Description
`offset` optional	integer	Number of results to skip for pagination. Default: 0. Use with limit for page navigation.

Response

Returns a paginated list of trunk objects with metadata about pagination state.

Response - 200 OK


```
{
                "meta": {
                  "limit": 10,
                  "offset": 0,
                  "total_count": 2
                },
                "objects": [
                  {
                    "trunk_id": "08c9431-fc2b-4a9e-997e-1b0fcd913565",
                    "account_id": "{Auth_ID}",
                    "name": "US Primary",
                    "trunk_domain": "08c9431.sip.vobiz.ai",
                    "trunk_status": "active",
                    "secure": false,
                    "trunk_direction": "both",
                    "concurrent_calls_limit": 20,
                    "cps_limit": 10,
                    "ipacl_uuid": "ip-acl-uuid-123",
                    "credential_uuid": "cred-uuid-123",
                    "primary_uri_uuid": "uri-uuid-123",
                    "fallback_uri_uuid": "uri-uuid-456",
                    "description": "Primary outbound trunk",
                    "inbound_destination": "5hj19p4hixv.sip.livekit.cloud",
                    "transport": "udp",
                    "created_at": "2025-10-17T11:18:06.869912Z",
                    "updated_at": "2025-10-28T10:15:09.12671Z"
                  },
                  {
                    "trunk_id": "22fed784-4ed9-4caf-8bbd-7738ca37f275",
                    "account_id": "{Auth_ID}",
                    "name": "US Primary",
                    "trunk_domain": "22fed784.sip.vobiz.ai",
                    "trunk_status": "active",
                    "secure": false,
                    "trunk_direction": "both",
                    "concurrent_calls_limit": 20,
                    "cps_limit": 10,
                    "ipacl_uuid": "ip-acl-uuid-789",
                    "credential_uuid": "cred-uuid-789",
```

```
                    "description": "Primary outbound trunk",
                    "inbound_destination": "5hj19p4hixv.sip.livekit.cloud",
                    "transport": "udp",
                    "created_at": "2025-10-17T11:17:46.06043Z",
                    "updated_at": "2025-10-27T11:31:21.799571Z"
                  }
                ]
              }
```

Examples

cURL - Default Pagination

cURL Request

```
curl -X GET "https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks" \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
```

cURL - Custom Pagination

cURL Request

```
curl -X GET "https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks?limit=50&offset=0" \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
```

Pagination Tip: Use `total_count` from the meta object to calculate total pages. For page 2 with limit 10, use offset=10.

Update a Trunk

Modify configuration settings for an existing SIP trunk.

This
API allows you to update the configuration of an existing trunk. You can modify the name, description, and rate limits. Only include fields you want to update; other fields will remain unchanged.

Note: The `trunk_id` and `account_id` cannot be changed after creation.

HTTP Request

PUT `https://api.vobiz.ai/api/v1/account/{account_id}/trunks/{trunk_id}`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Request Parameters

All parameters are optional. Only include fields you want to update.

Request Parameters

Parameter	Type	Description
`name` optional	string	Update the trunk name. Maximum 255 characters.
`description` optional	string	Update the trunk description.
`enabled` optional	boolean	Enable or disable the trunk. Set to false to temporarily disable without deleting.

Response

Returns the complete updated trunk object with the new `updated_at` timestamp.

Response - 200 OK

```
{
                "trunk_id": "aabbcc-dd-ee-ff-gg",
                "account_id": "MA_XYZ123",
                "name": "Updated Production Trunk",
                "trunk_domain": "aabbcc.sip.vobiz.ai",
                "trunk_status": "active",
                "secure": false,
                "trunk_direction": "both",
                "username": "testuser",
                "password": "TestPassword123!",
                "concurrent_calls_limit": 10,
                "cps_limit": 2,
                "ip_whitelist": [
                  "198.51.100.10",
                  "10.0.0.0/8"
                ],
                "credential_uuid": "xyz-abc-123",
                "description": "Updated description for production trunk",
                "transport": "udp",
                "created_at": "2025-11-03T14:09:12.08032875Z",
                "updated_at": "2025-11-03T14:10:15.12345678Z"
              }
```

Examples

cURL - Update Name Only

cURL Request

```
curl -X PUT https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks/bfab10fb-cb97-488b-9c63-989c32980b0f \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
  -d '{
    "name": "Updated Production Trunk"
  }'
```

cURL - Disable Trunk

cURL Request

```
curl -X PUT https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks/bfab10fb-cb97-488b-9c63-989c32980b0f \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
  -d '{
    "enabled": false
  }'
```

Best Practice:
Disable a trunk instead of deleting it if you might need the configuration later. Disabled trunks won't handle calls but preserve all settings, credentials, and routing rules.

Assign Number to Trunk

Link a phone number to a specific SIP Trunk for call routing.

This API endpoint allows you to assign a phone number to a specific SIP trunk. Once assigned, all inbound calls to that phone number will be routed through the designated trunk according to your trunk's configuration.

Important: The phone number must already be in your account inventory. You can purchase numbers using the Purchase Number endpoint before assigning them to

a trunk.

HTTP Request

POST `https://api.vobiz.ai/api/v1/account/{ACCOUNT_ID}/numbers/{PHONE_NUMBER}/assign`

URL Encoding Notice:

Always encode the phone number in the URL. Use `%2B` instead of the `+` symbol. For example: `%2B912271264217` (not +912271264217). Failure to encode properly may result in a 404 error.

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., MA_BN2MZ1VV)
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

URL Parameters

Path Parameters

Parameter	Type	Description
`ACCOUNT_ID` required	string	Your unique Vobiz account identifier (e.g., MA_BN2MZ1VV). Must match your X-Auth-ID header.
`PHONE_NUMBER` required	string	The phone number to assign, URL-encoded. Use %2B instead of + (e.g., %2B912271264217).

Request Body

Request Parameters

Parameter	Type	Description
`trunk_group_id` required	string (UUID)	The UUID of the trunk to which you want to assign this phone number (e.g., e3e55a78-1234-5678-90ab-cdef12345678).

Request Body Example

```
{
  "trunk_group_id": "xxxxxxxx-xxxx-xxxx-xxxx-xxxxxxxxxxxx"
}
```

Response

On successful assignment, the API returns a `204 No Content` status with no response body. This indicates the number has been successfully linked to the trunk.

Success Response - 204 No Content

```
HTTP/1.1 204 No Content
Date: Thu, 23 Jan 2026 07:07:24 GMT
Server: Vobiz API Gateway
```

Error Responses

Error Response - 404 Not Found (Invalid Phone Number Format)

```
{
  "error": "Number not found",
  "message": "The phone number could not be found. Ensure it is URL-encoded correctly."
}
```

Error Response - 400 Bad Request (Number Already Assigned)

```
{
  "error": "invalid request",
  "message": "This number is already assigned to a trunk."
}
```

Examples

cURL - Assign Number to Trunk

cURL Request

```
curl -X POST "https://api.vobiz.ai/api/v1/account/{ACCOUNT_ID}/numbers/%2B1234567890/assign"
\
  -H "X-Auth-ID: {ACCOUNT_ID}" \
  -H "X-Auth-Token: {AUTH_TOKEN}" \
  -H "Content-Type: application/json" \
  -d '{
    "trunk_group_id": "{TRUNK_ID}"
  }'
```

Generic Template (Use Your Own Values)

cURL Template

```
curl -X POST "https://api.vobiz.ai/api/v1/account/{ACCOUNT_ID}/numbers/{PHONE_NUMBER}/assign" \
  -H "X-Auth-ID: {ACCOUNT_ID}" \
  -H "X-Auth-Token: {AUTH_TOKEN}" \
  -H "Content-Type: application/json" \
  -d '{
    "trunk_group_id": "{TRUNK_ID}"
  }'
```

Quick Tips:

- **Success Code:** Look for `204 No Content` response
- **URL Encoding:** Always use `%2B` instead of `+` in the phone number
- **Trunk UUID:** Get the trunk_group_id from the Create Trunk response
- **Number Format:** Use E.164 format with country code (e.g., +1234567890)

Next Steps:

- Verify the assignment by retrieving your trunk details
- Configure your trunk's inbound routing rules
- Test inbound calls to the assigned number
- To remove the assignment, use the Unassign Number endpoint

Unassign Number from Trunk

Remove the link between a phone number and a SIP trunk.

This API endpoint allows you to remove the assignment between a phone number and a SIP trunk. After unassignment, the number will remain in your account inventory but will no longer route calls through the previously assigned trunk.

Warning: Unassigning a number from a trunk will immediately stop routing inbound calls to that number. Ensure you have an alternative routing configuration or reassign the number to a different trunk if you want to continue receiving calls.

HTTP Request

DELETE `https://api.vobiz.ai/api/v1/account/{ACCOUNT_ID}/numbers/{PHONE_NUMBER}/assign`

URL Encoding Notice:

Always encode the phone number in the URL. Use `%2B` instead of the `+` symbol. For example: `%2B912271264217` (not +912271264217). Failure to encode properly may result in a 404 error.

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., MA_BN2MZ1VV)
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Note: This endpoint uses the `DELETE` HTTP method on the same URL path as the assignment endpoint. No request body is required.

URL Parameters

Path Parameters

Parameter	Type	Description
`ACCOUNT_ID` required	string	Your unique Vobiz account identifier (e.g., MA_BN2MZ1VV). Must match your X-Auth-ID header.
`PHONE_NUMBER` required	string	The phone number to unassign, URL-encoded. Use %2B instead of + (e.g., %2B912271264217).

No Request Body Required:
The DELETE method does not require a request body. The phone number specified in the URL will be unassigned from its currently associated trunk.

Response

On successful unassignment, the API returns a `204 No Content` status with no response body. This indicates the number has been successfully unlinked from the trunk.

Success Response - 204 No Content

```
HTTP/1.1 204 No Content
Date: Thu, 23 Jan 2026 07:07:24 GMT
Server: Vobiz API Gateway
```

Error Responses

Error Response - 404 Not Found (Invalid Phone Number)

```
{
  "error": "Number not found",
  "message": "The phone number could not be found or is not assigned to any trunk."
}
```

Error Response - 400 Bad Request (Invalid Format)

```
{
  "error": "invalid request",
  "message": "The phone number format is invalid. Ensure it is URL-encoded correctly."
}
```

Examples

cURL - Unassign Number from Trunk

cURL Request

```
curl -X DELETE
"https://api.vobiz.ai/api/v1/account/{ACCOUNT_ID}/numbers/%2B1234567890/assign" \
  -H "X-Auth-ID: {ACCOUNT_ID}" \
  -H "X-Auth-Token: {AUTH_TOKEN}" \
  -H "Content-Type: application/json"
```

Generic Template (Use Your Own Values)

cURL Template

```
curl -X DELETE
"https://api.vobiz.ai/api/v1/account/{ACCOUNT_ID}/numbers/{PHONE_NUMBER}/assign" \
  -H "X-Auth-ID: {ACCOUNT_ID}" \
  -H "X-Auth-Token: {AUTH_TOKEN}" \
  -H "Content-Type: application/json"
```

Quick Tips:

- **Success Code:** Look for `204 No Content` response
- **URL Encoding:** Always use `%2B` instead of `+` in the phone number
- **No Request Body:** DELETE requests do not require a request body

- **Number Format:** Use E.164 format with country code (e.g., +1234567890)

Important Considerations:

- **Immediate Effect:** Unassignment takes effect immediately; inbound calls will no longer route
- **Number Retention:** The number remains in your account inventory after unassignment
- **Reassignment:** You can reassign the number to a different trunk or the same trunk later
- **Billing:** Number rental charges continue until you release the number using the Unrent Number endpoint

Next Steps:

- Reassign to a different trunk using the Assign Number endpoint
- Or, release the number entirely using the Unrent Number endpoint
- Verify the unassignment by listing your trunk details
- Update your application logic to handle the routing change

Delete a Trunk

Permanently remove a SIP trunk and all its associated resources.

This API permanently deletes a trunk and all its associated resources including credentials, IP ACL entries, and origination URIs. This action cannot be undone.

Warning: Deleting a trunk will:

- Permanently delete all credentials associated with this trunk
- Remove all IP ACL entries
- Delete all origination URIs
- Immediately stop all active calls on this trunk
- Make the trunk's SIP domain unavailable for inbound calls

Alternative: Consider disabling the trunk instead (set `enabled: false`) to preserve configuration while preventing new calls.

HTTP Request

DELETE `https://api.vobiz.ai/api/v1/account/{account_id}/trunks/{trunk_id}`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Response

Returns HTTP 204 No Content on successful deletion. No response body is returned.

Response - 204 No Content

`No Content`

Error Responses:

- **404 Not Found:** Trunk does not exist or doesn't belong to your account
- **409 Conflict:** Trunk has active calls (wait for calls to end first)

Examples

cURL

cURL Request

```
curl -X DELETE https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks/bfab10fb-cb97-488b-9c63-989c32980b0f \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
```

Before Deleting:

- Verify no active calls are using this trunk
- Document any credentials or routing configurations

- Check if phone numbers are associated with this trunk
- Consider exporting trunk configuration for backup
- Notify users who may be affected by the deletion

Credentials

Manage SIP credentials for username/password authentication on your trunks.

Introduction

Credentials provide username/password-based authentication for your SIP trunks. Each credential consists of a unique username and password combination that SIP clients can use to authenticate when making or receiving calls through your trunk.

Multiple credentials can be created for a single trunk, allowing different users, devices, or applications to connect with separate authentication details. This provides flexibility in managing access and tracking usage across different endpoints.

Security Note: Passwords are write-only and never returned in API responses. Once set, passwords cannot be retrieved - only updated or reset.

Best Practice: Use strong passwords (minimum 8 characters) with a mix of uppercase, lowercase, numbers, and special characters. Rotate credentials regularly for enhanced security.

Use Cases

Dynamic IP Environments

Perfect for remote workers, mobile devices, or any scenario where the source IP address changes frequently. Username/password authentication works regardless of network location.

Multi-User Access

Create separate credentials for different users or departments, making it easier to track usage and manage access permissions independently.

SIP Client Integration

Configure softphones, desk phones, or PBX systems with unique credentials for reliable authentication without IP whitelisting requirements.

Combined Authentication

Use credentials alongside IP ACL for maximum security - requiring both valid credentials AND whitelisted IP addresses for authentication.

Available Operations

1

The Credential Object

Learn about the structure and attributes of credential objects

2

Create Credential

Add new SIP credentials to a trunk with username and password

3

Retrieve All Credentials

List all credentials associated with a trunk with pagination support

4

Update Credential

Modify existing credential properties like password, status, or description

5

Delete Credential

Permanently remove credentials from a trunk

Quick Start:
Begin by reviewing the credential object structure, then create your first credential to start authenticating SIP clients to your trunk.

The Credential Object

Complete structure and attributes of a SIP Credential object.

The Credential object represents a set of SIP authentication credentials (username and password) that can be used to authenticate calls on a specific trunk. Multiple credentials can exist for a single trunk, enabling different users, devices, or applications to connect with unique authentication details.

Password Security: The `password` field is write-only and will never be returned in API responses. Once created, passwords cannot be retrieved - only updated.

Username Immutability: The `username` cannot be changed after credential creation. To use a different username, create a new credential and delete the old one.

Attributes

Credential Attributes

Parameter	Type	Description
`id` optional	string (UUID)	Unique identifier for the credential. Automatically generated upon creation.
`trunk_id` optional	string (UUID)	The ID of the trunk this credential belongs to.
`username` optional	string	SIP username for authentication. Required field. Must be unique within the trunk. Cannot be changed after creation.
`password` optional	string	SIP password for authentication. Required field (minimum 8 characters). Write-only - never returned in responses.

Parameter	Type	Description
`enabled` optional	boolean	Whether the credential is active and can be used for authentication. Default: true.
`description` optional	string	Optional description providing context about the credential's purpose or which device/user it belongs to.
`created_at` optional	string (ISO 8601)	Timestamp when the credential was created. Format: YYYY-MM-DDTHH:mm:ssZ (UTC timezone).
`updated_at` optional	string (ISO 8601)	Timestamp of the last update to the credential. Format: YYYY-MM-DDTHH:mm:ssZ (UTC timezone).

Example

Credential Object Response

A typical credential object as returned by the API (note: password is not included):

Credential Object

```
{
  "id": "a1b2c3d4-e5f6-7890-abcd-ef1234567890",
  "trunk_id": "bfab10fb-cb97-488b-9c63-989c32980b0f",
  "username": "trunk_user_001",
  "enabled": true,
  "description": "Primary trunk credential for production",
  "created_at": "2025-01-15T10:35:20Z",
  "updated_at": "2025-01-15T10:35:20Z"
}
```

Security Best Practices:

- Use strong passwords with at least 12 characters
- Include uppercase, lowercase, numbers, and special characters
- Rotate credentials regularly (quarterly recommended)
- Disable unused credentials immediately rather than deleting them
- Use descriptive usernames that identify the device or user

Create Credential

Add new SIP authentication credentials to a trunk.

This
API creates a new set of SIP credentials (username and password) for authenticating calls on a specific trunk. The username must be unique within the trunk, and the password must meet minimum security requirements.

Important:
Save the password securely after creation. The API will never return the password in future responses - it is write-only for security purposes.

Note:
The username cannot be changed after creation. If you need a different username, create a new credential and delete the old one.

HTTP Request

POST `https://api.vobiz.ai/api/v1/account/{account_id}/credentials`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Request Parameters

Request Parameters

Parameter	Type	Description
`username` required	string	SIP username for authentication. Must be unique within the account. Cannot be changed after creation. Use descriptive names

Parameter	Type	Description
		like "office_phone_01" or "user_john_mobile".
`password` required	string	SIP password for authentication. Minimum 8 characters. Recommended: 12+ characters with mixed case, numbers, and special characters.
`enabled` optional	boolean	Whether the credential is active and can be used for authentication. Default: true. Set to false to create a disabled credential.
`description` optional	string	Optional description providing context about the credential's purpose, such as "Primary office phone" or "John's mobile device".

Response

Returns the complete credential object including the auto-generated `id` UUID. Note that the password is not included in the response for security reasons.

Response - 201 Created

```
{
  "id": "a1b2c3d4-e5f6-7890-abcd-ef1234567890",
  "username": "trunk_user_002",
  "enabled": true,
  "description": "Backup credential",
  "created_at": "2025-01-22T10:30:00Z",
  "updated_at": "2025-01-22T10:30:00Z"
}
```

Examples

cURL - Basic Credential

cURL Request

```
curl -X POST https://api.vobiz.ai/api/v1/account/{Auth_ID}/credentials \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
```

```
  -d '{
    "username": "trunk_user_001",
    "password": "SecurePassword123!",
    "enabled": true,
    "description": "Primary credential"
  }'
```

cURL - Credential with Strong Password

cURL Request

```
curl -X POST https://api.vobiz.ai/api/v1/account/{Auth_ID}/credentials \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
  -d '{
    "username": "office_phone_main",
    "password": "Vbz!2025$SecureP@ss",
    "enabled": true,
    "description": "Main office desk phone"
  }'
```

Error Response (409 Conflict): If the username already exists for this trunk:

Error Response

```
{
  "error": "Username already exists for this trunk",
  "code": 409
}
```

Next Steps:

- Save the credential `id` for future operations
- Store the password securely in your password manager
- Configure your SIP client with the username and password
- Test authentication by making a test call

Retrieve All Credentials

List all SIP credentials associated with a trunk.

This
 API retrieves a paginated list of all credentials associated with the account. Use this endpoint to audit all authentication credentials,

review which usernames are in use, or identify disabled credentials that can be cleaned up.

Pagination Support:
Results are paginated using limit and offset parameters. The response includes metadata showing the total count, current offset, and limit applied.

HTTP Request

GET `https://api.vobiz.ai/api/v1/account/{account_id}/trunks/credentials`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Query Parameters

Request Parameters

Parameter	Type	Description
`limit` optional	integer	Maximum number of credentials to return per page. Default: 20. Useful for controlling response size.
`offset` optional	integer	Number of credentials to skip before starting to return results. Default: 0. Used for pagination - e.g., offset=20 with limit=20 returns page 2.

Response

Returns a paginated response with metadata and an array of credential objects. Passwords are never included in the response.

Response - 200 OK

```
{
  "meta": {
```

```
    "limit": 20,
    "offset": 0,
    "total_count": 3
  },
  "objects": [
    {
      "id": "a1b2c3d4-e5f6-7890-abcd-ef1234567890",

      "username": "trunk_user_001",
      "enabled": true,
      "description": "Primary trunk credential",
      "created_at": "2025-01-15T10:35:20Z",
      "updated_at": "2025-01-15T10:35:20Z"
    },
    {
      "id": "b2c3d4e5-f6a7-8901-bcde-f23456789012",

      "username": "trunk_user_002",
      "enabled": true,
      "description": "Backup credential",
      "created_at": "2025-01-16T14:20:30Z",
      "updated_at": "2025-01-16T14:20:30Z"
    },
    {
      "id": "c3d4e5f6-a7b8-9012-cdef-345678901234",

      "username": "trunk_user_003",
      "enabled": false,
      "description": "Disabled test credential",
      "created_at": "2025-01-17T09:15:45Z",
      "updated_at": "2025-01-20T16:30:00Z"
    }
  ]
}
```


Examples

cURL - Default Pagination

cURL Request

```
curl -X GET https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks/credentials \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
```

cURL - Custom Pagination

cURL Request

```
curl -X GET "https://api.vobiz.ai/api/v1/account/{Auth_ID}/trunks/credentials?limit=10&offset=0" \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
```

Pagination Tips:

- Use `total_count` from metadata to calculate total pages
- Increment offset by limit value for each subsequent page
- Page 1: offset=0, Page 2: offset=20, Page 3: offset=40 (with limit=20)
- Empty `objects` array indicates no more results

Use Case:
This endpoint is ideal for displaying credential management interfaces, auditing which credentials are active, and identifying unused credentials that can be safely removed.

Update Credential

Modify existing SIP credential properties.

This API updates an existing credential's password, enabled status, or description. Use this endpoint to rotate passwords, enable or disable credentials, or update descriptive information.

Important Limitation:
The username cannot be changed after credential creation. If you need a different username, you must create a new credential and delete the old one.

Security Note:
When updating the password, ensure it meets minimum security requirements (8+ characters). The new password will not be returned in the response.

HTTP Request

PUT `https://api.vobiz.ai/api/v1/account/{account_id}/credentials/{credential_id}`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Request Parameters

All parameters are optional. Include only the fields you want to update.

Request Parameters

Parameter	Type	Description
`password` optional	string	New SIP password. Minimum 8 characters. Use this to rotate passwords regularly for security. Recommended: 12+ characters with mixed case, numbers, and special characters.
`enabled` optional	boolean	Whether the credential is active. Set to false to temporarily disable authentication without deleting the credential. Set to true to re-enable.
`description` optional	string	Updated description for the credential. Use this to document changes like "Rotated password on 2025-01-22" or "Assigned to new device".

Note: The `username` field cannot be updated. It is immutable after credential creation.

Response

Returns the updated credential object with the new values. The password is not included in the response. Note the `updated_at` timestamp reflects when the change

was made.

Response - 200 OK

```
{
  "id": "a1b2c3d4-e5f6-7890-abcd-ef1234567890",
```

```
  "username": "trunk_user_001",
  "enabled": false,
  "description": "Updated credential description",
  "created_at": "2025-01-15T10:35:20Z",
  "updated_at": "2025-01-22T11:15:45Z"
}
```

Examples

cURL - Update Password

cURL Request

```
curl -X PUT https://api.vobiz.ai/api/v1/account/{Auth_ID}/credentials/a1b2c3d4-e5f6-7890-abcd-ef1234567890 \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
  -d '{
    "password": "UpdatedSecurePassword456!",
    "description": "Password rotated on 2025-01-22"
  }'
```

cURL - Disable Credential

cURL Request

```
curl -X PUT https://api.vobiz.ai/api/v1/account/{Auth_ID}/credentials/a1b2c3d4-e5f6-7890-abcd-ef1234567890 \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
  -d '{
    "enabled": false,
    "description": "Temporarily disabled for maintenance"
  }'
```

cURL - Re-enable Credential

cURL Request

```
curl -X PUT https://api.vobiz.ai/api/v1/account/{Auth_ID}/credentials/a1b2c3d4-e5f6-7890-abcd-ef1234567890 \
```

```
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN" \
  -H "Content-Type: application/json" \
  -d '{
    "enabled": true,
    "description": "Re-enabled after maintenance"
  }'
```

Best Practices:

- Rotate passwords quarterly or when a device is compromised
- Use the `enabled` flag to disable credentials temporarily instead of deleting them
- Update the description when making changes to document the reason
- Notify affected users before changing passwords to prevent service disruption

Error Response (404): If the credential_id doesn't exist or doesn't belong to the specified trunk, you'll receive a 404 Not Found error.

Delete Credential

Permanently remove SIP credentials from a trunk.

This API permanently deletes a credential from a trunk. Once deleted, the credential can no longer be used for SIP authentication, and any devices or applications using this credential will be unable to connect. This action cannot be undone.

Warning: Deleting a credential will:

- Immediately prevent authentication using this username and password
- Disconnect any active calls using this credential
- Block any devices configured with this credential from making new calls
- Permanently remove the credential - this cannot be undone

Alternative: Consider disabling the credential instead (set `enabled: false`) to temporarily prevent authentication while preserving the credential for future use or audit purposes.

HTTP Request

DELETE `https://api.vobiz.ai/api/v1/account/{account_id}/credentials/{credential_id}`

Authentication Required:

- **X-Auth-ID:** Your account ID (e.g., {Auth_ID})
- **X-Auth-Token:** Your account Auth Token
- **Content-Type:** application/json

Response

Returns HTTP 204 No Content on successful deletion. No response body is returned.

Response - 204 No Content

`No Content`

Error Responses:

- **404 Not Found:** Credential does not exist or doesn't belong to the specified trunk
- **409 Conflict:** Credential is currently in use by active calls (wait for calls to end first)

Examples

cURL

cURL Request

```
curl -X DELETE https://api.vobiz.ai/api/v1/account/{Auth_ID}/credentials/a1b2c3d4-e5f6-7890-abcd-ef1234567890 \
  -H "X-Auth-ID: YOUR_AUTH_ID" \
  -H "X-Auth-Token: YOUR_AUTH_TOKEN"
```

Before Deleting:

- Verify no active calls are using this credential
- Document the credential details (username, description) for records
- Check if any devices or applications are configured with this credential

- Notify affected users who may be using this credential
- Consider disabling instead of deleting to preserve audit trail
- Ensure you have alternative credentials configured for the trunk

Common Use Cases:

- Removing credentials for decommissioned devices
- Cleaning up test credentials after development
- Deleting compromised credentials after creating replacements
- Removing access for users who no longer need it

Recovery:
If you accidentally delete a credential, you cannot recover it. You'll need to create a new credential with a new username and password, then reconfigure all affected devices.