WinPE Image deployment

- boot the computer with the WinPE usb stick
- once the WinPE environment has loaded
- Diskpart:

```
> diskpart
> list volume
// take note of the volume label of the usb stick
> select volume <usb volume label>
> assign letter=E
> list disk
// lists disk numbers and details
> select disk <CF number>
> clean
> create partition primary size=700
> active
> assign letter=C
> format fs=ntfs quick
// for the 2nd partition size subtract 700 and another 100 from
// the total CF size.
// For example: calculated size = 3800 - 700 - 100 = 3000
// use the 'list disk' command to check
> create partition primary size=<calculated size>
> assign letter=D
> format fs=ntfs quick
> exit
```

– Navigate to E:

> E:

 assuming the image and the file 'imagex.exe' are in a folder called image (tip: imagex.exe can be put in the path variable in WinPE)

```
> cd image
// <wimfile> is the image file (*.wim) associated with the pc
> imagex.exe /apply <wimfile> 1 C:
```

- Reboot the computer without the USB stick, FBA should now load.