

Command line tool (kubectl)



- 1: [Introduction to kubectl](#)
- 2: [kubectl Quick Reference](#)
- 3: [kubectl reference](#)
 - 3.1: [kubectl](#)
 - 3.2: [kubectl annotate](#)
 - 3.3: [kubectl api-resources](#)
 - 3.4: [kubectl api-versions](#)
 - 3.5: [kubectl apply](#)
 - 3.5.1: [kubectl apply edit-last-applied](#)
 - 3.5.2: [kubectl apply set-last-applied](#)
 - 3.5.3: [kubectl apply view-last-applied](#)
 - 3.6: [kubectl attach](#)
 - 3.7: [kubectl auth](#)
 - 3.7.1: [kubectl auth can-i](#)
 - 3.7.2: [kubectl auth reconcile](#)
 - 3.7.3: [kubectl auth whoami](#)
 - 3.8: [kubectl autoscale](#)
 - 3.9: [kubectl certificate](#)
 - 3.9.1: [kubectl certificate approve](#)
 - 3.9.2: [kubectl certificate deny](#)
 - 3.10: [kubectl cluster-info](#)
 - 3.10.1: [kubectl cluster-info dump](#)
 - 3.11: [kubectl completion](#)
 - 3.12: [kubectl config](#)
 - 3.12.1: [kubectl config current-context](#)
 - 3.12.2: [kubectl config delete-cluster](#)
 - 3.12.3: [kubectl config delete-context](#)
 - 3.12.4: [kubectl config delete-user](#)
 - 3.12.5: [kubectl config get-clusters](#)
 - 3.12.6: [kubectl config get-contexts](#)
 - 3.12.7: [kubectl config get-users](#)
 - 3.12.8: [kubectl config rename-context](#)
 - 3.12.9: [kubectl config set](#)
 - 3.12.10: [kubectl config set-cluster](#)

- 3.12.11: [kubectl config set-context](#)
- 3.12.12: [kubectl config set-credentials](#)
- 3.12.13: [kubectl config unset](#)
- 3.12.14: [kubectl config use-context](#)
- 3.12.15: [kubectl config view](#)
- 3.13: [kubectl cordon](#)
- 3.14: [kubectl cp](#)
- 3.15: [kubectl create](#)
 - 3.15.1: [kubectl create clusterrole](#)
 - 3.15.2: [kubectl create clusterrolebinding](#)
 - 3.15.3: [kubectl create configmap](#)
 - 3.15.4: [kubectl create cronjob](#)
 - 3.15.5: [kubectl create deployment](#)
 - 3.15.6: [kubectl create ingress](#)
 - 3.15.7: [kubectl create job](#)
 - 3.15.8: [kubectl create namespace](#)
 - 3.15.9: [kubectl create poddisruptionbudget](#)
 - 3.15.10: [kubectl create priorityclass](#)
 - 3.15.11: [kubectl create quota](#)
 - 3.15.12: [kubectl create role](#)
 - 3.15.13: [kubectl create rolebinding](#)
 - 3.15.14: [kubectl create secret](#)
 - 3.15.15: [kubectl create secret docker-registry](#)
 - 3.15.16: [kubectl create secret generic](#)
 - 3.15.17: [kubectl create secret tls](#)
 - 3.15.18: [kubectl create service](#)
 - 3.15.19: [kubectl create service clusterip](#)
 - 3.15.20: [kubectl create service externalname](#)
 - 3.15.21: [kubectl create service loadbalancer](#)
 - 3.15.22: [kubectl create service nodeport](#)
 - 3.15.23: [kubectl create serviceaccount](#)
 - 3.15.24: [kubectl create token](#)
- 3.16: [kubectl debug](#)
- 3.17: [kubectl delete](#)
- 3.18: [kubectl describe](#)
- 3.19: [kubectl diff](#)
- 3.20: [kubectl drain](#)

- 3.21: [kubectl edit](#)
- 3.22: [kubectl events](#)
- 3.23: [kubectl exec](#)
- 3.24: [kubectl explain](#)
- 3.25: [kubectl expose](#)
- 3.26: [kubectl get](#)
- 3.27: [kubectl kuberc](#)
 - 3.27.1: [kubectl kuberc set](#)
 - 3.27.2: [kubectl kuberc view](#)
- 3.28: [kubectl kustomize](#)
- 3.29: [kubectl label](#)
- 3.30: [kubectl logs](#)
- 3.31: [kubectl options](#)
- 3.32: [kubectl patch](#)
- 3.33: [kubectl plugin](#)
 - 3.33.1: [kubectl plugin list](#)
- 3.34: [kubectl port-forward](#)
- 3.35: [kubectl proxy](#)
- 3.36: [kubectl replace](#)
- 3.37: [kubectl rollout](#)
 - 3.37.1: [kubectl rollout history](#)
 - 3.37.2: [kubectl rollout pause](#)
 - 3.37.3: [kubectl rollout restart](#)
 - 3.37.4: [kubectl rollout resume](#)
 - 3.37.5: [kubectl rollout status](#)
 - 3.37.6: [kubectl rollout undo](#)
- 3.38: [kubectl run](#)
- 3.39: [kubectl scale](#)
- 3.40: [kubectl set](#)
 - 3.40.1: [kubectl set env](#)
 - 3.40.2: [kubectl set image](#)
 - 3.40.3: [kubectl set resources](#)
 - 3.40.4: [kubectl set selector](#)
 - 3.40.5: [kubectl set serviceaccount](#)
 - 3.40.6: [kubectl set subject](#)
- 3.41: [kubectl taint](#)
- 3.42: [kubectl top](#)

- 3.42.1: [kubectl top node](#)
- 3.42.2: [kubectl top pod](#)
- 3.43: [kubectl uncordon](#)
- 3.44: [kubectl version](#)
- 3.45: [kubectl wait](#)
- 4: [kubectl Commands](#)
- 5: [kubectl](#)
- 6: [JSONPath Support](#)
- 7: [kubectl for Docker Users](#)
- 8: [kubectl Usage Conventions](#)
- 9: [Kubectl user preferences \(kuberc\)](#)

Kubernetes provides a command line tool for communicating with a Kubernetes cluster's control plane, using the Kubernetes API.

This tool is named `kubectl`.

For configuration, `kubectl` looks for a file named `config` in the `$HOME/.kube` directory. You can specify other `kubeconfig` files by setting the `KUBECONFIG` environment variable or by setting the `--kubeconfig` flag.

This overview covers `kubectl` syntax, describes the command operations, and provides common examples. For details about each command, including all the supported flags and subcommands, see the [kubectl](#) reference documentation.

For an overview, see [The kubectl command-line tool](#). For installation instructions, see [Installing kubectl](#); for a quick guide, see the [cheat sheet](#). If you're used to using the `docker` command-line tool, [kubectl for Docker Users](#) explains some equivalent commands for Kubernetes.

Syntax

Use the following syntax to run `kubectl` commands from your terminal window:

```
kubectl [command] [TYPE] [NAME] [flags]
```

where `command`, `TYPE`, `NAME`, and `flags` are:

- `command`: Specifies the operation that you want to perform on one or more resources, for example `create`, `get`, `describe`, `delete`.

- **TYPE** : Specifies the [resource type](#). Resource types are case-insensitive and you can specify the singular, plural, or abbreviated forms. For example, the following commands produce the same output:

```
kubectl get pod pod1
kubectl get pods pod1
kubectl get po pod1
```

- **NAME** : Specifies the name of the resource. Names are case-sensitive. If the name is omitted, details for all resources are displayed, for example `kubectl get pods`.

When performing an operation on multiple resources, you can specify each resource by type and name or specify one or more files:

- To specify resources by type and name:
 - To group resources if they are all the same type: `TYPE1 name1 name2 name<#>` .
Example: `kubectl get pod example-pod1 example-pod2`
 - To specify multiple resource types individually: `TYPE1/name1 TYPE1/name2 TYPE2/name3 TYPE<#>/name<#>` .
Example: `kubectl get pod/example-pod1 replicationcontroller/example-rc1`
- To specify resources with one or more files: `-f file1 -f file2 -f file<#>`
 - Use YAML rather than JSON since YAML tends to be more user-friendly, especially for configuration files.
Example: `kubectl get -f ./pod.yaml`
- **flags** : Specifies optional flags. For example, you can use the `-s` or `--server` flags to specify the address and port of the Kubernetes API server.

Caution:

Flags that you specify from the command line override default values and any corresponding environment variables.

If you need help, run `kubectl help` from the terminal window.

In-cluster authentication and namespace overrides

By default `kubectl` will first determine if it is running within a pod, and thus in a cluster. It starts by checking for the `KUBERNETES_SERVICE_HOST` and `KUBERNETES_SERVICE_PORT` environment variables and the existence of a service account token file at `/var/run/secrets/kubernetes.io/serviceaccount/token`. If all three are found in-cluster authentication is assumed.

To maintain backwards compatibility, if the `POD_NAMESPACE` environment variable is set during in-cluster authentication it will override the default namespace from the service account token. Any manifests or tools relying on namespace defaulting will be affected by this.

`POD_NAMESPACE` environment variable

If the `POD_NAMESPACE` environment variable is set, cli operations on namespaced resources will default to the variable value. For example, if the variable is set to `seattle`, `kubectl get pods` would return pods in the `seattle` namespace. This is because pods are a namespaced resource, and no namespace was provided in the command. Review the output of `kubectl api-resources` to determine if a resource is namespaced.

Explicit use of `--namespace <value>` overrides this behavior.

How kubectl handles ServiceAccount tokens

If:

- there is Kubernetes service account token file mounted at `/var/run/secrets/kubernetes.io/serviceaccount/token`, and
- the `KUBERNETES_SERVICE_HOST` environment variable is set, and
- the `KUBERNETES_SERVICE_PORT` environment variable is set, and
- you don't explicitly specify a namespace on the kubectl command line

then kubectl assumes it is running in your cluster. The kubectl tool looks up the namespace of that ServiceAccount (this is the same as the namespace of the Pod) and acts against that namespace. This is different from what happens outside of a cluster; when kubectl runs outside a cluster and you don't specify a namespace, the kubectl command acts against the namespace set for the current context in your client configuration. To change the default namespace for your kubectl you can use the following command:

```
kubectl config set-context --current --namespace=<namespace-name>
```

Operations

The following table includes short descriptions and the general syntax for all of the `kubectl` operations:

Operation	Syntax	Description
alpha	<code>kubectl alpha SUBCOMMAND [flags]</code>	List the available commands that correspond to alpha features, which are not enabled in Kubernetes clusters by default.
annotate	<code>kubectl annotate (-f FILENAME TYPE NAME TYPE/NAME) KEY_1=VAL_1 ... KEY_N=VAL_N [--overwrite] [--all] [--resource-version=version] [flags]</code>	Add or update the annotations of one or more resources.
api-resources	<code>kubectl api-resources [flags]</code>	List the API resources that are available.
api-versions	<code>kubectl api-versions [flags]</code>	List the API versions that are available.
apply	<code>kubectl apply -f FILENAME [flags]</code>	Apply a configuration change to a resource from a file or stdin.
attach	<code>kubectl attach POD -c CONTAINER [-i] [-t] [flags]</code>	Attach to a running container either to view the output stream or interact with the container (stdin).
auth	<code>kubectl auth [flags] [options]</code>	Inspect authorization.
autoscale	<code>kubectl autoscale (-f FILENAME TYPE NAME TYPE/NAME) [--min=MINPODS] --max=MAXPODS [--cpu=CPU] [flags]</code>	Automatically scale the set of pods that are managed by a replication controller.
certificate	<code>kubectl certificate SUBCOMMAND [options]</code>	Modify certificate resources.

Operation	Syntax	Description
cluster-info	<code>kubectl cluster-info [flags]</code>	Display endpoint information about the master and services in the cluster.
completion	<code>kubectl completion SHELL [options]</code>	Output shell completion code for the specified shell (bash or zsh).
config	<code>kubectl config SUBCOMMAND [flags]</code>	Modifies kubeconfig files. See the individual subcommands for details.
convert	<code>kubectl convert -f FILENAME [options]</code>	Convert config files between different API versions. Both YAML and JSON formats are accepted. Note - requires <code>kubectl-convert</code> plugin to be installed.
cordon	<code>kubectl cordon NODE [options]</code>	Mark node as unschedulable.
cp	<code>kubectl cp <file-spec-src> <file-spec-dest> [options]</code>	Copy files and directories to and from containers.
create	<code>kubectl create -f FILENAME [flags]</code>	Create one or more resources from a file or stdin.
delete	<code>kubectl delete (-f FILENAME TYPE [NAME /NAME -l label --all]) [flags]</code>	Delete resources either from a file, stdin, or specifying label selectors, names, resource selectors, or resources.
describe	<code>kubectl describe (-f FILENAME TYPE [NAME_PREFIX /NAME -l label]) [flags]</code>	Display the detailed state of one or more resources.
diff	<code>kubectl diff -f FILENAME [flags]</code>	Diff file or stdin against live configuration.

Operation	Syntax	Description
drain	<code>kubectl drain NODE [options]</code>	Drain node in preparation for maintenance.
edit	<code>kubectl edit (-f FILENAME TYPE NAME TYPE/NAME) [flags]</code>	Edit and update the definition of one or more resources on the server by using the default editor.
events	<code>kubectl events</code>	List events
exec	<code>kubectl exec POD [-c CONTAINER] [-i] [-t] [flags] [-- COMMAND [args...]]</code>	Execute a command against a container in a pod.
explain	<code>kubectl explain TYPE [-- recursive=false] [flags]</code>	Get documentation of various resources. For instance pods, nodes, services, etc.
expose	<code>kubectl expose (-f FILENAME TYPE NAME TYPE/NAME) [-- port=port] [--protocol=TCP UDP] [--target-port=number-or-name] [--name=name] [--external-ip=external-ip-of-service] [--type=type] [flags]</code>	Expose a replication controller, service, or pod as a new Kubernetes service.
get	<code>kubectl get (-f FILENAME TYPE [NAME /NAME -l label]) [-- watch] [--sort-by=FIELD] [--output=OUTPUT_FORMAT] [flags]</code>	List one or more resources.

Operation	Syntax	Description
kustomize	<code>kubectl kustomize <dir> [flags] [options]</code>	List a set of API resources generated from instructions in a kustomization.yaml file. The argument must be the path to the directory containing the file, or a git repository URL with a path suffix specifying same with respect to the repository root.
label	<code>kubectl label (-f FILENAME TYPE NAME TYPE/NAME) KEY_1=VAL_1 ... KEY_N=VAL_N [-- overwrite] [--all] [--resource- version=version] [flags]</code>	Add or update the labels of one or more resources.
logs	<code>kubectl logs POD [-c CONTAINER] [--follow] [flags]</code>	Print the logs for a container in a pod.
options	<code>kubectl options</code>	List of global command-line options, which apply to all commands.
patch	<code>kubectl patch (-f FILENAME TYPE NAME TYPE/NAME) --patch PATCH [flags]</code>	Update one or more fields of a resource by using the strategic merge patch process.
plugin	<code>kubectl plugin [flags] [options]</code>	Provides utilities for interacting with plugins.
port-forward	<code>kubectl port-forward POD [LOCAL_PORT:]REMOTE_PORT [... [LOCAL_PORT_N:]REMOTE_PORT_N] [flags]</code>	Forward one or more local ports to a pod.
proxy	<code>kubectl proxy [--port=PORT] [-- www=static-dir] [--www- prefix=prefix] [--api- prefix=prefix] [flags]</code>	Run a proxy to the Kubernetes API server.

Operation	Syntax	Description
replace	<code>kubectl replace -f FILENAME</code>	Replace a resource from a file or stdin.
rollout	<code>kubectl rollout SUBCOMMAND [options]</code>	Manage the rollout of a resource. Valid resource types include: deployments, daemonsets and statefulsets.
run	<code>kubectl run NAME --image=image [--env="key=value"] [--port=port] [--dry-run=server client none] [--overrides=inline-json] [flags]</code>	Run a specified image on the cluster.
scale	<code>kubectl scale (-f FILENAME TYPE NAME TYPE/NAME) --replicas=COUNT [--resource-version=version] [--current-replicas=count] [flags]</code>	Update the size of the specified replication controller.
set	<code>kubectl set SUBCOMMAND [options]</code>	Configure application resources.
taint	<code>kubectl taint NODE NAME KEY_1=VAL_1:TAINT_EFFECT_1 ... KEY_N=VAL_N:TAINT_EFFECT_N [options]</code>	Update the taints on one or more nodes.
top	<code>kubectl top (POD NODE) [flags] [options]</code>	Display Resource (CPU/Memory/Storage) usage of pod or node.
uncordon	<code>kubectl uncordon NODE [options]</code>	Mark node as schedulable.
version	<code>kubectl version [--client] [flags]</code>	Display the Kubernetes version running on the client and server.
wait	<code>kubectl wait ([-f FILENAME] resource.group/resource.name resource.group [(-l label --</code>	Experimental: Wait for a specific condition on one or many resources.

Operation	Syntax	Description
	all)) [--for=delete --for condition=available] [options]	

To learn more about command operations, see the [kubectl](#) reference documentation.

Resource types

The following table includes a list of all the supported resource types and their abbreviated aliases.

(This output can be retrieved from `kubectl api-resources`, and was accurate as of Kubernetes 1.25.0)

NAME	SHORTNAMES	APIVERSION
bindings		v1
componentstatuses	cs	v1
configmaps	cm	v1
endpoints	ep	v1
events	ev	v1
limitranges	limits	v1
namespaces	ns	v1
nodes	no	v1
persistentvolumeclaims	pvc	v1
persistentvolumes	pv	v1
Pods	po	v1
podtemplates		v1
replicationcontrollers	rc	v1
resourcequotas	quota	v1
secrets		v1
serviceaccounts	sa	v1

NAME	SHORTNAMES	APIVERSION
services	svc	v1
mutatingwebhookconfigurations		admissionregistration.k8s.io/
validatingwebhookconfigurations		admissionregistration.k8s.io/
customresourcedefinitions	crd,crds	apiextensions.k8s.io/v1
apiservices		apiregistration.k8s.io/v1
controllerrevisions		apps/v1
daemonsets	ds	apps/v1
deployments	deploy	apps/v1
replicasets	rs	apps/v1
statefulsets	sts	apps/v1
tokenreviews		authentication.k8s.io/v1
localsubjectaccessreviews		authorization.k8s.io/v1
selfsubjectaccessreviews		authorization.k8s.io/v1
selfsubjectrulesreviews		authorization.k8s.io/v1
subjectaccessreviews		authorization.k8s.io/v1
horizontalpodautoscalers	hpa	autoscaling/v2
cronjobs	cj	batch/v1
jobs		batch/v1
certificatesigningrequests	csr	certificates.k8s.io/v1
leases		coordination.k8s.io/v1
endpointslices		discovery.k8s.io/v1
events	ev	events.k8s.io/v1
flowschemas		flowcontrol.apiserver.k8s.io/v1

NAME	SHORTNAMES	APIVERSION
prioritylevelconfigurations		flowcontrol.apiserver.k8s.io/v1
ingressclasses		networking.k8s.io/v1
ingresses	ing	networking.k8s.io/v1
networkpolicies	netpol	networking.k8s.io/v1
runtimeclasses		node.k8s.io/v1
poddisruptionbudgets	pdb	policy/v1
podsecuritypolicies	psp	policy/v1beta1
clusterrolebindings		rbac.authorization.k8s.io/v1
clusterroles		rbac.authorization.k8s.io/v1
rolebindings		rbac.authorization.k8s.io/v1
roles		rbac.authorization.k8s.io/v1
priorityclasses	pc	scheduling.k8s.io/v1
csidrivers		storage.k8s.io/v1
csinodes		storage.k8s.io/v1
csistoragecapacities		storage.k8s.io/v1
storageclasses	sc	storage.k8s.io/v1
volumeattachments		storage.k8s.io/v1

Output options

Use the following sections for information about how you can format or sort the output of certain commands. For details about which commands support the various output options, see the [kubect1](#) reference documentation.

Formatting output

The default output format for all `kubect1` commands is the human readable plain-text format. To output details to your terminal window in a specific format, you can add either the `-o` or `--output` flags to a supported `kubect1` command.

Syntax

```
kubectl [command] [TYPE] [NAME] -o <output_format>
```

Depending on the `kubectl` operation, the following output formats are supported:

Output format	Description
<code>-o custom-columns=<spec></code>	Print a table using a comma separated list of custom columns .
<code>-o custom-columns-file=<filename></code>	Print a table using the custom columns template in the <code><filename></code> file.
<code>-o json</code>	Output a JSON formatted API object.
<code>-o jsonpath=<template></code>	Print the fields defined in a jsonpath expression.
<code>-o jsonpath-file=<filename></code>	Print the fields defined by the jsonpath expression in the <code><filename></code> file.
<code>-o yaml</code>	Output a KYAML formatted API object.
<code>-o name</code>	Print only the resource name and nothing else.
<code>-o wide</code>	Output in the plain-text format with any additional information. For pods, the node name is included.
<code>-o yaml</code>	Output a YAML formatted API object. KYAML is a Kubernetes-specific dialect of YAML, and can be parsed as YAML.

Example

In this example, the following command outputs the details for a single pod as a YAML formatted object:

```
kubectl get pod web-pod-13je7 -o yaml
```

Remember: See the [kubectl](#) reference documentation for details about which output format is supported by each command.

Custom columns

To define custom columns and output only the details that you want into a table, you can use the `custom-columns` option. You can choose to define the custom columns inline or use a template file: `-o custom-columns=<spec>` Or `-o custom-columns-file=<filename>`.

Examples

Inline:

```
kubectl get pods <pod-name> -o custom-columns=NAME:.metadata.name,RSRC:.metadata.re
```

Template file:

```
kubectl get pods <pod-name> -o custom-columns-file=template.txt
```

where the `template.txt` file contains:

NAME	RSRC
metadata.name	metadata.resourceVersion

The result of running either command is similar to:

NAME	RSRC
submit-queue	610995

Server-side columns

`kubectl` supports receiving specific column information from the server about objects. This means that for any given resource, the server will return columns and rows relevant to that resource, for the client to print. This allows for consistent human-readable output across clients used against the same cluster, by having the server encapsulate the details of printing.

This feature is enabled by default. To disable it, add the `--server-print=false` flag to the `kubectl get` command.

Examples

To print information about the status of a pod, use a command like the following:

```
kubectl get pods <pod-name> --server-print=false
```

The output is similar to:

NAME	AGE
pod-name	1m

Sorting list objects

To output objects to a sorted list in your terminal window, you can add the `--sort-by` flag to a supported `kubectl` command. Sort your objects by specifying any numeric or string field with the `--sort-by` flag. To specify a field, use a [jsonpath](#) expression.

Syntax

```
kubectl [command] [TYPE] [NAME] --sort-by=<jsonpath_exp>
```

Example

To print a list of pods sorted by name, you run:

```
kubectl get pods --sort-by=.metadata.name
```

Examples: Common operations

Use the following set of examples to help you familiarize yourself with running the commonly used `kubectl` operations:

`kubectl apply` - Apply or Update a resource from a file or stdin.

Create a service using the definition in example-service.yaml.

```
kubectl apply -f example-service.yaml
```

Create a replication controller using the definition in example-controller.yaml.

```
kubectl apply -f example-controller.yaml
```

Create the objects that are defined in any .yaml, .yml, or .json file within the

```
kubectl apply -f <directory>
```

`kubectl get` - List one or more resources.

List all pods in plain-text output format.

```
kubectl get pods
```

List all pods in plain-text output format and include additional information (such as IP address).

```
kubectl get pods -o wide
```

List the replication controller with the specified name in plain-text output format.

```
kubectl get replicationcontroller <rc-name>
```

List all replication controllers and services together in plain-text output format.

```
kubectl get rc,services
```

List all daemon sets in plain-text output format.

```
kubectl get ds
```

List all pods running on node server01

```
kubectl get pods --field-selector=spec.nodeName=server01
```

`kubectl describe` - Display detailed state of one or more resources, including the uninitialized ones by default.

Display the details of the node with name <node-name>.

```
kubectl describe nodes <node-name>
```

Display the details of the pod with name <pod-name>.

```
kubectl describe pods/<pod-name>
```

Display the details of all the pods that are managed by the replication controller.

Remember: Any pods that are created by the replication controller get prefixed with <rc-name>.

```
kubectl describe pods <rc-name>
```

Describe all pods

```
kubectl describe pods
```

Note:

The `kubectl get` command is usually used for retrieving one or more resources of the same resource type. It features a rich set of flags that allows you to customize the output format using the `-o` or `--output` flag, for example. You can specify the `-w`

or `--watch` flag to start watching updates to a particular object. The `kubectl describe` command is more focused on describing the many related aspects of a specified resource. It may invoke several API calls to the API server to build a view for the user. For example, the `kubectl describe node` command retrieves not only the information about the node, but also a summary of the pods running on it, the events generated for the node etc.

`kubectl delete` - Delete resources either from a file, stdin, or specifying label selectors, names, resource selectors, or resources.

Delete a pod using the type and name specified in the pod.yaml file.

```
kubectl delete -f pod.yaml
```

Delete all the pods and services that have the label '<label-key>=<label-value>'

```
kubectl delete pods,services -l <label-key>=<label-value>
```

Delete all pods, including uninitialized ones.

```
kubectl delete pods --all
```

`kubectl exec` - Execute a command against a container in a pod.

Get output from running 'date' from pod <pod-name>. By default, output is from the first container.

```
kubectl exec <pod-name> -- date
```

Get output from running 'date' in container <container-name> of pod <pod-name>.

```
kubectl exec <pod-name> -c <container-name> -- date
```

Get an interactive TTY and run /bin/bash from pod <pod-name>. By default, output is from the first container.

```
kubectl exec -ti <pod-name> -- /bin/bash
```

`kubectl logs` - Print the logs for a container in a pod.

Return a snapshot of the Logs from pod <pod-name>.

```
kubectl logs <pod-name>
```

Start streaming the Logs from pod <pod-name>. This is similar to the 'tail -f' L

```
kubectl logs -f <pod-name>
```



`kubectl diff` - View a diff of the proposed updates to a cluster.

Diff resources included in "pod.json".

```
kubectl diff -f pod.json
```

Diff file read from stdin.

```
cat service.yaml | kubectl diff -f -
```

Examples: Creating and using plugins

Use the following set of examples to help you familiarize yourself with writing and using `kubectl` plugins:

create a simple plugin in any language and name the resulting executable file

so that it begins with the prefix "kubectl-"

```
cat ./kubectl-hello
```

```
#!/bin/sh
```

this plugin prints the words "hello world"

```
echo "hello world"
```

With a plugin written, let's make it executable:

```
chmod a+x ./kubectl-hello
```

and move it to a location in our PATH

```
sudo mv ./kubectl-hello /usr/local/bin
```

```
sudo chown root:root /usr/local/bin
```

You have now created and "installed" a kubectl plugin.


```
# You can begin using this plugin by invoking it from kubectl as if it were a regular command  
kubectl hello
```

```
hello world
```

```
# You can "uninstall" a plugin, by removing it from the folder in your $PATH where you placed it  
sudo rm /usr/local/bin/kubectl-hello
```

In order to view all of the plugins that are available to `kubectl`, use the `kubectl plugin list` subcommand:

```
kubectl plugin list
```

The output is similar to:

```
The following kubectl-compatible plugins are available:
```

```
/usr/local/bin/kubectl-hello  
/usr/local/bin/kubectl-foo  
/usr/local/bin/kubectl-bar
```

`kubectl plugin list` also warns you about plugins that are not executable, or that are shadowed by other plugins; for example:

```
sudo chmod -x /usr/local/bin/kubectl-foo # remove execute permission  
kubectl plugin list
```

```
The following kubectl-compatible plugins are available:
```

```
/usr/local/bin/kubectl-hello  
/usr/local/bin/kubectl-foo  
  - warning: /usr/local/bin/kubectl-foo identified as a plugin, but it is not executable  
/usr/local/bin/kubectl-bar
```

```
error: one plugin warning was found
```

You can think of plugins as a means to build more complex functionality on top of the existing kubectl commands:

```
cat ./kubectl-whoami
```

The next few examples assume that you already made `kubectl-whoami` have the following contents:

```
#!/bin/bash

# this plugin makes use of the `kubectl config` command in order to output
# information about the current user, based on the currently selected context
kubectl config view --template='{{ range .contexts }}{{ if eq .name "$(kubectl config view --template="{{ range .contexts }}" | jq -r ".current-context")" }}{{ print "\nCurrent user: plugins-user" }}
```

Running the above command gives you an output containing the user for the current context in your KUBECONFIG file:

```
# make the file executable
sudo chmod +x ./kubectl-whoami

# and move it into your PATH
sudo mv ./kubectl-whoami /usr/local/bin

kubectl whoami
Current user: plugins-user
```

What's next

- Read the `kubectl` reference documentation:
 - the [kubectl command reference](#)
 - the [command line arguments](#) reference
- Learn about [kubectl usage conventions](#)
- Read about [JSONPath support](#) in kubectl

- Read about how to [extend kubectl with plugins](#)
 - To find out more about plugins, take a look at the [example CLI plugin](#).

1 - Introduction to kubectl

kubectl is a command-line tool for interacting with Kubernetes clusters, using the Kubernetes API. Use it to deploy applications, inspect resources, and manage workloads.

While this Book is focused on using kubectl to declaratively manage applications in Kubernetes, it also covers other kubectl functions.

Command Families

Most kubectl commands typically fall into one of a few categories:

Type	Used For	Description
Declarative Resource Management	Deployment and operations (e.g. GitOps)	Declaratively manage Kubernetes workloads using resource configuration
Imperative Resource Management	Development Only	Run commands to manage Kubernetes workloads using Command Line arguments and flags
Printing Workload State	Debugging	Print information about workloads
Interacting with Containers	Debugging	Exec, attach, cp, logs
Cluster Management	Cluster operations	Drain and cordon Nodes

Declarative Application Management

The preferred approach for managing resources is through declarative files called resource configuration used with the kubectl *Apply* command. This command reads a local (or remote) file structure and modifies cluster state to reflect the declared intent.

Apply

Apply is the preferred mechanism for managing resources in a Kubernetes cluster.

Printing State about Workloads

Users will need to view workload state.

- Printing summarize state and information about resources
- Printing complete state and information about resources
- Printing specific fields from resources
- Query resources matching labels

Debugging Workloads

kubectl supports debugging by providing commands for:

- Printing Container logs
- Printing cluster events
- Exec or attaching to a Container
- Copying files from Containers in the cluster to a user's filesystem

Cluster Management

On occasion, users may need to perform operations to the Nodes of cluster. kubectl supports commands to drain workloads from a Node so that it can be decommissioned or debugged.

Porcelain

Users may find using resource configuration overly verbose for *development* and prefer to work with the cluster *imperatively* with a shell-like workflow. kubectl offers porcelain commands for generating and modifying resources.

- Generating + creating resources such as Deployments, StatefulSets, Services, ConfigMaps, etc.
- Setting fields on resources
- Editing (live) resources in a text editor

Porcelain for Dev Only

Porcelain commands are time saving for experimenting with workloads in a dev cluster, but shouldn't be used for production.

2 - kubectl Quick Reference

This page contains a list of commonly used `kubectl` commands and flags.

Note:

These instructions are for Kubernetes v1.37. To check the version, use the `kubectl version` command.

Kubectl autocomplete

BASH

```
source <(kubectl completion bash) # set up autocomplete in bash into the current shell
echo "source <(kubectl completion bash)" >> ~/.bashrc # add autocomplete permanently
```

You can also use a shorthand alias for `kubectl` that also works with completion:

```
alias k=kubectl
complete -o default -F __start_kubectl k
```

ZSH

```
source <(kubectl completion zsh) # set up autocomplete in zsh into the current shell
echo '[[ $commands[kubectl] ]] && source <(kubectl completion zsh)' >> ~/.zshrc # add autocomplete permanently
```

FISH

Note:

Requires `kubectl` version 1.23 or above.

```
echo 'kubectl completion fish | source' > ~/.config/fish/completions/kubectl.fish
```

A note on --all-namespaces

Appending `--all-namespaces` happens frequently enough that you should be aware of the shorthand for `--all-namespaces` :

```
kubectl -A
```

Kubectl context and configuration

Set which Kubernetes cluster `kubectl` communicates with and modifies configuration information. See [Authenticating Across Clusters with kubeconfig](#) documentation for detailed config file information.

```
kubectl config view # Show Merged kubeconfig settings.
```

```
# use multiple kubeconfig files at the same time and view merged config
KUBECONFIG=~/.kube/config:~/.kube/kubconfig2
```

```
kubectl config view
```

```
# Show merged kubeconfig settings and raw certificate data and exposed secrets
kubectl config view --raw
```

```
# get the password for the e2e user
```

```
kubectl config view -o jsonpath='{.users[?(@.name == "e2e")].user.password}'
```

```
# get the certificate for the e2e user
```

```
kubectl config view --raw -o jsonpath='{.users[?(@.name == "e2e")].user.client-certificate}'
```

```
kubectl config view -o jsonpath='{.users[0].name}' # display the first user
```

```
kubectl config view -o jsonpath='{.users[*].name}' # get a list of users
```

```
kubectl config get-contexts # display list of contexts
```

```
kubectl config get-contexts -o name # get all context names
```

```
kubectl config current-context # display the current-context
```

```
kubectl config use-context my-cluster-name # set the default context to my-cluster-name
```

```
kubectl config set-cluster my-cluster-name # set a cluster entry in the kubeconfig
```

```
# configure the URL to a proxy server to use for requests made by this client in the cluster
```

```
kubectl config set-cluster my-cluster-name --proxy-url=my-proxy-url
```

```

# add a new user to your kubeconf that supports basic auth
kubectl config set-credentials kubeuser/foo.kubernetes.com --username=kubeuser --password=kubeuser

# permanently save the namespace for all subsequent kubectl commands in that context
kubectl config set-context --current --namespace=ggckad-s2

# set a context utilizing a specific username and namespace.
kubectl config set-context gce --user=cluster-admin --namespace=foo \
    && kubectl config use-context gce

kubectl config unset users.foo # delete user foo

# short alias to set/show context/namespace (only works for bash and bash-compatible shells)
alias kx='f() { [ "$1" ] && kubectl config use-context $1 || kubectl config current-context >>> $1; }'
alias kn='f() { [ "$1" ] && kubectl config set-context --current --namespace $1 || kubectl config current-context >>> $1; }'

```

Kubectl apply

`apply` manages applications through files defining Kubernetes resources. It creates and updates resources in a cluster through running `kubectl apply`. This is the recommended way of managing Kubernetes applications on production. See [Kubectl Book](#).

Creating objects

Kubernetes manifests can be defined in YAML or JSON. The file extension `.yaml`, `.yml`, and `.json` can be used.

```

kubectl apply -f ./my-manifest.yaml # create resource(s)
kubectl apply -f ./my1.yaml -f ./my2.yaml # create from multiple files
kubectl apply -f ./dir # create resource(s) in all manifest files in dir
kubectl apply -f https://example.com/manifest.yaml # create resource(s) from url
kubectl create deployment nginx --image=nginx # start a single instance of nginx

# create a Job which prints "Hello World"
kubectl create job hello --image=busybox:1.28 -- echo "Hello World"

# create a CronJob that prints "Hello World" every minute
kubectl create cronjob hello --image=busybox:1.28 --schedule="*/1 * * * *" -- echo "Hello World"

kubectl explain pods # get the documentation for pod manifest

```



```
# Create multiple YAML objects from stdin
```

```
kubectl apply -f - <<EOF
```

```
apiVersion: v1
```

```
kind: Pod
```

```
metadata:
```

```
  name: busybox-sleep
```

```
spec:
```

```
  containers:
```

```
  - name: busybox
```

```
    image: busybox:1.28
```

```
    args:
```

```
    - sleep
```

```
    - "1000000"
```

```
---
```

```
apiVersion: v1
```

```
kind: Pod
```

```
metadata:
```

```
  name: busybox-sleep-less
```

```
spec:
```

```
  containers:
```

```
  - name: busybox
```

```
    image: busybox:1.28
```

```
    args:
```

```
    - sleep
```

```
    - "1000"
```

```
EOF
```

```
# Create a secret with several keys
```

```
kubectl apply -f - <<EOF
```

```
apiVersion: v1
```

```
kind: Secret
```

```
metadata:
```

```
  name: mysecret
```

```
type: Opaque
```

```
data:
```

```
  password: $(echo -n "s33msi4" | base64 -w0)
```

```
  username: $(echo -n "jane" | base64 -w0)
```

```
EOF
```

Viewing and finding resources

```
# Get commands with basic output
```

```
kubectl get services
```

```
kubectl get pods --all-namespaces
```

```
# List all services in the namespace
```

```
# List all pods in all namespaces
```

```

kubect1 get pods -o wide           # List all pods in the current namespace
kubect1 get deployment my-dep      # List a particular deployment
kubect1 get pods                   # List all pods in the namespace
kubect1 get pod my-pod -o yaml     # Get a pod's YAML

# Describe commands with verbose output
kubect1 describe nodes my-node
kubect1 describe pods my-pod

# List Services Sorted by Name
kubect1 get services --sort-by=.metadata.name

# List pods Sorted by Restart Count
kubect1 get pods --sort-by='.status.containerStatuses[0].restartCount'

# List PersistentVolumes sorted by capacity
kubect1 get pv --sort-by=.spec.capacity.storage

# Get the version label of all pods with Label app=cassandra
kubect1 get pods --selector=app=cassandra -o \
  jsonpath='{.items[*].metadata.labels.version}'

# Retrieve the value of a key with dots, e.g. 'ca.crt'
kubect1 get configmap myconfig \
  -o jsonpath='{.data.ca\.crt}'

# Retrieve a base64 encoded value with dashes instead of underscores.
kubect1 get secret my-secret --template='{{index .data "key-name-with-dashes"}}'

# Get all worker nodes (use a selector to exclude results that have a Label
# named 'node-role.kubernetes.io/control-plane')
kubect1 get node --selector='!node-role.kubernetes.io/control-plane'

# Get all running pods in the namespace
kubect1 get pods --field-selector=status.phase=Running

# Get ExternalIPs of all nodes
kubect1 get nodes -o jsonpath='{.items[*].status.addresses[?(@.type=="ExternalIP")]'

# List Names of Pods that belong to Particular RC
# "jq" command useful for transformations that are too complex for jsonpath, it can
sel=${$(kubect1 get rc my-rc --output=json | jq -j '.spec.selector | to_entries |
echo ${kubect1 get pods --selector=$sel --output=jsonpath='{.items..metadata.name}')}

# Show Labels for all pods (or any other Kubernetes object that supports Labelling,
kubect1 get pods --show-labels

# Check which nodes are ready
JSONPATH='{range .items[*]}{@.metadata.name}:{range @.status.conditions[*]}{@.type}{'

```

```

&& kubectl get nodes -o jsonpath="$JSONPATH" | grep "Ready=True"

# Check which nodes are ready with custom-columns
kubectl get node -o custom-columns='NODE_NAME:.metadata.name,STATUS:.status.conditions[0].status'

# Output decoded secrets without external tools
kubectl get secret my-secret -o go-template='{{range $k,$v := .data}}{{"### "}}{{$k}}\n{{end}}'

# List all Secrets currently in use by a pod
kubectl get pods -o json | jq '.items[].spec.containers[].env[]?.valueFrom.secretKeyRef'

# List all containerIDs of initContainer of all pods
# Helpful when cleaning up stopped containers, while avoiding removal of initContainers
kubectl get pods --all-namespaces -o jsonpath='{range .items[*].status.initContainers[*].id}{{.}}\n{{end}}'

# List Events sorted by timestamp
kubectl get events --sort-by=.metadata.creationTimestamp

# List all warning events
kubectl events --types=Warning

# Compares the current state of the cluster against the state that the cluster would have been in if the given manifest was applied
kubectl diff -f ./my-manifest.yaml

# Produce a period-delimited tree of all keys returned for nodes
# Helpful when locating a key within a complex nested JSON structure
kubectl get nodes -o json | jq -c 'paths|join(".")'

# Produce a period-delimited tree of all keys returned for pods, etc
kubectl get pods -o json | jq -c 'paths|join(".")'

# Produce ENV for all pods, assuming you have a default container for the pods, deployment
# Helpful when running any supported command across all pods, not just `env`
for pod in $(kubectl get po --output=jsonpath={.items..metadata.name}); do echo $pod; done

# Get a deployment's status subresource
kubectl get deployment nginx-deployment --subresource=status

```

Updating resources

```

kubectl set image deployment/frontend www=image:v2 # Rolling update
kubectl rollout history deployment/frontend # Check the history of deployments
kubectl rollout undo deployment/frontend # Rollback to the previous deployment
kubectl rollout undo deployment/frontend --to-revision=2 # Rollback to a specific revision

```

```

kubect1 rollout status -w deployment/frontend           # Watch rolling up
kubect1 rollout restart deployment/frontend             # Rolling restart

cat pod.json | kubect1 replace -f -                     # Replace a pod by

# Force replace, delete and then re-create the resource. Will cause a service outage
kubect1 replace --force -f ./pod.json

# Create a service for a replicated nginx, which serves on port 80 and connects to
kubect1 expose rc nginx --port=80 --target-port=8000

# Update a single-container pod's image version (tag) to v4
kubect1 get pod mypod -o yaml | sed 's/\(image: myimage\):.*$/\1:v4/' | kubect1 replace -f -

kubect1 label pods my-pod new-label=awesome           # Add a Label
kubect1 label pods my-pod new-label-                 # Remove a Label
kubect1 label pods my-pod new-label=new-value --overwrite # Overwrite an existing label
kubect1 annotate pods my-pod icon-url=http://goo.gl/XXBTWq # Add an annotation
kubect1 annotate pods my-pod icon-url-                 # Remove an annotation
kubect1 autoscale deployment foo --min=2 --max=10     # Auto scale a deployment

```

Patching resources

```

# Partially update a node
kubect1 patch node k8s-node-1 -p '{"spec":{"unschedulable":true}}'

# Update a container's image; spec.containers[*].name is required because it's a merge patch
kubect1 patch pod valid-pod -p '{"spec":{"containers":[{"name":"kubernetes-serve-hosts","image":"gcr.io/google-containers/kubernetes-serve-hosts:v1.0.0"}]}}'

# Update a container's image using a json patch with positional arrays
kubect1 patch pod valid-pod --type='json' -p='[{"op": "replace", "path": "/spec/containers/0/image", "value": "gcr.io/google-containers/kubernetes-serve-hosts:v1.0.0"}]'

# Disable a deployment livenessProbe using a json patch with positional arrays
kubect1 patch deployment valid-deployment --type json -p='[{"op": "remove", "path": "/spec/template/spec/containers/0/livenessProbe"}]'

# Add a new element to a positional array
kubect1 patch sa default --type='json' -p='[{"op": "add", "path": "/secrets/1", "value": {"name": "default", "namespace": "default", "data": {"foo": "bar"}}}]'

# Update a deployment's replica count by patching its scale subresource
kubect1 patch deployment nginx-deployment --subresource='scale' --type='merge' -p '{"spec":{"replicas": 3}}'

```

Editing resources

Edit any API resource in your preferred editor.

```
kubectl edit svc/docker-registry          # Edit the service named docker-registry
KUBE_EDITOR="nano" kubectl edit svc/docker-registry  # Use an alternative editor
```

Scaling resources

```
kubectl scale --replicas=3 rs/foo          # Scale a replication controller
kubectl scale --replicas=3 -f foo.yaml     # Scale a resource defined in a file
kubectl scale --current-replicas=2 --replicas=3 deployment/mysql # If the deployment is scaled
kubectl scale --replicas=5 rc/foo rc/bar rc/baz # Scale multiple resources
```

Deleting resources

```
kubectl delete -f ./pod.json              # Delete a pod using local file
kubectl delete pod unwanted --now         # Delete a pod without waiting
kubectl delete pod,service baz foo        # Delete pods and services
kubectl delete pods,services -l name=myLabel # Delete pods and services with label
kubectl -n my-ns delete pod,svc --all      # Delete all pods and services in namespace
# Delete all pods matching the awk pattern1 or pattern2
kubectl get pods -n mynamespace --no-headers=true | awk '/pattern1|pattern2/{print $1}'
```

Interacting with running Pods

```
kubectl logs my-pod                      # dump pod Logs (stdout)
kubectl logs -l name=myLabel              # dump pod Logs, with label selector
kubectl logs my-pod --previous            # dump pod Logs (stdout) for a previous incarnation
kubectl logs my-pod -c my-container       # dump pod container Logs (stdout)
kubectl logs -l name=myLabel -c my-container # dump pod container Logs, with label selector
kubectl logs my-pod -c my-container --previous # dump pod container Logs (stdout) for a previous incarnation
```

```

kubect1 logs -f my-pod # stream pod logs (stdout)
kubect1 logs -f my-pod -c my-container # stream pod container logs (stdout)
kubect1 logs -f -l name=myLabel --all-containers # stream all pods logs with label
kubect1 run -i --tty busybox --image=busybox:1.28 -- sh # Run pod as interactive shell
kubect1 run nginx --image=nginx -n mynamespace # Start a single instance of nginx
kubect1 run nginx --image=nginx --dry-run=client -o yaml > pod.yaml # Generate spec for running pod
kubect1 attach my-pod -i # Attach to Running Container
kubect1 port-forward my-pod 5000:6000 # Listen on port 5000 on the local machine
kubect1 exec my-pod -- ls / # Run command in existing pod
kubect1 exec --stdin --tty my-pod -- /bin/sh # Interactive shell access to existing pod
kubect1 exec my-pod -c my-container -- ls / # Run command in existing pod
kubect1 debug my-pod -it --image=busybox:1.28 # Create an interactive debugging pod
kubect1 debug node/my-node -it --image=busybox:1.28 # Create an interactive debugging pod
kubect1 top pod # Show metrics for all pods in the cluster
kubect1 top pod POD_NAME --containers # Show metrics for a given pod
kubect1 top pod POD_NAME --sort-by=cpu # Show metrics for a given pod sorted by CPU

```

Copying files and directories to and from containers

```

kubect1 cp /tmp/foo_dir my-pod:/tmp/bar_dir # Copy /tmp/foo_dir local directory to pod
kubect1 cp /tmp/foo my-pod:/tmp/bar -c my-container # Copy /tmp/foo local file to pod
kubect1 cp /tmp/foo my-namespace/my-pod:/tmp/bar # Copy /tmp/foo local file to pod
kubect1 cp my-namespace/my-pod:/tmp/foo /tmp/bar # Copy /tmp/foo from a remote pod

```

Note:

kubect1 cp requires that the 'tar' binary is present in your container image. If 'tar' is not present, kubect1 cp will fail. For advanced use cases, such as symlinks, wildcard expansion or file mode preservation consider using kubect1 exec.

```

tar cf - /tmp/foo | kubect1 exec -i -n my-namespace my-pod -- tar xf - -C /tmp/bar
kubect1 exec -n my-namespace my-pod -- tar cf - /tmp/foo | tar xf - -C /tmp/bar

```

Interacting with Deployments and Services

```
kubectl logs deploy/my-deployment           # dump Pod Logs for a Deployment
kubectl logs deploy/my-deployment -c my-container # dump Pod Logs for a Deployment

kubectl port-forward svc/my-service 5000     # Listen on Local port 5000
kubectl port-forward svc/my-service 5000:my-service-port # Listen on Local port 5000

kubectl port-forward deploy/my-deployment 5000:6000 # Listen on Local port 5000
kubectl exec deploy/my-deployment -- ls          # run command in first Pod
```

Interacting with Nodes and cluster

```
kubectl cordon my-node           # Mark my-node as unschedulable
kubectl drain my-node            # Drain my-node
kubectl uncordon my-node         # Mark my-node as schedulable
kubectl top node                 # Show metrics for all nodes
kubectl top node my-node         # Show metrics for my-node
kubectl cluster-info             # Display additional cluster information
kubectl cluster-info dump        # Dump current cluster information
kubectl cluster-info dump --output-directory=/path/to/cluster-state # Dump current cluster information to a directory

# View existing taints on which exist on current nodes.
kubectl get nodes -o='custom-columns=NodeName:.metadata.name,TaintKey:.spec.taints'

# If a taint with that key and effect already exists, its value is replaced as specified
kubectl taint nodes foo dedicated=special-user:NoSchedule
```

Resource types

List all supported resource types along with their shortnames, [API group](#), whether they are [namespaced](#), and [kind](#):

```
kubectl api-resources
```

Other operations for exploring API resources:

```
kubectl api-resources --namespaced=true      # ALL namespaced resources
kubectl api-resources --namespaced=false     # ALL non-namespaced resources
kubectl api-resources -o name                # ALL resources with simple output (or
kubectl api-resources -o wide                # ALL resources with expanded (aka "w
kubectl api-resources --verbs=list,get       # ALL resources that support the "list
kubectl api-resources --api-group=extensions # ALL resources in the "extensions" API
```

Formatting output

To output details to your terminal window in a specific format, add the `-o` (or `--output`) flag to a supported `kubectl` command.

Output format	Description
<code>-o=custom-columns=<spec></code>	Print a table using a comma separated list of custom columns
<code>-o=custom-columns-file=<filename></code>	Print a table using the custom columns template in the <code><filename></code> file
<code>-o=go-template=<template></code>	Print the fields defined in a golang template
<code>-o=go-template-file=<filename></code>	Print the fields defined by the golang template in the <code><filename></code> file
<code>-o=json</code>	Output a JSON formatted API object
<code>-o=jsonpath=<template></code>	Print the fields defined in a jsonpath expression
<code>-o=jsonpath-file=<filename></code>	Print the fields defined by the jsonpath expression in the <code><filename></code> file
<code>-o=yaml</code>	Output a KYAML formatted API object. KYAML is a Kubernetes-specific dialect of YAML, and can be parsed as YAML.
<code>-o=name</code>	Print only the resource name and nothing else
<code>-o=wide</code>	Output in the plain-text format with any additional information, and for pods, the node name is included
<code>-o=yaml</code>	Output a YAML formatted API object

Examples using `-o=custom-columns` :

All images running in a cluster

```
kubectl get pods -A -o=custom-columns='DATA:spec.containers[*].image'
```

All images running in namespace: default, grouped by Pod

```
kubectl get pods --namespace default --output=custom-columns="NAME:.metadata.name,DATA:spec.containers[*].image"
```

All images excluding "registry.k8s.io/coredns:1.6.2"

```
kubectl get pods -A -o=custom-columns='DATA:spec.containers[?(@.image!="registry.k8s.io/coredns:1.6.2")].image'
```

All fields under metadata regardless of name

```
kubectl get pods -A -o=custom-columns='DATA:metadata.*'
```

More examples in the [kubectl reference documentation](#).

Kubectl output verbosity and debugging

Kubectl verbosity is controlled with the `-v` or `--v` flags followed by an integer representing the log level. General Kubernetes logging conventions and the associated log levels are described [here](#).

Verbosity Description

`--v=0`

Generally useful for this to *always* be visible to a cluster operator.

`--v=1`

A reasonable default log level if you don't want verbosity.

`--v=2`

Useful steady state information about the service and important log messages that may correlate to significant changes in the system. This is the recommended default log level for most systems.

`--v=3`

Extended information about changes.

`--v=4`

Debug level verbosity.

`--v=5`

Trace level verbosity.

`--v=6`

Display requested resources.

`--v=7`

Display HTTP request headers.

`--v=8`

Display HTTP request contents.

Verbosity	Description
-----------	-------------

--v=9	Display HTTP request contents without truncation of contents.
-------	---

What's next

- Learn about [kubectl overview](#) and its role in the Kubernetes ecosystem.
- Read the [kubectl reference](#) and learn about [JsonPath](#).
- See [kubectl](#) options.
- See [kuberc](#) options.
- Also read [kubectl Usage Conventions](#) to understand how to use kubectl in reusable scripts.
- See more community [kubectl cheatsheets](#).

3 - kubectl reference

3.1 - kubectl

kubectl controls the Kubernetes cluster manager

Synopsis

kubectl controls the Kubernetes cluster manager.

Find more information at: <https://kubernetes.io/docs/reference/kubectl/>

```
kubectl [flags]
```

Options

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`-h, --help`

help for kubectl

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token` string

Bearer token for authentication to the API server

`--user` string

The name of the kubeconfig user to use

`--username` string

Username for basic authentication to the API server

`--version` version[=true]

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl annotate](#) - Update the annotations on a resource
- [kubectl api-resources](#) - Print the supported API resources on the server
- [kubectl api-versions](#) - Print the supported API versions on the server, in the form of "group/version"
- [kubectl apply](#) - Apply a configuration to a resource by file name or stdin
- [kubectl attach](#) - Attach to a running container
- [kubectl auth](#) - Inspect authorization
- [kubectl autoscale](#) - Auto-scale a deployment, replica set, stateful set, or replication controller
- [kubectl certificate](#) - Modify certificate resources
- [kubectl cluster-info](#) - Display cluster information
- [kubectl completion](#) - Output shell completion code for the specified shell (bash, zsh, fish, or powershell)
- [kubectl config](#) - Modify kubeconfig files
- [kubectl cordon](#) - Mark node as unschedulable
- [kubectl cp](#) - Copy files and directories to and from containers
- [kubectl create](#) - Create a resource from a file or from stdin
- [kubectl debug](#) - Create debugging sessions for troubleshooting workloads and nodes
- [kubectl delete](#) - Delete resources by file names, stdin, resources and names, or by resources and label selector
- [kubectl describe](#) - Show details of a specific resource or group of resources
- [kubectl diff](#) - Diff the live version against a would-be applied version
- [kubectl drain](#) - Drain node in preparation for maintenance
- [kubectl edit](#) - Edit a resource on the server
- [kubectl events](#) - List events
- [kubectl exec](#) - Execute a command in a container
- [kubectl explain](#) - Get documentation for a resource
- [kubectl expose](#) - Take a replication controller, service, deployment or pod and expose it as a new Kubernetes service
- [kubectl get](#) - Display one or many resources
- [kubectl kuberc](#) - Manage kuberc configuration files
- [kubectl kustomize](#) - Build a kustomization target from a directory or URL
- [kubectl label](#) - Update the labels on a resource
- [kubectl logs](#) - Print the logs for a container in a pod
- [kubectl options](#) - Print the list of flags inherited by all commands

- [kubectl patch](#) - Update fields of a resource
- [kubectl plugin](#) - Provides utilities for interacting with plugins
- [kubectl port-forward](#) - Forward one or more local ports to a pod
- [kubectl proxy](#) - Run a proxy to the Kubernetes API server
- [kubectl replace](#) - Replace a resource by file name or stdin
- [kubectl rollout](#) - Manage the rollout of a resource
- [kubectl run](#) - Run a particular image on the cluster
- [kubectl scale](#) - Set a new size for a deployment, replica set, or replication controller
- [kubectl set](#) - Set specific features on objects
- [kubectl taint](#) - Update the taints on one or more nodes
- [kubectl top](#) - Display resource (CPU/memory) usage
- [kubectl uncordon](#) - Mark node as schedulable
- [kubectl version](#) - Print the client and server version information
- [kubectl wait](#) - Wait for a specific condition on one or many resources

3.2 - kubectl annotate

Update the annotations on a resource

Synopsis

Update the annotations on one or more resources.

All Kubernetes objects support the ability to store additional data with the object as annotations. Annotations are key/value pairs that can be larger than labels and include arbitrary string values such as structured JSON. Tools and system extensions may use annotations to store their own data.

Attempting to set an annotation that already exists will fail unless `--overwrite` is set. If `--resource-version` is specified and does not match the current resource version on the server the command will fail.

Use "kubectl api-resources" for a complete list of supported resources.

```
kubectl annotate [--overwrite] (-f FILENAME | TYPE NAME) KEY_1=VAL_1 ... KEY_N=VAL_N
```

Examples

```
# Update pod 'foo' with the annotation 'description' and the value 'my frontend'
# If the same annotation is set multiple times, only the last value will be applied
kubectl annotate pods foo description='my frontend'

# Update a pod identified by type and name in "pod.json"
kubectl annotate -f pod.json description='my frontend'

# Update pod 'foo' with the annotation 'description' and the value 'my frontend running nginx'
kubectl annotate --overwrite pods foo description='my frontend running nginx'

# Update all pods in the namespace
kubectl annotate pods --all description='my frontend running nginx'

# Update pod 'foo' only if the resource is unchanged from version 1
kubectl annotate pods foo description='my frontend running nginx' --resource-version=1

# Update pod 'foo' by removing an annotation named 'description' if it exists
```

```
# Does not require the --overwrite flag
kubectl annotate pods foo description-
```

Options

`--all`

Select all resources in the namespace of the specified resource types

`-A, --all-namespaces`

If present, list the requested object(s) across all namespaces. Namespace in current context is ignored even if specified with `--namespace`.

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-annotate"

Name of the manager used to track field ownership.

`--field-selector string`

Selector (field query) to filter on, supports '=', '==', and '!='.(e.g. `--field-selector key1=value1,key2=value2`). The server only supports a limited number of field queries per type.

`-f, --filename strings`

identifying the resource.

`-h, --help`

help for annotate

-k, --kustomize string

Process a kustomization directory. This flag can't be used together with -f or -R.

--list

If true, display the annotations for a given resource.

--local

If true, annotation will NOT contact api-server but run locally.

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

--overwrite

If true, allow annotations to be overwritten, otherwise reject annotation updates that overwrite existing annotations.

-R, --recursive Default: true

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

--resource-version string

If non-empty, the annotation update will only succeed if this is the current resource-version for the object. Only valid when specifying a single resource.

-l, --selector string

Selector (label query) to filter on, supports '=', '==', and '!='.(e.g. -l key1=value1,key2=value2)

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [http://golang.org/pkg/text/template/#pkg-overview].

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

--cache-dir string Default: "\$HOME/.kube/cache"

Default cache directory

--certificate-authority string

Path to a cert file for the certificate authority

--client-certificate string

Path to a client certificate file for TLS

--client-key string

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none|cpu|heap|goroutine|threadcreate|block|mutex|trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.3 - kubectl api-resources

Print the supported API resources on the server

Synopsis

Print the supported API resources on the server.

```
kubectl api-resources [flags]
```

Examples

```
# Print the supported API resources
kubectl api-resources

# Print the supported API resources with more information
kubectl api-resources -o wide

# Print the supported API resources sorted by a column
kubectl api-resources --sort-by=name

# Print the supported namespaced resources
kubectl api-resources --namespaced=true

# Print the supported non-namespaced resources
kubectl api-resources --namespaced=false

# Print the supported API resources with a specific APIGroup
kubectl api-resources --api-group=rbac.authorization.k8s.io
```

Options

--api-group string

Limit to resources in the specified API group.

--cached

Use the cached list of resources if available.

`--categories strings`

Limit to resources that belong to the specified categories.

`-h, --help`

help for api-resources

`--namespaced` Default: true

If false, non-namespaced resources will be returned, otherwise returning namespaced resources by default.

`--no-headers`

When using the default or custom-column output format, don't print headers (default print headers).

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, wide).

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--sort-by string`

If non-empty, sort list of resources using specified field. The field can be either 'name' or 'kind'.

`--verbs strings`

Limit to resources that support the specified verbs.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.4 - kubectl api-versions

Print the supported API versions on the server, in the form of "group/version"

Synopsis

Print the supported API versions on the server, in the form of "group/version".

```
kubectl api-versions
```

Examples

```
# Print the supported API versions
kubectl api-versions
```

Options

```
-h, --help
```

help for api-versions

Parent Options Inherited

```
--as string
```

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

```
--as-group strings
```

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

```
--as-uid string
```

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.5 - kubectl apply

Apply a configuration to a resource by file name or stdin

Synopsis

Apply a configuration to a resource by file name or stdin. The resource name must be specified. This resource will be created if it doesn't exist yet. To use 'apply', always create the resource initially with either 'apply' or 'create --save-config'.

JSON and YAML formats are accepted.

Alpha Disclaimer: the --prune functionality is not yet complete. Do not use unless you are aware of what the current state is. See <https://issues.k8s.io/34274>.

```
kubectl apply (-f FILENAME | -k DIRECTORY)
```

Examples

```
# Apply the configuration in pod.json to a pod
kubectl apply -f ./pod.json

# Apply resources from a directory containing kustomization.yaml - e.g. dir/kusto
kubectl apply -k dir/

# Apply the JSON passed into stdin to a pod
cat pod.json | kubectl apply -f -

# Apply the configuration from all files that end with '.json'
kubectl apply -f '*.json'

# Note: --prune is still in Alpha
# Apply the configuration in manifest.yaml that matches label app=nginx and delete
kubectl apply --prune -f manifest.yaml -l app=nginx

# Apply the configuration in manifest.yaml and delete all the other config maps t
kubectl apply --prune -f manifest.yaml --all --prune-allowlist=core/v1/ConfigMap
```

Options

`--all`

Select all resources in the namespace of the specified resource types.

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--cascade string[="background"]` Default: "background"

Must be "background", "orphan", or "foreground". Selects the deletion cascading strategy for the dependents (e.g. Pods created by a ReplicationController). Defaults to background.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-client-side-apply"

Name of the manager used to track field ownership.

`-f, --filename strings`

The files, directories or URLs that contain the configurations to apply.

`--force`

If true, immediately remove resources from API and bypass graceful deletion. Note that immediate deletion of some resources may result in inconsistency or data loss and requires confirmation.

`--force-conflicts`

If true, server-side apply will force the changes against conflicts.

`--grace-period int` Default: -1

Period of time in seconds given to the resource to terminate gracefully. Ignored if negative. Set to 1 for immediate shutdown. Can only be set to 0 when --force is true (force deletion).

`-h, --help`

help for apply

`-k, --kustomize string`

Process a kustomization directory. This flag can't be used together with `-f` or `-R`.

`--openapi-patch` Default: true

If true, use openapi to calculate diff when the openapi presents and the resource can be found in the openapi spec. Otherwise, fall back to use baked-in types.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--overwrite` Default: true

Automatically resolve conflicts between the modified and live configuration by using values from the modified configuration

`--prune`

Automatically delete resource objects, that do not appear in the configs and are created by either apply or create `--save-config`. Should be used with either `-l` or `--all`.

`--prune-allowlist strings`

Overwrite the default allowlist with `<group/version/kind>` for `--prune`

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--server-side`

If true, apply runs in the server instead of the client.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--subresource string`

If specified, apply will operate on the subresource of the requested object. Only allowed when using `--server-side`.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--timeout duration`

The length of time to wait before giving up on a delete, zero means determine a timeout from the size of the object

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

`--wait`

If true, wait for resources to be gone before returning. This waits for finalizers.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl apply edit-last-applied](#) - Edit latest last-applied-configuration annotations of a resource/object
- [kubectl apply set-last-applied](#) - Set the last-applied-configuration annotation on a live object to match the contents of a file
- [kubectl apply view-last-applied](#) - View the latest last-applied-configuration annotations of a resource/object

3.5.1 - kubectl apply edit-last-applied

Edit latest last-applied-configuration annotations of a resource/object

Synopsis

Edit the latest last-applied-configuration annotations of resources from the default editor.

The edit-last-applied command allows you to directly edit any API resource you can retrieve via the command-line tools. It will open the editor defined by your KUBE_EDITOR, or EDITOR environment variables, or fall back to 'vi' for Linux or 'notepad' for Windows. You can edit multiple objects, although changes are applied one at a time. The command accepts file names as well as command-line arguments, although the files you point to must be previously saved versions of resources.

The default format is YAML. To edit in JSON, specify "-o json".

The flag --windows-line-endings can be used to force Windows line endings, otherwise the default for your operating system will be used.

In the event an error occurs while updating, a temporary file will be created on disk that contains your unapplied changes. The most common error when updating a resource is another editor changing the resource on the server. When this occurs, you will have to apply your changes to the newer version of the resource, or update your temporary saved copy to include the latest resource version.

```
kubectl apply edit-last-applied (RESOURCE/NAME | -f FILENAME)
```

Examples

```
# Edit the last-applied-configuration annotations by type/name in YAML
kubectl apply edit-last-applied deployment/nginx

# Edit the last-applied-configuration annotations by file in JSON
kubectl apply edit-last-applied -f deploy.yaml -o json
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--field-manager` string Default: "kubectl-client-side-apply"

Name of the manager used to track field ownership.

`-f, --filename` strings

Filename, directory, or URL to files to use to edit the resource

`-h, --help`

help for edit-last-applied

`-k, --kustomize` string

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output` string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template` string

Template string or path to template file to use when `-o=go-template, -o=go-template-file`. The template format is goyaml templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate` string[="strict"] Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server

side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

`--windows-line-endings`

Defaults to the line ending native to your platform.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl apply](#) - Apply a configuration to a resource by file name or stdin

3.5.2 - kubectl apply set-last-applied

Set the last-applied-configuration annotation on a live object to match the contents of a file

Synopsis

Set the latest last-applied-configuration annotations by setting it to match the contents of a file. This results in the last-applied-configuration being updated as though 'kubectl apply -f<file> ' was run, without updating any other parts of the object.

```
kubectl apply set-last-applied -f FILENAME
```

Examples

```
# Set the last-applied-configuration of a resource to match the contents of a file
kubectl apply set-last-applied -f deploy.yaml

# Execute set-last-applied against each configuration file in a directory
kubectl apply set-last-applied -f path/

# Set the last-applied-configuration of a resource to match the contents of a file
kubectl apply set-last-applied -f deploy.yaml --create-annotation=true
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--create-annotation

Will create 'last-applied-configuration' annotations if current objects doesn't have one

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

-f, --filename strings

Filename, directory, or URL to files that contains the last-applied-configuration annotations

-h, --help

help for set-last-applied

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl apply](#) - Apply a configuration to a resource by file name or stdin

3.5.3 - kubectl apply view-last-applied

View the latest last-applied-configuration annotations of a resource/object

Synopsis

View the latest last-applied-configuration annotations by type/name or file.

The default output will be printed to stdout in YAML format. You can use the -o option to change the output format.

```
kubectl apply view-last-applied (TYPE [NAME | -l label] | TYPE/NAME | -f FILENAME)
```

Examples

```
# View the last-applied-configuration annotations by type/name in YAML
kubectl apply view-last-applied deployment/nginx

# View the last-applied-configuration annotations by file in JSON
kubectl apply view-last-applied -f deploy.yaml -o json
```

Options

--all

Select all resources in the namespace of the specified resource types

-f, --filename strings

Filename, directory, or URL to files that contains the last-applied-configuration annotations

-h, --help

help for view-last-applied

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output string` Default: "yaml"

Output format. Must be one of (yaml, json)

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cAdvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl apply](#) - Apply a configuration to a resource by file name or stdin

3.6 - kubectl attach

Attach to a running container

Synopsis

Attach to a process that is already running inside an existing container.

```
kubectl attach (POD | TYPE/NAME) -c CONTAINER
```

Examples

```
# Get output from running pod mypod; use the 'kubectl.kubernetes.io/default-container' annotation
# for selecting the container to be attached or the first container in the pod will be chosen
kubectl attach mypod

# Get output from ruby-container from pod mypod
kubectl attach mypod -c ruby-container

# Switch to raw terminal mode; sends stdin to 'bash' in ruby-container from pod mypod
# and sends stdout/stderr from 'bash' back to the client
kubectl attach mypod -c ruby-container -i -t

# Get output from the first pod of a replica set named nginx
kubectl attach rs/nginx
```

Options

-c, --container string

Container name. If omitted, use the `kubectl.kubernetes.io/default-container` annotation for selecting the container to be attached or the first container in the pod will be chosen

--detach-keys string Default: "ctrl-p,ctrl-q"

Override the key sequence for detaching a container

`-h, --help`

help for attach

`--pod-running-timeout` duration Default: 1m0s

The length of time (like 5s, 2m, or 3h, higher than zero) to wait until at least one pod is running

`-q, --quiet`

Only print output from the remote session

`-i, --stdin`

Pass stdin to the container

`-t, --tty`

Stdin is a TTY

Parent Options Inherited

`--as` string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group` strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid` string

UID to impersonate for the operation.

`--as-user-extra` strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.7 - kubectl auth

Inspect authorization

Synopsis

Inspect authorization.

```
kubectl auth [flags]
```

Options

-h, --help

help for auth

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl auth can-i](#) - Check whether an action is allowed
- [kubectl auth reconcile](#) - Reconciles rules for RBAC role, role binding, cluster role, and cluster role binding objects
- [kubectl auth whoami](#) - Experimental: Check self subject attributes

3.7.1 - kubectl auth can-i

Check whether an action is allowed

Synopsis

Check whether an action is allowed.

VERB is a logical Kubernetes API verb like 'get', 'list', 'watch', 'delete', etc. TYPE is a Kubernetes resource. Shortcuts and groups will be resolved. NONRESOURCEURL is a partial URL that starts with "/". NAME is the name of a particular Kubernetes resource. This command pairs nicely with impersonation. See --as global flag.

```
kubectl auth can-i VERB [TYPE | TYPE/NAME | NONRESOURCEURL]
```

Examples

```
# Check to see if I can create pods in any namespace
kubectl auth can-i create pods --all-namespaces
```

```
# Check to see if I can list deployments in my current namespace
kubectl auth can-i list deployments.apps
```

```
# Check to see if service account "foo" of namespace "dev" can list pods in the r
# You must be allowed to use impersonation for the global option "--as"
kubectl auth can-i list pods --as=system:serviceaccount:dev:foo -n prod
```

```
# Check to see if I can do everything in my current namespace ("*" means all)
kubectl auth can-i '*' '*'
```

```
# Check to see if I can get the job named "bar" in namespace "foo"
kubectl auth can-i list jobs.batch/bar -n foo
```

```
# Check to see if I can read pod logs
kubectl auth can-i get pods --subresource=log
```

```
# Check to see if I can access the URL /logs/
kubectl auth can-i get /logs/
```

```
# Check to see if I can approve certificates.k8s.io
kubectl auth can-i approve certificates.k8s.io
```



```
# List all allowed actions in namespace "foo"
kubectl auth can-i --list --namespace=foo
```

Options

-A, --all-namespaces

If true, check the specified action in all namespaces.

-h, --help

help for can-i

--list

If true, prints all allowed actions.

--no-headers

If true, prints allowed actions without headers

-q, --quiet

If true, suppress output and just return the exit code.

--subresource string

SubResource such as pod/log or deployment/scale

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectx auth](#) - Inspect authorization

3.7.2 - kubectl auth reconcile

Reconciles rules for RBAC role, role binding, cluster role, and cluster role binding objects

Synopsis

Reconciles rules for RBAC role, role binding, cluster role, and cluster role binding objects.

Missing objects are created, and the containing namespace is created for namespaced objects, if required.

Existing roles are updated to include the permissions in the input objects, and remove extra permissions if `--remove-extra-permissions` is specified.

Existing bindings are updated to include the subjects in the input objects, and remove extra subjects if `--remove-extra-subjects` is specified.

This is preferred to 'apply' for RBAC resources so that semantically-aware merging of rules and subjects is done.

```
kubectl auth reconcile -f FILENAME
```

Examples

```
# Reconcile RBAC resources from a file
kubectl auth reconcile -f my-rbac-rules.yaml
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

-f, --filename strings

Filename, directory, or URL to files identifying the resource to reconcile.

-h, --help

help for reconcile

-k, --kustomize string

Process the kustomization directory. This flag can't be used together with -f or -R.

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

-R, --recursive

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

--remove-extra-permissions

If true, removes extra permissions added to roles

--remove-extra-subjects

If true, removes extra subjects added to rolebindings

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl auth](#) - Inspect authorization

3.7.3 - kubectl auth whoami

Experimental: Check self subject attributes

Synopsis

Experimental: Check who you are and your attributes (groups, extra).

This command is helpful to get yourself aware of the current user attributes, especially when dynamic authentication, e.g., token webhook, auth proxy, or OIDC is enabled in the Kubernetes cluster.

```
kubectl auth whoami
```

Examples

```
# Get your subject attributes
kubectl auth whoami

# Get your subject attributes in JSON format
kubectl auth whoami -o json
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`-h, --help`

help for whoami

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl auth](#) - Inspect authorization

3.8 - kubectl autoscale

Auto-scale a deployment, replica set, stateful set, or replication controller

Synopsis

Creates an autoscaler that automatically chooses and sets the number of pods that run in a Kubernetes cluster. The command will attempt to use the autoscaling/v2 API first, in case of an error, it will fall back to autoscaling/v1 API.

Looks up a deployment, replica set, stateful set, or replication controller by name and creates an autoscaler that uses the given resource as a reference. An autoscaler can automatically increase or decrease number of pods deployed within the system as needed.

```
kubectl autoscale (-f FILENAME | TYPE NAME | TYPE/NAME) [--min=MINPODS] --max=MAXPODS
```

Examples

```
# Auto scale a deployment "foo", with the number of pods between 2 and 10, no target
kubectl autoscale deployment foo --min=2 --max=10
```

```
# Auto scale a replication controller "foo", with the number of pods between 1 and 5, target 80% CPU
kubectl autoscale rc foo --max=5 --cpu=80%
```

```
# Auto scale a deployment "bar", with the number of pods between 3 and 6, target 500m CPU, 200Mi memory
kubectl autoscale deployment bar --min=3 --max=6 --cpu=500m --memory=200Mi
```

```
# Auto scale a deployment "bar", with the number of pods between 2 and 8, target 60% CPU, 70% memory
kubectl autoscale deployment bar --min=2 --max=8 --cpu=60% --memory=70%
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goolang and jsonpath output formats.

`--cpu string`

Target CPU utilization over all the pods. When specified as a percentage (e.g. "70%" for 70% of requested CPU) it will target average utilization. When specified as quantity (e.g. "500m" for 500 milliCPU) it will target average value. Value without units is treated as a quantity with miliCPU being the unit (e.g. "500" is "500m").

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-autoscale"

Name of the manager used to track field ownership.

`-f, --filename strings`

Filename, directory, or URL to files identifying the resource to autoscale.

`-h, --help`

help for autoscale

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with -f or -R.

`--max int32` Default: -1

The upper limit for the number of pods that can be set by the autoscaler. Required.

`--memory string`

Target memory utilization over all the pods. When specified as a percentage (e.g. "60%" for 60% of requested memory) it will target average utilization. When specified as quantity (e.g. "200Mi" for 200 MiB, "1Gi" for 1 GiB) it will target average value. Value without units is treated as a quantity with mebibytes being the unit (e.g. "200" is "200Mi").

`--min int32` Default: -1

The lower limit for the number of pods that can be set by the autoscaler. If it's not specified or negative, the server will apply a default value.

`--name string`

The name for the newly created object. If not specified, the name of the input resource will be used.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform `kubectl apply` on this object in the future.

`--show-managed-fields`

If true, keep the `managedFields` when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template, -o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.9 - kubectl certificate

Modify certificate resources

Synopsis

Modify certificate resources.

```
kubectl certificate SUBCOMMAND
```

Options

-h, --help

help for certificate

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl certificate approve](#) - Approve a certificate signing request
- [kubectl certificate deny](#) - Deny a certificate signing request

3.9.1 - kubectl certificate approve

Approve a certificate signing request

Synopsis

Approve a certificate signing request.

`kubectl certificate approve` allows a cluster admin to approve a certificate signing request (CSR). This action tells a certificate signing controller to issue a certificate to the requester with the attributes requested in the CSR.

SECURITY NOTICE: Depending on the requested attributes, the issued certificate can potentially grant a requester access to cluster resources or to authenticate as a requested identity. Before approving a CSR, ensure you understand what the signed certificate can do.

```
kubectl certificate approve (-f FILENAME | NAME)
```

Examples

```
# Approve CSR 'csr-sqgzp'
kubectl certificate approve csr-sqgzp
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`-f, --filename` strings

Filename, directory, or URL to files identifying the resource to update

`--force`

Update the CSR even if it is already approved.

`-h, --help`

help for approve

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl certificate](#) - Modify certificate resources

3.9.2 - kubectl certificate deny

Deny a certificate signing request

Synopsis

Deny a certificate signing request.

kubectl certificate deny allows a cluster admin to deny a certificate signing request (CSR). This action tells a certificate signing controller to not to issue a certificate to the requester.

```
kubectl certificate deny (-f FILENAME | NAME)
```

Examples

```
# Deny CSR 'csr-sqgzp'
kubectl certificate deny csr-sqgzp
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyang and jsonpath output formats.

`-f, --filename` strings

Filename, directory, or URL to files identifying the resource to update

`--force`

Update the CSR even if it is already denied.

`-h, --help`

help for deny

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

--match-server-version

Require server version to match client version

-n, --namespace string

If present, the namespace scope for this CLI request

--password string

Password for basic authentication to the API server

--profile string Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl certificate](#) - Modify certificate resources

3.10 - kubectl cluster-info

Display cluster information

Synopsis

Display addresses of the control plane and services with label `kubernetes.io/cluster-service=true`. To further debug and diagnose cluster problems, use `'kubectl cluster-info dump'`.

```
kubectl cluster-info [flags]
```

Examples

```
# Print the address of the control plane and cluster services
kubectl cluster-info
```

Options

```
-h, --help
```

help for cluster-info

Parent Options Inherited

```
--as string
```

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

```
--as-group strings
```

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl cluster-info dump](#) - Dump relevant information for debugging and diagnosis

3.10.1 - kubectl cluster-info dump

Dump relevant information for debugging and diagnosis

Synopsis

Dump cluster information out suitable for debugging and diagnosing cluster problems. By default, dumps everything to stdout. You can optionally specify a directory with `--output-directory`. If you specify a directory, Kubernetes will build a set of files in that directory. By default, only dumps things in the current namespace and 'kube-system' namespace, but you can switch to a different namespace with the `--namespaces` flag, or specify `--all-namespaces` to dump all namespaces.

The command also dumps the logs of all of the pods in the cluster; these logs are dumped into different directories based on namespace and pod name.

```
kubectl cluster-info dump [flags]
```

Examples

```
# Dump current cluster state to stdout
kubectl cluster-info dump

# Dump current cluster state to /path/to/cluster-state
kubectl cluster-info dump --output-directory=/path/to/cluster-state

# Dump all namespaces to stdout
kubectl cluster-info dump --all-namespaces

# Dump a set of namespaces to /path/to/cluster-state
kubectl cluster-info dump --namespaces default,kube-system --output-directory=/pa
```

Options

`-A, --all-namespaces`

If true, dump all namespaces. If true, `--namespaces` is ignored.

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`-h, --help`

help for dump

`--namespaces` strings

A comma separated list of namespaces to dump.

`-o, --output` string Default: "json"

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--output-directory` string

Where to output the files. If empty or '-' uses stdout, otherwise creates a directory hierarchy in that directory

`--pod-running-timeout` duration Default: 20s

The length of time (like 5s, 2m, or 3h, higher than zero) to wait until at least one pod is running

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template` string

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is goyaml templates [http://golang.org/pkg/text/template/#pkg-overview].

Parent Options Inherited

`--as` string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl cluster-info](#) - Display cluster information

3.11 - kubectl completion

Output shell completion code for the specified shell (bash, zsh, fish, or powershell)

Synopsis

Output shell completion code for the specified shell (bash, zsh, fish, or powershell). The shell code must be evaluated to provide interactive completion of kubectl commands. This can be done by sourcing it from the .bash_profile.

Detailed instructions on how to do this are available here:

```
for macOS:
https://kubernetes.io/docs/tasks/tools/install-kubectl-macos/#enable-shell-autoc

for linux:
https://kubernetes.io/docs/tasks/tools/install-kubectl-linux/#enable-shell-autoc

for windows:
https://kubernetes.io/docs/tasks/tools/install-kubectl-windows/#enable-shell-autoc
```

Note for zsh users: [1] zsh completions are only supported in versions of zsh >= 5.2.

```
kubectl completion SHELL
```

Examples

```
# Installing bash completion on macOS using homebrew
## If running Bash 3.2 included with macOS
brew install bash-completion
## or, if running Bash 4.1+
brew install bash-completion@2
## If kubectl is installed via homebrew, this should start working immediately
## If you've installed via other means, you may need add the completion to your path
kubectl completion bash > $(brew --prefix)/etc/bash_completion.d/kubectl

# Installing bash completion on Linux
## If bash-completion is not installed on Linux, install the 'bash-completion' package
```

```

## via your distribution's package manager.
## Load the kubectl completion code for bash into the current shell
source <(kubectl completion bash)
## Write bash completion code to a file and source it from .bash_profile
kubectl completion bash > ~/.kube/completion.bash.inc
printf "
# kubectl shell completion
source '$HOME/.kube/completion.bash.inc'
" >> $HOME/.bash_profile
source $HOME/.bash_profile

# Load the kubectl completion code for zsh[1] into the current shell
source <(kubectl completion zsh)
# Set the kubectl completion code for zsh[1] to autoload on startup
kubectl completion zsh > "${fpath[1]}/_kubectl"

# Load the kubectl completion code for fish[2] into the current shell
kubectl completion fish | source
# To load completions for each session, execute once:
kubectl completion fish > ~/.config/fish/completions/kubectl.fish

# Load the kubectl completion code for powershell into the current shell
kubectl completion powershell | Out-String | Invoke-Expression
# Set kubectl completion code for powershell to run on startup
## Save completion code to a script and execute in the profile
kubectl completion powershell > "$HOME\.kube\completion.ps1"
Add-Content $PROFILE ". '$HOME\.kube\completion.ps1'"
## Execute completion code in the profile
Add-Content $PROFILE "if (Get-Command kubectl -ErrorAction SilentlyContinue) {
kubectl completion powershell | Out-String | Invoke-Expression
}"
## Add completion code directly to the $PROFILE script
kubectl completion powershell >> $PROFILE

```

Options

-h, --help

help for completion

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.12 - kubectl config

Modify kubeconfig files

Synopsis

Modify kubeconfig files using subcommands like "kubectl config set current-context my-context".

The loading order follows these rules:

1. If the --kubeconfig flag is set, then only that file is loaded. The flag may only be set once and no merging takes place.
2. If \$KUBECONFIG environment variable is set, then it is used as a list of paths (normal path delimiting rules for your system). These paths are merged. When a value is modified, it is modified in the file that defines the stanza. When a value is created, it is created in the first file that exists. If no files in the chain exist, then it creates the last file in the list.
3. Otherwise, \${HOME}/.kube/config is used and no merging takes place.

```
kubectl config SUBCOMMAND
```

Options

```
-h, --help
```

help for config

```
--kubeconfig string
```

use a particular kubeconfig file

Parent Options Inherited

```
--as string
```

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl config current-context](#) - Display the current-context
- [kubectl config delete-cluster](#) - Delete the specified cluster from the kubeconfig
- [kubectl config delete-context](#) - Delete the specified context from the kubeconfig
- [kubectl config delete-user](#) - Delete the specified user from the kubeconfig
- [kubectl config get-clusters](#) - Display clusters defined in the kubeconfig
- [kubectl config get-contexts](#) - Describe one or many contexts
- [kubectl config get-users](#) - Display users defined in the kubeconfig
- [kubectl config rename-context](#) - Rename a context from the kubeconfig file
- [kubectl config set](#) - Set an individual value in a kubeconfig file
- [kubectl config set-cluster](#) - Set a cluster entry in kubeconfig
- [kubectl config set-context](#) - Set a context entry in kubeconfig
- [kubectl config set-credentials](#) - Set a user entry in kubeconfig
- [kubectl config unset](#) - Unset an individual value in a kubeconfig file
- [kubectl config use-context](#) - Set the current-context in a kubeconfig file
- [kubectl config view](#) - Display merged kubeconfig settings or a specified kubeconfig file

3.12.1 - kubectl config current-context

Display the current-context

Synopsis

Display the current-context.

```
kubectl config current-context [flags]
```

Examples

```
# Display the current-context
kubectl config current-context
```

Options

-h, --help

help for current-context

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.2 - kubectl config delete-cluster

Delete the specified cluster from the kubeconfig

Synopsis

Delete the specified cluster from the kubeconfig.

```
kubectl config delete-cluster NAME
```

Examples

```
# Delete the minikube cluster
kubectl config delete-cluster minikube
```

Options

-h, --help

help for delete-cluster

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.3 - kubectl config delete-context

Delete the specified context from the kubeconfig

Synopsis

Delete the specified context from the kubeconfig.

```
kubectl config delete-context NAME
```

Examples

```
# Delete the context for the minikube cluster
kubectl config delete-context minikube
```

Options

-h, --help

help for delete-context

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.4 - kubectl config delete-user

Delete the specified user from the kubeconfig

Synopsis

Delete the specified user from the kubeconfig.

```
kubectl config delete-user NAME
```

Examples

```
# Delete the minikube user
kubectl config delete-user minikube
```

Options

-h, --help

help for delete-user

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.5 - kubectl config get-clusters

Display clusters defined in the kubeconfig

Synopsis

Display clusters defined in the kubeconfig.

```
kubectl config get-clusters [flags]
```

Examples

```
# List the clusters that kubectl knows about
kubectl config get-clusters
```

Options

-h, --help

help for get-clusters

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.6 - kubectl config get-contexts

Describe one or many contexts

Synopsis

Display one or many contexts from the kubeconfig file.

```
kubectl config get-contexts [(-o|--output=)name)]
```

Examples

```
# List all the contexts in your kubeconfig file
kubectl config get-contexts

# Describe one context in your kubeconfig file
kubectl config get-contexts my-context
```

Options

-h, --help

help for get-contexts

--no-headers

When using the default or custom-column output format, don't print headers (default print headers).

-o, --output string

Output format. One of: (name).

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.7 - kubectl config get-users

Display users defined in the kubeconfig

Synopsis

Display users defined in the kubeconfig.

```
kubectl config get-users [flags]
```

Examples

```
# List the users that kubectl knows about
kubectl config get-users
```

Options

```
-h, --help
```

help for get-users

Parent Options Inherited

```
--as string
```

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

```
--as-group strings
```

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

```
--as-uid string
```

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.8 - kubectl config rename-context

Rename a context from the kubeconfig file

Synopsis

Renames a context from the kubeconfig file.

CONTEXT_NAME is the context name that you want to change.

NEW_NAME is the new name you want to set.

Note: If the context being renamed is the 'current-context', this field will also be updated.

```
kubectl config rename-context CONTEXT_NAME NEW_NAME
```

Examples

```
# Rename the context 'old-name' to 'new-name' in your kubeconfig file
kubectl config rename-context old-name new-name
```

Options

```
-h, --help
```

help for rename-context

Parent Options Inherited

```
--as string
```

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

```
--as-group strings
```

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.9 - kubectl config set

Set an individual value in a kubeconfig file

Synopsis

Set an individual value in a kubeconfig file.

PROPERTY_NAME is a dot delimited name where each token represents either an attribute name or a map key. Map keys may not contain dots.

PROPERTY_VALUE is the new value you want to set. Binary fields such as 'certificate-authority-data' expect a base64 encoded string unless the --set-raw-bytes flag is used.

Specifying an attribute name that already exists will merge new fields on top of existing values.

```
kubectl config set PROPERTY_NAME PROPERTY_VALUE
```

Examples

```
# Set the server field on the my-cluster cluster to https://1.2.3.4
kubectl config set clusters.my-cluster.server https://1.2.3.4

# Set the certificate-authority-data field on the my-cluster cluster
kubectl config set clusters.my-cluster.certificate-authority-data $(echo "cert_data_here" | base64)

# Set the cluster field in the my-context context to my-cluster
kubectl config set contexts.my-context.cluster my-cluster

# Set the client-key-data field in the cluster-admin user using --set-raw-bytes
kubectl config set users.cluster-admin.client-key-data cert_data_here --set-raw-bytes
```

Options

-h, --help

help for set

`--set-raw-bytes tristate[=true]`

When writing a []byte PROPERTY_VALUE, write the given string directly without base64 decoding.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output` string Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url` string

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.10 - kubectl config set-cluster

Set a cluster entry in kubeconfig

Synopsis

Set a cluster entry in kubeconfig.

Specifying a name that already exists will merge new fields on top of existing values for those fields.

```
kubectl config set-cluster NAME [--server=server] [--certificate-authority=path/to,
```

Examples

```
# Set only the server field on the e2e cluster entry without touching other values
kubectl config set-cluster e2e --server=https://1.2.3.4

# Embed certificate authority data for the e2e cluster entry
kubectl config set-cluster e2e --embed-certs --certificate-authority=~/.kube/e2e-ca.crt

# Disable cert checking for the e2e cluster entry
kubectl config set-cluster e2e --insecure-skip-tls-verify=true

# Set the custom TLS server name to use for validation for the e2e cluster entry
kubectl config set-cluster e2e --tls-server-name=my-cluster-name

# Set the proxy URL for the e2e cluster entry
kubectl config set-cluster e2e --proxy-url=https://1.2.3.4
```

Options

`--certificate-authority string`

Path to certificate-authority file for the cluster entry in kubeconfig

`--embed-certs tristate[=true]`

embed-certs for the cluster entry in kubeconfig

`-h, --help`

help for set-cluster

`--insecure-skip-tls-verify tristate[=true]`

insecure-skip-tls-verify for the cluster entry in kubeconfig

`--proxy-url string`

proxy-url for the cluster entry in kubeconfig

`--server string`

server for the cluster entry in kubeconfig

`--tls-server-name string`

tls-server-name for the cluster entry in kubeconfig

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cAdvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.11 - kubectl config set-context

Set a context entry in kubeconfig

Synopsis

Set a context entry in kubeconfig.

Specifying a name that already exists will merge new fields on top of existing values for those fields.

```
kubectl config set-context [NAME | --current] [--cluster=cluster_nickname] [--user=
```

Examples

```
# Set the user field on the gce context entry without touching other values
kubectl config set-context gce --user=cluster-admin
```

Options

`--cluster string`

cluster for the context entry in kubeconfig

`--current`

Modify the current context

`-h, --help`

help for set-context

`-n, --namespace string`

namespace for the context entry in kubeconfig

`--user string`

user for the context entry in kubeconfig

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

--context string

The name of the kubeconfig context to use

--disable-compression

If true, opt-out of response compression for all requests to the server

--insecure-skip-tls-verify

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

--kubeconfig string

use a particular kubeconfig file

--kuberc string

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

--match-server-version

Require server version to match client version

--password string

Password for basic authentication to the API server

--profile string Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.12 - kubectl config set-credentials

Set a user entry in kubeconfig

Synopsis

Set a user entry in kubeconfig.

Specifying a name that already exists will merge new fields on top of existing values.

```
Client-certificate flags:
--client-certificate=certfile --client-key=keyfile

Bearer token flags:
--token=bearer_token

Basic auth flags:
--username=basic_user --password=basic_password
```

Bearer token and basic auth are mutually exclusive.

```
kubectl config set-credentials NAME [--client-certificate=path/to/certfile] [--cli
```

Examples

```
# Set only the "client-key" field on the "cluster-admin"
# entry, without touching other values
kubectl config set-credentials cluster-admin --client-key=~/.kube/admin.key

# Set basic auth for the "cluster-admin" entry
kubectl config set-credentials cluster-admin --username=admin --password=uXFGweUS

# Embed client certificate data in the "cluster-admin" entry
kubectl config set-credentials cluster-admin --client-certificate=~/.kube/admin.c

# Enable the Google Compute Platform auth provider for the "cluster-admin" entry
kubectl config set-credentials cluster-admin --auth-provider=gcp

# Enable the OpenID Connect auth provider for the "cluster-admin" entry with addi
kubectl config set-credentials cluster-admin --auth-provider=oidc --auth-provider
```

```
# Remove the "client-secret" config value for the OpenID Connect auth provider for the user entry in kubeconfig
kubectl config set-credentials cluster-admin --auth-provider=oidc --auth-provider-args="client-secret="

# Enable new exec auth plugin for the "cluster-admin" entry
kubectl config set-credentials cluster-admin --exec-command=/path/to/the/executable

# Enable new exec auth plugin for the "cluster-admin" entry with interactive mode
kubectl config set-credentials cluster-admin --exec-command=/path/to/the/executable --exec-interactive=true

# Define new exec auth plugin arguments for the "cluster-admin" entry
kubectl config set-credentials cluster-admin --exec-arg=arg1 --exec-arg=arg2

# Create or update exec auth plugin environment variables for the "cluster-admin" entry
kubectl config set-credentials cluster-admin --exec-env=key1=val1 --exec-env=key2=val2

# Remove exec auth plugin environment variables for the "cluster-admin" entry
kubectl config set-credentials cluster-admin --exec-env=var-to-remove-
```

Options

`--auth-provider string`

Auth provider for the user entry in kubeconfig

`--auth-provider-arg strings`

'key=value' arguments for the auth provider

`--client-certificate string`

Path to client-certificate file for the user entry in kubeconfig

`--client-key string`

Path to client-key file for the user entry in kubeconfig

`--embed-certs tristate[=true]`

Embed client cert/key for the user entry in kubeconfig

`--exec-api-version string`

API version of the exec credential plugin for the user entry in kubeconfig

`--exec-arg strings`

New arguments for the exec credential plugin command for the user entry in kubeconfig

`--exec-command string`

Command for the exec credential plugin for the user entry in kubeconfig

`--exec-env strings`

'key=value' environment values for the exec credential plugin

`--exec-interactive-mode string`

InteractiveMode of the exec credentials plugin for the user entry in kubeconfig

`--exec-provide-cluster-info tristate[=true]`

ProvideClusterInfo of the exec credentials plugin for the user entry in kubeconfig

`-h, --help`

help for set-credentials

`--password string`

password for the user entry in kubeconfig

`--token string`

token for the user entry in kubeconfig

`--username string`

username for the user entry in kubeconfig

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--user string`

The name of the kubeconfig user to use

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.13 - kubectl config unset

Unset an individual value in a kubeconfig file

Synopsis

Unset an individual value in a kubeconfig file.

PROPERTY_NAME is a dot delimited name where each token represents either an attribute name or a map key. Map keys may not contain dots.

```
kubectl config unset PROPERTY_NAME
```

Examples

```
# Unset the current-context
kubectl config unset current-context

# Unset namespace in foo context
kubectl config unset contexts.foo.namespace
```

Options

```
-h, --help
```

help for unset

Parent Options Inherited

```
--as string
```

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

```
--as-group strings
```

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.14 - kubectl config use-context

Set the current-context in a kubeconfig file

Synopsis

Set the current-context in a kubeconfig file.

```
kubectl config use-context CONTEXT_NAME
```

Examples

```
# Use the context for the minikube cluster
kubectl config use-context minikube
```

Options

-h, --help

help for use-context

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.12.15 - kubectl config view

Display merged kubeconfig settings or a specified kubeconfig file

Synopsis

Display merged kubeconfig settings or a specified kubeconfig file.

You can use `--output jsonpath={...}` to extract specific values using a jsonpath expression.

```
kubectl config view [flags]
```

Examples

```
# Show merged kubeconfig settings
```

```
kubectl config view
```

```
# Show merged kubeconfig settings, raw certificate data, and exposed secrets
```

```
kubectl config view --raw
```

```
# Get the password for the e2e user
```

```
kubectl config view -o jsonpath='{.users[?(@.name == "e2e")].user.password}'
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to golang and jsonpath output formats.

`--flatten`

Flatten the resulting kubeconfig file into self-contained output (useful for creating portable kubeconfig files)

`-h, --help`

help for view

`--merge tristate[=true]` Default: true

Merge the full hierarchy of kubeconfig files

`--minify`

Remove all information not used by current-context from the output

`-o, --output string` Default: "yaml"

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--raw`

Display raw byte data and sensitive data

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

use a particular kubeconfig file

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl config](#) - Modify kubeconfig files

3.13 - kubectl cordon

Mark node as unschedulable

Synopsis

Mark node as unschedulable.

```
kubectl cordon NODE
```

Examples

```
# Mark node "foo" as unschedulable
kubectl cordon foo
```

Options

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`-h, --help`

help for cordon

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.14 - kubectl cp

Copy files and directories to and from containers

Synopsis

Copy files and directories to and from containers.

```
kubectl cp <file-spec-src> <file-spec-dest>
```

Examples

```
# !!!Important Note!!!
# Requires that the 'tar' binary is present in your container
# image. If 'tar' is not present, 'kubectl cp' will fail.
#
# For advanced use cases, such as symlinks, wildcard expansion or
# file mode preservation, consider using 'kubectl exec'.

# Copy /tmp/foo local file to /tmp/bar in a remote pod in namespace <some-namespace>
tar cf - /tmp/foo | kubectl exec -i -n <some-namespace> <some-pod> -- tar xf - -C /tmp

# Copy /tmp/foo from a remote pod to /tmp/bar locally
kubectl exec -n <some-namespace> <some-pod> -- tar cf - /tmp/foo | tar xf - -C /tmp

# Copy /tmp/foo_dir local directory to /tmp/bar_dir in a remote pod in the default namespace
kubectl cp /tmp/foo_dir <some-pod>:/tmp/bar_dir

# Copy /tmp/foo local file to /tmp/bar in a remote pod in a specific container
kubectl cp /tmp/foo <some-pod>:/tmp/bar -c <specific-container>

# Copy /tmp/foo local file to /tmp/bar in a remote pod in namespace <some-namespace>
kubectl cp /tmp/foo <some-namespace>/<some-pod>:/tmp/bar

# Copy /tmp/foo from a remote pod to /tmp/bar locally
kubectl cp <some-namespace>/<some-pod>:/tmp/foo /tmp/bar
```

Options

`-c, --container string`

Container name. If omitted, use the `kubectrl.kubernetes.io/default-container` annotation for selecting the container to be attached or the first container in the pod will be chosen

`-h, --help`

help for cp

`--no-preserve`

The copied file/directory's ownership and permissions will not be preserved in the container

`--retries int`

Set number of retries to complete a copy operation from a container. Specify 0 to disable or any negative value for infinite retrying. The default is 0 (no retry).

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cAdvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token` string

Bearer token for authentication to the API server

`--user` string

The name of the kubeconfig user to use

`--username` string

Username for basic authentication to the API server

`--version` version[=true]

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.15 - kubectl create

Create a resource from a file or from stdin

Synopsis

Create a resource from a file or from stdin.

JSON and YAML formats are accepted.

```
kubectl create -f FILENAME
```

Examples

```
# Create a pod using the data in pod.json
kubectl create -f ./pod.json

# Create a pod based on the JSON passed into stdin
cat pod.json | kubectl create -f -

# Edit the data in registry.yaml in JSON then create the resource using the editor
kubectl create -f registry.yaml --edit -o json
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--edit`

Edit the API resource before creating

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`-f, --filename strings`

Filename, directory, or URL to files to use to create the resource

`-h, --help`

help for create

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--raw string`

Raw URI to POST to the server. Uses the transport specified by the kubeconfig file.

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

`--windows-line-endings`

Only relevant if `--edit=true`. Defaults to the line ending native to your platform.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl create clusterrole](#) - Create a cluster role
- [kubectl create clusterrolebinding](#) - Create a cluster role binding for a particular cluster role
- [kubectl create configmap](#) - Create a config map from a local file, directory or literal value
- [kubectl create cronjob](#) - Create a cron job with the specified name
- [kubectl create deployment](#) - Create a deployment with the specified name
- [kubectl create ingress](#) - Create an ingress with the specified name
- [kubectl create job](#) - Create a job with the specified name
- [kubectl create namespace](#) - Create a namespace with the specified name
- [kubectl create poddisruptionbudget](#) - Create a pod disruption budget with the specified name
- [kubectl create priorityclass](#) - Create a priority class with the specified name
- [kubectl create quota](#) - Create a quota with the specified name
- [kubectl create role](#) - Create a role with single rule
- [kubectl create rolebinding](#) - Create a role binding for a particular role or cluster role
- [kubectl create secret](#) - Create a secret using a specified subcommand
- [kubectl create service](#) - Create a service using a specified subcommand
- [kubectl create serviceaccount](#) - Create a service account with the specified name
- [kubectl create token](#) - Request a service account token

3.15.1 - kubectl create clusterrole

Create a cluster role

Synopsis

Create a cluster role.

```
kubectl create clusterrole NAME --verb=verb --resource=resource.group [--resource-r
```

Examples

```
# Create a cluster role named "pod-reader" that allows user to perform "get", "watch"
kubectl create clusterrole pod-reader --verb=get,list,watch --resource=pods

# Create a cluster role named "pod-reader" with ResourceName specified
kubectl create clusterrole pod-reader --verb=get --resource=pods --resource-name=

# Create a cluster role named "foo" with API Group specified
kubectl create clusterrole foo --verb=get,list,watch --resource=rs.apps

# Create a cluster role named "foo" with SubResource specified
kubectl create clusterrole foo --verb=get,list,watch --resource=pods,pods/status

# Create a cluster role name "foo" with NonResourceURL specified
kubectl create clusterrole "foo" --verb=get --non-resource-url=/logs/*

# Create a cluster role name "monitoring" with AggregationRule specified
kubectl create clusterrole monitoring --aggregation-rule="rbac.example.com/aggreg
```

Options

`--aggregation-rule` <comma-separated 'key=value' pairs>

An aggregation label selector for combining ClusterRoles.

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goolang and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`-h, --help`

help for clusterrole

`--non-resource-url strings`

A partial url that user should have access to.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--resource strings`

Resource that the rule applies to

`--resource-name strings`

Resource in the white list that the rule applies to, repeat this flag for multiple items

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [http://golang.org/pkg/text/template/#pkg-overview].

--validate string[="strict"] Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

--verb strings

Verb that applies to the resources contained in the rule

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.2 - kubectl create clusterrolebinding

Create a cluster role binding for a particular cluster role

Synopsis

Create a cluster role binding for a particular cluster role.

```
kubectl create clusterrolebinding NAME --clusterrole=NAME [--user=username] [--group=group]
```

Examples

```
# Create a cluster role binding for user1, user2, and group1 using the cluster-admin role
kubectl create clusterrolebinding cluster-admin --clusterrole=cluster-admin --user=user1 --group=group1
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--clusterrole string

ClusterRole this ClusterRoleBinding should reference

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

`--group strings`

Groups to bind to the clusterrole. The flag can be repeated to add multiple groups.

`-h, --help`

help for clusterrolebinding

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--serviceaccount strings`

Service accounts to bind to the clusterrole, in the format <namespace>:<name>. The flag can be repeated to add multiple service accounts.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--user strings`

Username to bind to the clusterrole. The flag can be repeated to add multiple users.

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none|cpu|heap|goroutine|threadcreate|block|mutex|trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.3 - kubectl create configmap

Create a config map from a local file, directory or literal value

Synopsis

Create a config map based on a file, directory, or specified literal value.

A single config map may package one or more key/value pairs.

When creating a config map based on a file, the key will default to the basename of the file, and the value will default to the file content. If the basename is an invalid key, you may specify an alternate key.

When creating a config map based on a directory, each file whose basename is a valid key in the directory will be packaged into the config map. Any directory entries except regular files are ignored (e.g. subdirectories, symlinks, devices, pipes, etc).

```
kubectl create configmap NAME [--from-file=[key=]source] [--from-literal=key1=value1]
```

Examples

```
# Create a new config map named my-config based on folder bar
```

```
kubectl create configmap my-config --from-file=path/to/bar
```

```
# Create a new config map named my-config with specified keys instead of file bas
```

```
kubectl create configmap my-config --from-file=key1=/path/to/bar/file1.txt --from
```

```
# Create a new config map named my-config with key1=config1 and key2=config2
```

```
kubectl create configmap my-config --from-literal=key1=config1 --from-literal=key
```

```
# Create a new config map named my-config with key=value pairs from an env file
```

```
kubectl create configmap my-config --from-env-file=path/to/bar.env
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--append-hash`

Append a hash of the configmap to its name.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`--from-env-file strings`

Specify the path to a file to read lines of key=val pairs to create a configmap.

`--from-file strings`

Key file can be specified using its file path, in which case file basename will be used as configmap key, or optionally with a key and file path, in which case the given key will be used. Specifying a directory will iterate each named file in the directory whose basename is a valid configmap key.

`--from-literal strings`

Specify a key and literal value to insert in configmap (i.e. mykey=somevalue)

`-h, --help`

help for configmap

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.4 - kubectl create cronjob

Create a cron job with the specified name

Synopsis

Create a cron job with the specified name.

```
kubectl create cronjob NAME --image=image --schedule='0/5 * * * ?' -- [COMMAND] [a
```

Examples

```
# Create a cron job
kubectl create cronjob my-job --image=busybox --schedule="*/1 * * * *"

# Create a cron job with a command
kubectl create cronjob my-job --image=busybox --schedule="*/1 * * * *" -- date
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`-h, --help`

help for cronjob

`--image string`

Image name to run.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--restart string`

job's restart policy. supported values: OnFailure, Never

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--schedule string`

A schedule in the Cron format the job should be run with.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [http://golang.org/pkg/text/template/#pkg-overview].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none|cpu|heap|goroutine|threadcreate|block|mutex|trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.5 - kubectl create deployment

Create a deployment with the specified name

Synopsis

Create a deployment with the specified name.

```
kubectl create deployment NAME --image=image -- [COMMAND] [args...]
```

Examples

```
# Create a deployment named my-dep that runs the busybox image
kubectl create deployment my-dep --image=busybox

# Create a deployment with a command
kubectl create deployment my-dep --image=busybox -- date

# Create a deployment named my-dep that runs the nginx image with 3 replicas
kubectl create deployment my-dep --image=nginx --replicas=3

# Create a deployment named my-dep that runs the busybox image and expose port 5701
kubectl create deployment my-dep --image=busybox --port=5701

# Create a deployment named my-dep that runs multiple containers
kubectl create deployment my-dep --image=busybox:latest --image=ubuntu:latest --
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request

without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`-h, --help`

help for deployment

`--image strings`

Image names to run. A deployment can have multiple images set for multi-container pod.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--port int32` Default: -1

The containerPort that this deployment exposes.

`-r, --replicas int32` Default: 1

Number of replicas to create. Default is 1.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string=["strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.6 - kubectl create ingress

Create an ingress with the specified name

Synopsis

Create an ingress with the specified name.

```
kubectl create ingress NAME --rule=host/path=service:port[,tls[=secret]]
```

Examples

```
# Create a single ingress called 'simple' that directs requests to foo.com/bar to
# svc1:8080 with a TLS secret "my-cert"
kubectl create ingress simple --rule="foo.com/bar=svc1:8080,tls=my-cert"

# Create a catch all ingress of "/path" pointing to service svc:port and Ingress
kubectl create ingress catch-all --class=otheringress --rule="/path=svc:port"

# Create an ingress with two annotations: ingress.annotation1 and ingress.annotat
kubectl create ingress annotated --class=default --rule="foo.com/bar=svc:port" \
--annotation ingress.annotation1=foo \
--annotation ingress.annotation2=bla

# Create an ingress with the same host and multiple paths
kubectl create ingress multipath --class=default \
--rule="foo.com/=svc:port" \
--rule="foo.com/admin/=svcadmin:portadmin"

# Create an ingress with multiple hosts and the pathType as Prefix
kubectl create ingress ingress1 --class=default \
--rule="foo.com/path*=svc:8080" \
--rule="bar.com/admin*=svc2:http"

# Create an ingress with TLS enabled using the default ingress certificate and d
kubectl create ingress ingtls --class=default \
--rule="foo.com/=svc:https,tls" \
--rule="foo.com/path/subpath*=othersvc:8080"

# Create an ingress with TLS enabled using a specific secret and pathType as Pre
kubectl create ingress ingsecret --class=default \
--rule="foo.com/=svc:8080,tls=secret1"
```

```
# Create an ingress with a default backend
kubectl create ingress ingdefault --class=default \
--default-backend=defaultsvc:http \
--rule="foo.com/*=svc:8080,tls=secret1"
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--annotation strings`

Annotation to insert in the ingress object, in the format annotation=value

`--class string`

Ingress Class to be used

`--default-backend string`

Default service for backend, in format of svcname:port

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`-h, --help`

help for ingress

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--rule strings`

Rule in format host/path=service:port[,tls=secretname]. Paths containing the leading character '*' are considered pathType=Prefix. tls argument is optional.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.7 - kubectl create job

Create a job with the specified name

Synopsis

Create a job with the specified name.

```
kubectl create job NAME --image=image [--from=cronjob/name] -- [COMMAND] [args...]
```

Examples

```
# Create a job
kubectl create job my-job --image=busybox

# Create a job with a command
kubectl create job my-job --image=busybox -- date

# Create a job from a cron job named "a-cronjob"
kubectl create job test-job --from=cronjob/a-cronjob
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

`--from string`

The name of the resource to create a Job from (only CronJob is supported).

`-h, --help`

help for job

`--image string`

Image name to run.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.8 - kubectl create namespace

Create a namespace with the specified name

Synopsis

Create a namespace with the specified name.

```
kubectl create namespace NAME [--dry-run=server|client|none]
```

Examples

```
# Create a new namespace named my-namespace
kubectl create namespace my-namespace
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string["unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

-h, --help

help for namespace

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.9 - kubectl create poddisruptionbudget

Create a pod disruption budget with the specified name

Synopsis

Create a pod disruption budget with the specified name, selector, and desired minimum available pods.

```
kubectl create poddisruptionbudget NAME --selector=SELECTOR --min-available=N [--dry-run]
```

Examples

```
# Create a pod disruption budget named my-pdb that will select all pods with the
# and require at least one of them being available at any point in time
kubectl create poddisruptionbudget my-pdb --selector=app=rails --min-available=1

# Create a pod disruption budget named my-pdb that will select all pods with the
# and require at least half of the pods selected to be available at any point in
kubectl create pdb my-pdb --selector=app=nginx --min-available=50%
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to go lang and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager` string Default: "kubectl-create"

Name of the manager used to track field ownership.

`-h, --help`

help for poddisruptionbudget

`--max-unavailable` string

The maximum number or percentage of unavailable pods this budget requires.

`--min-available` string

The minimum number or percentage of available pods this budget requires.

`-o, --output` string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--selector` string

A label selector to use for this budget. Only equality-based selector requirements are supported.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template` string

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate` string[="strict"] Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none|cpu|heap|goroutine|threadcreate|block|mutex|trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.10 - kubectl create priorityclass

Create a priority class with the specified name

Synopsis

Create a priority class with the specified name, value, globalDefault and description.

```
kubectl create priorityclass NAME --value=VALUE --global-default=BOOL [--dry-run=se
```

Examples

```
# Create a priority class named high-priority
kubectl create priorityclass high-priority --value=1000 --description="high priority"

# Create a priority class named default-priority that is considered as the global default
kubectl create priorityclass default-priority --value=1000 --global-default=true

# Create a priority class named high-priority that cannot preempt pods with lower priority
kubectl create priorityclass high-priority --value=1000 --description="high priority"
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--description string

description is an arbitrary string that usually provides guidelines on when this priority class should be used.

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request

without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`--global-default`

global-default specifies whether this PriorityClass should be considered as the default priority.

`-h, --help`

help for priorityclass

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--preemption-policy string` Default: "PreemptLowerPriority"

preemption-policy is the policy for preempting pods with lower priority.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fail

back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

`--value int32`

the value of this priority class.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none|cpu|heap|goroutine|threadcreate|block|mutex|trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.11 - kubectl create quota

Create a quota with the specified name

Synopsis

Create a resource quota with the specified name, hard limits, and optional scopes.

```
kubectl create quota NAME [--hard=key1=value1,key2=value2] [--scopes=Scope1,Scope2]
```

Examples

```
# Create a new resource quota named my-quota
kubectl create quota my-quota --hard=cpu=1,memory=1G,pods=2,services=3,replications=1

# Create a new resource quota named best-effort
kubectl create quota best-effort --hard=pods=100 --scopes=BestEffort
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

--hard string

A comma-delimited set of resource=quantity pairs that define a hard limit.

`-h, --help`

help for quota

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--scopes string`

A comma-delimited set of quota scopes that must all match each object tracked by the quota.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.12 - kubectl create role

Create a role with single rule

Synopsis

Create a role with single rule.

```
kubectl create role NAME --verb=verb --resource=resource.group/subresource [--resou
```

Examples

```
# Create a role named "pod-reader" that allows user to perform "get", "watch" and
kubectl create role pod-reader --verb=get --verb=list --verb=watch --resource=pods

# Create a role named "pod-reader" with ResourceName specified
kubectl create role pod-reader --verb=get --resource=pods --resource-name=readable

# Create a role named "foo" with API Group specified
kubectl create role foo --verb=get,list,watch --resource=rs.apps

# Create a role named "foo" with SubResource specified
kubectl create role foo --verb=get,list,watch --resource=pods,pods/status
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

-h, --help

help for role

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

--resource strings

Resource that the rule applies to

--resource-name strings

Resource in the white list that the rule applies to, repeat this flag for multiple items

--save-config

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

--validate string[="strict"] Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore"

will not perform any schema validation, silently dropping any unknown or duplicate fields.

`--verb strings`

Verb that applies to the resources contained in the rule

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none|cpu|heap|goroutine|threadcreate|block|mutex|trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.13 - kubectl create rolebinding

Create a role binding for a particular role or cluster role

Synopsis

Create a role binding for a particular role or cluster role.

```
kubectl create rolebinding NAME --clusterrole=NAME|--role=NAME [--user=username] [...]
```

Examples

```
# Create a role binding for user1, user2, and group1 using the admin cluster role
kubectl create rolebinding admin --clusterrole=admin --user=user1 --user=user2 --group=group1
```

```
# Create a role binding for service account monitoring:sa-dev using the admin role
kubectl create rolebinding admin-binding --role=admin --serviceaccount=monitoring-sa-dev
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--clusterrole string

ClusterRole this RoleBinding should reference

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

`--group strings`

Groups to bind to the role. The flag can be repeated to add multiple groups.

`-h, --help`

help for rolebinding

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--role string`

Role this RoleBinding should reference

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--serviceaccount strings`

Service accounts to bind to the role, in the format <namespace>:<name>. The flag can be repeated to add multiple service accounts.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is go lang templates [http://golang.org/pkg/text/template/#pkg-overview].

`--user strings`

Username to bind to the role. The flag can be repeated to add multiple users.

`--validate string=["strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectrl create](#) - Create a resource from a file or from stdin

3.15.14 - kubectl create secret

Create a secret using a specified subcommand

Synopsis

Create a secret with specified type.

A docker-registry type secret is for accessing a container registry.

A generic type secret indicate an Opaque secret type.

A tls type secret holds TLS certificate and its associated key.

```
kubectl create secret (docker-registry | generic | tls)
```

Options

-h, --help

help for secret

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin
- [kubectl create secret docker-registry](#) - Create a secret for use with a Docker registry
- [kubectl create secret generic](#) - Create a secret from a local file, directory, or literal value
- [kubectl create secret tls](#) - Create a TLS secret

3.15.15 - kubectl create secret docker-registry

Create a secret for use with a Docker registry

Synopsis

Create a new secret for use with Docker registries.

Dockercfg secrets are used to authenticate against Docker registries.

When using the Docker command line to push images, you can authenticate to a registry by using the `docker login` command. For example, to push images to a registry, you can use the following command:

```
$ docker login DOCKER_REGISTRY_SERVER --username=DOCKER_USER --password=DOCKER_PASSWORD
```

That produces a `~/.dockercfg` file that is used by subsequent `'docker push'` and `'docker pull'` commands to authenticate to the registry. The email address is optional.

When creating applications, you may have a Docker registry that requires authentication. If you have nodes to pull images on your behalf, they must have the credentials. You can provide the credentials by creating a dockercfg secret and attaching it to your service account.

```
kubectl create secret docker-registry NAME --docker-username=user --docker-password=password
```

Examples

```
# If you do not already have a .dockercfg file, create a dockercfg secret directly
kubectl create secret docker-registry my-secret --docker-server=DOCKER_REGISTRY_SERVER --docker-username=DOCKER_USER --docker-password=DOCKER_PASSWORD

# Create a new secret named my-secret from ~/.docker/config.json
kubectl create secret docker-registry my-secret --from-file=path/to/.docker/config.json
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--append-hash`

Append a hash of the secret to its name.

`--docker-email` string

Email for Docker registry

`--docker-password` string

Password for Docker registry authentication

`--docker-server` string Default: "https://index.docker.io/v1/"

Server location for Docker registry

`--docker-username` string

Username for Docker registry authentication

`--dry-run` string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager` string Default: "kubectl-create"

Name of the manager used to track field ownership.

`--from-file` strings

Key files can be specified using their file path, in which case a default name of .dockerconfigjson will be given to them, or optionally with a name and file path, in which case the given name will be used. Specifying a directory will iterate each named file in the directory that is a valid secret key. For this command, the key should always be .dockerconfigjson.

`-h, --help`

help for docker-registry

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

--save-config

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

--validate string[="strict"] Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create secret](#) - Create a secret using a specified subcommand

3.15.16 - kubectl create secret generic

Create a secret from a local file, directory, or literal value

Synopsis

Create a secret based on a file, directory, or specified literal value.

A single secret may package one or more key/value pairs.

When creating a secret based on a file, the key will default to the basename of the file, and the value will default to the file content. If the basename is an invalid key or you wish to chose your own, you may specify an alternate key.

When creating a secret based on a directory, each file whose basename is a valid key in the directory will be packaged into the secret. Any directory entries except regular files are ignored (e.g. subdirectories, symlinks, devices, pipes, etc).

```
kubectl create secret generic NAME [--type=string] [--from-file=[key=]source] [--fr
```

Examples

```
# Create a new secret named my-secret with keys for each file in folder bar
```

```
kubectl create secret generic my-secret --from-file=path/to/bar
```

```
# Create a new secret named my-secret with specified keys instead of names on disc
```

```
kubectl create secret generic my-secret --from-file=ssh-privatekey=path/to/id_rsa
```

```
# Create a new secret named my-secret with key1=supersecret and key2=topsecret
```

```
kubectl create secret generic my-secret --from-literal=key1=supersecret --from-lit
```

```
# Create a new secret named my-secret using a combination of a file and a literal
```

```
kubectl create secret generic my-secret --from-file=ssh-privatekey=path/to/id_rsa
```

```
# Create a new secret named my-secret from env files
```

```
kubectl create secret generic my-secret --from-env-file=path/to/foo.env --from-en
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--append-hash`

Append a hash of the secret to its name.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`--from-env-file strings`

Specify the path to a file to read lines of key=val pairs to create a secret.

`--from-file strings`

Key files can be specified using their file path, in which case a default name will be given to them, or optionally with a name and file path, in which case the given name will be used. Specifying a directory will iterate each named file in the directory that is a valid secret key.

`--from-literal strings`

Specify a key and literal value to insert in secret (i.e. mykey=somevalue)

`-h, --help`

help for generic

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--type string`

The type of secret to create

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create secret](#) - Create a secret using a specified subcommand

3.15.17 - kubectl create secret tls

Create a TLS secret

Synopsis

Create a TLS secret from the given public/private key pair.

The public/private key pair must exist beforehand. The public key certificate must be .PEM encoded and match the given private key.

```
kubectl create secret tls NAME --cert=path/to/cert/file --key=path/to/key/file [--c
```

Examples

```
# Create a new TLS secret named tls-secret with the given key pair
kubectl create secret tls tls-secret --cert=path/to/tls.crt --key=path/to/tls.key
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to golang and jsonpath output formats.

--append-hash

Append a hash of the secret to its name.

--cert string

Path to PEM encoded public key certificate.

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`-h, --help`

help for tls

`--key string`

Path to private key associated with given certificate.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore"

will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create secret](#) - Create a secret using a specified subcommand

3.15.18 - kubectl create service

Create a service using a specified subcommand

Synopsis

Create a service using a specified subcommand.

```
kubectl create service [flags]
```

Options

-h, --help

help for service

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin
- [kubectl create service clusterip](#) - Create a ClusterIP service
- [kubectl create service externalname](#) - Create an ExternalName service
- [kubectl create service loadbalancer](#) - Create a LoadBalancer service
- [kubectl create service nodeport](#) - Create a NodePort service

3.15.19 - kubectl create service clusterip

Create a ClusterIP service

Synopsis

Create a ClusterIP service with the specified name.

```
kubectl create service clusterip NAME [--tcp=<port>:<targetPort>] [--dry-run=server]
```

Examples

```
# Create a new ClusterIP service named my-cs
kubectl create service clusterip my-cs --tcp=5678:8080

# Create a new ClusterIP service named my-cs (in headless mode)
kubectl create service clusterip my-cs --clusterip="None"
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--clusterip string

Assign your own ClusterIP or set to 'None' for a 'headless' service (no loadbalancing).

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`-h, --help`

help for clusterip

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--tcp strings`

Port pairs can be specified as '<port>:<targetPort>'.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create service](#) - Create a service using a specified subcommand

3.15.20 - kubectl create service externalname

Create an ExternalName service

Synopsis

Create an ExternalName service with the specified name.

ExternalName service references to an external DNS address instead of only pods, which will allow application authors to reference services that exist off platform, on other clusters, or locally.

```
kubectl create service externalname NAME --external-name external.name [--dry-run=s
```

Examples

```
# Create a new ExternalName service named my-ns
kubectl create service externalname my-ns --external-name bar.com
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--external-name string`

External name of service

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

-h, --help

help for externalname

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

--save-config

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--tcp strings

Port pairs can be specified as '<port>:<targetPort>'.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

--validate string[="strict"] Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create service](#) - Create a service using a specified subcommand

3.15.21 - kubectl create service loadbalancer

Create a LoadBalancer service

Synopsis

Create a LoadBalancer service with the specified name.

```
kubectl create service loadbalancer NAME [--tcp=port:targetPort] [--dry-run=server
```

Examples

```
# Create a new LoadBalancer service named my-lbs
kubectl create service loadbalancer my-lbs --tcp=5678:8080
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string=["unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

-h, --help

help for loadbalancer

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--tcp strings`

Port pairs can be specified as '<port>:<targetPort>'.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create service](#) - Create a service using a specified subcommand

3.15.22 - kubectl create service nodeport

Create a NodePort service

Synopsis

Create a NodePort service with the specified name.

```
kubectl create service nodeport NAME [--tcp=port:targetPort] [--dry-run=server|client]
```

Examples

```
# Create a new NodePort service named my-ns
kubectl create service nodeport my-ns --tcp=5678:8080
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-create"

Name of the manager used to track field ownership.

`-h, --help`

help for nodeport

`--node-port int`

Port used to expose the service on each node in a cluster.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--tcp strings`

Port pairs can be specified as '<port>:<targetPort>'.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create service](#) - Create a service using a specified subcommand

3.15.23 - kubectl create serviceaccount

Create a service account with the specified name

Synopsis

Create a service account with the specified name.

```
kubectl create serviceaccount NAME [--dry-run=server|client|none]
```

Examples

```
# Create a new service account named my-service-account
kubectl create serviceaccount my-service-account
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string["unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

--field-manager string Default: "kubectl-create"

Name of the manager used to track field ownership.

-h, --help

help for serviceaccount

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.15.24 - kubectl create token

Request a service account token

Synopsis

Request a service account token.

```
kubectl create token SERVICE_ACCOUNT_NAME
```

Examples

```
# Request a token to authenticate to the kube-apiserver as the service account "myapp"
kubectl create token myapp

# Request a token for a service account in a custom namespace
kubectl create token myapp --namespace myns

# Request a token with a custom expiration
kubectl create token myapp --duration 10m

# Request a token with a custom audience
kubectl create token myapp --audience https://example.com

# Request a token bound to an instance of a Secret object
kubectl create token myapp --bound-object-kind Secret --bound-object-name mysecret

# Request a token bound to an instance of a Secret object with a specific UID
kubectl create token myapp --bound-object-kind Secret --bound-object-name mysecret --bound-object-uid 1234567890
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--audience strings

Audience of the requested token. If unset, defaults to requesting a token for use with the Kubernetes API server. May be repeated to request a token valid for multiple audiences.

`--bound-object-kind` string

Kind of an object to bind the token to. Supported kinds are Node, Pod, Secret. If set, `--bound-object-name` must be provided.

`--bound-object-name` string

Name of an object to bind the token to. The token will expire when the object is deleted. Requires `--bound-object-kind`.

`--bound-object-uid` string

UID of an object to bind the token to. Requires `--bound-object-kind` and `--bound-object-name`. If unset, the UID of the existing object is used.

`--duration` duration

Requested lifetime of the issued token. If not set or if set to 0, the lifetime will be determined by the server automatically. The server may return a token with a longer or shorter lifetime.

`-h, --help`

help for token

`-o, --output` string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template` string

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl create](#) - Create a resource from a file or from stdin

3.16 - kubectl debug

Create debugging sessions for troubleshooting workloads and nodes

Synopsis

Debug cluster resources using interactive debugging containers.

'debug' provides automation for common debugging tasks for cluster objects identified by resource and name. Pods will be used by default if no resource is specified.

The action taken by 'debug' varies depending on what resource is specified. Supported actions include:

- Workload: Create a copy of an existing pod with certain attributes changed, for example changing the image tag to a new version.
- Workload: Add an ephemeral container to an already running pod, for example to add debugging utilities without restarting the pod.
- Node: Create a new pod that runs in the node's host namespaces and can access the node's filesystem.

Note: When a non-root user is configured for the entire target Pod, some capabilities granted by debug profile may not work.

```
kubectl debug (POD | TYPE[.VERSION].GROUP)/NAME [ -- COMMAND [args...] ]
```

Examples

```
# Create an interactive debugging session in pod mypod and immediately attach to it
kubectl debug mypod -it --image=busybox

# Create an interactive debugging session for the pod in the file pod.yaml and immediately attach to it
# (requires the EphemeralContainers feature to be enabled in the cluster)
kubectl debug -f pod.yaml -it --image=busybox

# Create a debug container named debugger using a custom automated debugging image
kubectl debug --image=myproj/debug-tools -c debugger mypod

# Create a copy of mypod adding a debug container and attach to it
kubectl debug mypod -it --image=busybox --copy-to=my-debugger

# Create a copy of mypod changing the command of mycontainer
```

```
kubectl debug mypod -it --copy-to=my-debugger --container=mycontainer -- sh

# Create a copy of mypod changing all container images to busybox
kubectl debug mypod --copy-to=my-debugger --set-image=*=busybox

# Create a copy of mypod adding a debug container and changing container images
kubectl debug mypod -it --copy-to=my-debugger --image=debian --set-image=app=app

# Create an interactive debugging session on a node and immediately attach to it
# The container will run in the host namespaces and the host's filesystem will be
kubectl debug node/mynode -it --image=busybox
```

Options

--arguments-only

If specified, everything after -- will be passed to the new container as Args instead of Command.

--attach

If true, wait for the container to start running, and then attach as if 'kubectl attach ...' were called. Default false, unless '-i/--stdin' is set, in which case the default is true.

-c, --container string

Container name to use for debug container.

--copy-to string

Create a copy of the target Pod with this name.

--custom string

Path to a JSON or YAML file containing a partial container spec to customize built-in debug profiles.

--env stringToString Default: []

Environment variables to set in the container.

`-f, --filename strings`

identifying the resource to debug

`-h, --help`

help for debug

`--image string`

Container image to use for debug container.

`--image-pull-policy string`

The image pull policy for the container. If left empty, this value will not be specified by the client and defaulted by the server.

`--keep-annotations`

If true, keep the original pod annotations.(This flag only works when used with '--copy-to')

`--keep-init-containers` Default: true

Run the init containers for the pod. Defaults to true.(This flag only works when used with '--copy-to')

`--keep-labels`

If true, keep the original pod labels.(This flag only works when used with '--copy-to')

`--keep-liveness`

If true, keep the original pod liveness probes.(This flag only works when used with '--copy-to')

`--keep-readiness`

If true, keep the original pod readiness probes.(This flag only works when used with '--copy-to')

`--keep-startup`

If true, keep the original startup probes.(This flag only works when used with '--copy-to')

--profile string Default: "general"

Options are "general", "baseline", "restricted", "netadmin" or "sysadmin". Defaults to "general"

-q, --quiet

If true, suppress informational messages.

--replace

When used with '--copy-to', delete the original Pod.

--same-node

When used with '--copy-to', schedule the copy of target Pod on the same node.

--set-image stringToString Default: []

When used with '--copy-to', a list of name=image pairs for changing container images, similar to how 'kubectl set image' works.

--share-processes Default: true

When used with '--copy-to', enable process namespace sharing in the copy.

-i, --stdin

Keep stdin open on the container(s) in the pod, even if nothing is attached.

--target string

When using an ephemeral container, target processes in this container name.

-t, --tty

Allocate a TTY for the debugging container.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero

means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.17 - kubectl delete

Delete resources by file names, stdin, resources and names, or by resources and label selector

Synopsis

Delete resources by file names, stdin, resources and names, or by resources and label selector.

JSON and YAML formats are accepted. Only one type of argument may be specified: file names, resources and names, or resources and label selector.

Some resources, such as pods, support graceful deletion. These resources define a default period before they are forcibly terminated (the grace period) but you may override that value with the `--grace-period` flag, or pass `--now` to set a grace-period of 1. Because these resources often represent entities in the cluster, deletion may not be acknowledged immediately. If the node hosting a pod is down or cannot reach the API server, termination may take significantly longer than the grace period. To force delete a resource, you must specify the `--force` flag. Note: only a subset of resources support graceful deletion. In absence of the support, the `--grace-period` flag is ignored.

IMPORTANT: Force deleting pods does not wait for confirmation that the pod's processes have been terminated, which can leave those processes running until the node detects the deletion and completes graceful deletion. If your processes use shared storage or talk to a remote API and depend on the name of the pod to identify themselves, force deleting those pods may result in multiple processes running on different machines using the same identification which may lead to data corruption or inconsistency. Only force delete pods when you are sure the pod is terminated, or if your application can tolerate multiple copies of the same pod running at once. Also, if you force delete pods, the scheduler may place new pods on those nodes before the node has released those resources and causing those pods to be evicted immediately.

Note that the delete command does NOT do resource version checks, so if someone submits an update to a resource right when you submit a delete, their update will be lost along with the rest of the resource.

After a CustomResourceDefinition is deleted, invalidation of discovery cache may take up to 6 hours. If you don't want to wait, you might want to run `"kubectl api-resources"` to refresh the discovery cache.

```
kubectl delete ([-f FILENAME] | [-k DIRECTORY] | TYPE [(NAME | -l label | --all)])
```

Examples

```
# Delete a pod using the type and name specified in pod.json
```

```
kubectl delete -f ./pod.json
```

```
# Delete resources from a directory containing kustomization.yaml - e.g. dir/kust
```

```
kubectl delete -k dir
```

```
# Delete resources from all files that end with '.json'
```

```
kubectl delete -f '*.json'
```

```
# Delete a pod based on the type and name in the JSON passed into stdin
```

```
cat pod.json | kubectl delete -f -
```

```
# Delete pods and services with same names "baz" and "foo"
```

```
kubectl delete pod,service baz foo
```

```
# Delete pods and services with label name=myLabel
```

```
kubectl delete pods,services -l name=myLabel
```

```
# Delete a pod with minimal delay
```

```
kubectl delete pod foo --now
```

```
# Force delete a pod on a dead node
```

```
kubectl delete pod foo --force
```

```
# Delete all pods
```

```
kubectl delete pods --all
```

```
# Delete all pods only if the user confirms the deletion
```

```
kubectl delete pods --all --interactive
```

Options

--all

Delete all resources, in the namespace of the specified resource types.

`-A, --all-namespaces`

If present, list the requested object(s) across all namespaces. Namespace in current context is ignored even if specified with `--namespace`.

`--cascade string[="background"]` Default: "background"

Must be "background", "orphan", or "foreground". Selects the deletion cascading strategy for the dependents (e.g. Pods created by a ReplicationController). Defaults to background.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-selector string`

Selector (field query) to filter on, supports '=', '==', and '!='.(e.g. `--field-selector key1=value1,key2=value2`). The server only supports a limited number of field queries per type.

`-f, --filename strings`

containing the resource to delete.

`--force`

If true, immediately remove resources from API and bypass graceful deletion. Note that immediate deletion of some resources may result in inconsistency or data loss and requires confirmation.

`--grace-period int` Default: -1

Period of time in seconds given to the resource to terminate gracefully. Ignored if negative. Set to 1 for immediate shutdown. Can only be set to 0 when `--force` is true (force deletion).

`-h, --help`

help for delete

`--ignore-not-found`

Treat "resource not found" as a successful delete. Defaults to "true" when --all is specified.

-i, --interactive

If true, delete resource only when user confirms.

-k, --kustomize string

Process a kustomization directory. This flag can't be used together with -f or -R.

--now

If true, resources are signaled for immediate shutdown (same as --grace-period=1).

-o, --output string

Output mode. Use "-o name" for shorter output (resource/name).

--raw string

Raw URI to DELETE to the server. Uses the transport specified by the kubeconfig file.

-R, --recursive

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

-l, --selector string

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

--timeout duration

The length of time to wait before giving up on a delete, zero means determine a timeout from the size of the object

--wait Default: true

If true, wait for resources to be gone before returning. This waits for finalizers.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectrl](#) - kubectrl controls the Kubernetes cluster manager

3.18 - kubectl describe

Show details of a specific resource or group of resources

Synopsis

Show details of a specific resource or group of resources.

Print a detailed description of the selected resources, including related resources such as events or controllers. You may select a single object by name, all objects of that type, provide a name prefix, or label selector. For example:

```
$ kubectl describe TYPE NAME_PREFIX
```

will first check for an exact match on TYPE and NAME_PREFIX. If no such resource exists, it will output details for every resource that has a name prefixed with NAME_PREFIX.

Use "kubectl api-resources" for a complete list of supported resources.

```
kubectl describe (-f FILENAME | TYPE [NAME_PREFIX | -l label] | TYPE/NAME)
```

Examples

```
# Describe a node
kubectl describe nodes kubernetes-node-emt8.c.myproject.internal

# Describe a pod
kubectl describe pods/nginx

# Describe a pod identified by type and name in "pod.json"
kubectl describe -f pod.json

# Describe all pods
kubectl describe pods

# Describe pods by label name=myLabel
kubectl describe pods -l name=myLabel

# Describe all pods managed by the 'frontend' replication controller
```

```
# (rc-created pods get the name of the rc as a prefix in the pod name)
kubectl describe pods frontend
```

Options

-A, --all-namespaces

If present, list the requested object(s) across all namespaces. Namespace in current context is ignored even if specified with `--namespace`.

--chunk-size int Default: 500

Return large lists in chunks rather than all at once. Pass 0 to disable.

-f, --filename strings

Filename, directory, or URL to files containing the resource to describe

-h, --help

help for describe

-k, --kustomize string

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

-R, --recursive

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

-l, --selector string

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

--show-events Default: true

If true, display events related to the described object. Defaults to true for a single object, false for multiple objects and prefix matching.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectrl](#) - kubectrl controls the Kubernetes cluster manager

3.19 - kubectl diff

Diff the live version against a would-be applied version

Synopsis

Diff configurations specified by file name or stdin between the current online configuration, and the configuration as it would be if applied.

The output is always YAML.

KUBECTL_EXTERNAL_DIFF environment variable can be used to select your own diff command. Users can use external commands with params too, example:

```
KUBECTL_EXTERNAL_DIFF="colordiff -N -u"
```

By default, the "diff" command available in your path will be run with the "-u" (unified diff) and "-N" (treat absent files as empty) options.

Exit status: 0 No differences were found. 1 Differences were found. >1 Kubectl or diff failed with an error.

Note: KUBECTL_EXTERNAL_DIFF, if used, is expected to follow that convention.

```
kubectl diff -f FILENAME
```

Examples

```
# Diff resources included in pod.json
kubectl diff -f pod.json

# Diff file read from stdin
cat service.yaml | kubectl diff -f -
```

Options

```
--concurrency int    Default: 1
```

Number of objects to process in parallel when diffing against the live version. Larger number = faster, but more memory, I/O and CPU over that shorter period of time.

`--field-manager string` Default: "kubectl-client-side-apply"

Name of the manager used to track field ownership.

`-f, --filename strings`

Filename, directory, or URL to files contains the configuration to diff

`--force-conflicts`

If true, server-side apply will force the changes against conflicts.

`-h, --help`

help for diff

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`--prune`

Include resources that would be deleted by pruning. Can be used with `-l` and default shows all resources would be pruned

`--prune-allowlist strings`

Overwrite the default allowlist with `<group/version/kind>` for `--prune`

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--server-side`

If true, apply runs in the server instead of the client.

`--show-managed-fields`

If true, include managed fields in the diff.

`--show-secrets`

If true, do not mask secret values in the diff.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.20 - kubectl drain

Drain node in preparation for maintenance

Synopsis

Drain node in preparation for maintenance.

The given node will be marked unschedulable to prevent new pods from arriving.

'drain' evicts the pods if the API server supports

<https://kubernetes.io/docs/concepts/workloads/pods/disruptions/> eviction

<https://kubernetes.io/docs/concepts/workloads/pods/disruptions/> . Otherwise, it will use normal DELETE to delete the pods. The 'drain' evicts or deletes all pods except mirror pods (which cannot be deleted through the API server). If there are daemon set-managed pods, drain will not proceed without --ignore-daemonsets, and regardless it will not delete any daemon set-managed pods, because those pods would be immediately replaced by the daemon set controller, which ignores unschedulable markings. If there are any pods that are neither mirror pods nor managed by a replication controller, replica set, daemon set, stateful set, or job, then drain will not delete any pods unless you use --force. --force will also allow deletion to proceed if the managing resource of one or more pods is missing.

'drain' waits for graceful termination. You should not operate on the machine until the command completes.

When you are ready to put the node back into service, use kubectl uncordon, which will make the node schedulable again.

https://kubernetes.io/images/docs/kubectl_drain.svg

Workflowhttps://kubernetes.io/images/docs/kubectl_drain.svg

```
kubectl drain NODE
```

Examples

```
# Drain node "foo", even if there are pods not managed by a replication controller
kubectl drain foo --force
```

```
# As above, but abort if there are pods not managed by a replication controller,  
kubectl drain foo --grace-period=900
```

Options

`--chunk-size int` Default: 500

Return large lists in chunks rather than all at once. Pass 0 to disable.

`--delete-emptydir-data`

Continue even if there are pods using emptyDir (local data that will be deleted when the node is drained).

`--disable-eviction`

Force drain to use delete, even if eviction is supported. This will bypass checking PodDisruptionBudgets, use with caution.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--force`

Continue even if there are pods that do not declare a controller.

`--grace-period int` Default: -1

Period of time in seconds given to each pod to terminate gracefully. If negative, the default value specified in the pod will be used.

`-h, --help`

help for drain

`--ignore-daemonsets`

Ignore DaemonSet-managed pods.

`--pod-selector string`

Label selector to filter pods on the node

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--skip-wait-for-delete-timeout int`

If pod DeletionTimestamp older than N seconds, skip waiting for the pod. Seconds must be greater than 0 to skip.

`--timeout duration`

The length of time to wait before giving up, zero means infinite

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cAdvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.21 - kubectl edit

Edit a resource on the server

Synopsis

Edit a resource from the default editor.

The edit command allows you to directly edit any API resource you can retrieve via the command-line tools. It will open the editor defined by your KUBE_EDITOR, or EDITOR environment variables, or fall back to 'vi' for Linux or 'notepad' for Windows. When attempting to open the editor, it will first attempt to use the shell that has been defined in the 'SHELL' environment variable. If this is not defined, the default shell will be used, which is '/bin/bash' for Linux or 'cmd' for Windows.

You can edit multiple objects, although changes are applied one at a time. The command accepts file names as well as command-line arguments, although the files you point to must be previously saved versions of resources.

Editing is done with the API version used to fetch the resource. To edit using a specific API version, fully-qualify the resource, version, and group.

The default format is YAML. To edit in JSON, specify "-o json".

The flag --windows-line-endings can be used to force Windows line endings, otherwise the default for your operating system will be used.

In the event an error occurs while updating, a temporary file will be created on disk that contains your unapplied changes. The most common error when updating a resource is another editor changing the resource on the server. When this occurs, you will have to apply your changes to the newer version of the resource, or update your temporary saved copy to include the latest resource version.

```
kubectl edit (RESOURCE/NAME | -f FILENAME)
```

Examples

```
# Edit the service named 'registry'
kubectl edit svc/registry

# Use an alternative editor
```

```
KUBE_EDITOR="nano" kubectl edit svc/registry

# Edit the job 'myjob' in JSON using the v1 API format
kubectl edit job.v1.batch/myjob -o json

# Edit the deployment 'mydeployment' in YAML and save the modified config in its
kubectl edit deployment/mydeployment -o yaml --save-config

# Edit the 'status' subresource for the 'mydeployment' deployment
kubectl edit deployment mydeployment --subresource='status'
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--field-manager` string Default: "kubectl-edit"

Name of the manager used to track field ownership.

`-f, --filename` strings

Filename, directory, or URL to files to use to edit the resource

`-h, --help`

help for edit

`-k, --kustomize` string

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output` string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--output-patch`

Output the patch if the resource is edited.

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform `kubectl` apply on this object in the future.

`--show-managed-fields`

If true, keep the `managedFields` when printing objects in JSON or YAML format.

`--subresource string`

If specified, edit will operate on the subresource of the requested object.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is `gotemplates` [<http://golang.org/pkg/text/template/#pkg-overview>].

`--validate string[="strict"]` Default: "strict"

Must be one of: `strict` (or `true`), `warn`, `ignore` (or `false`). `"true"` or `"strict"` will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. `"warn"` will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as `"ignore"` otherwise. `"false"` or `"ignore"` will not perform any schema validation, silently dropping any unknown or duplicate fields.

`--windows-line-endings`

Defaults to the line ending native to your platform.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectrl](#) - kubectrl controls the Kubernetes cluster manager

3.22 - kubectl events

List events

Synopsis

Display events.

Prints a table of the most important information about events. You can request events for a namespace, for all namespace, or filtered to only those pertaining to a specified resource.

```
kubectl events [(-o|--output=json|yaml|kyaml|name|go-template|go-template-file|ter
```

Examples

```
# List recent events in the default namespace
kubectl events
```

```
# List recent events in all namespaces
kubectl events --all-namespaces
```

```
# List recent events for the specified pod, then wait for more events and list them
kubectl events --for pod/web-pod-13je7 --watch
```

```
# List recent events in YAML format
kubectl events -oyaml
```

```
# List recent only events of type 'Warning' or 'Normal'
kubectl events --types=Warning,Normal
```

Options

```
-A, --all-namespaces
```

If present, list the requested object(s) across all namespaces. Namespace in current context is ignored even if specified with --namespace.

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--chunk-size int Default: 500

Return large lists in chunks rather than all at once. Pass 0 to disable.

--for string

Filter events to only those pertaining to the specified resource.

-h, --help

help for events

--no-headers

When using the default output format, don't print headers.

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is goyaml templates [http://golang.org/pkg/text/template/#pkg-overview].

--types strings

Output only events of given types.

`-w, --watch`

After listing the requested events, watch for more events.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectrl](#) - kubectrl controls the Kubernetes cluster manager

3.23 - kubectl exec

Execute a command in a container

Synopsis

Execute a command in a container.

```
kubectl exec (POD | TYPE/NAME) [-c CONTAINER] [flags] -- COMMAND [args...]
```

Examples

```
# Get output from running the 'date' command from pod mypod, using the first container
kubectl exec mypod -- date

# Get output from running the 'date' command in ruby-container from pod mypod
kubectl exec mypod -c ruby-container -- date

# Switch to raw terminal mode; sends stdin to 'bash' in ruby-container from pod mypod
# and sends stdout/stderr from 'bash' back to the client
kubectl exec mypod -c ruby-container -i -t -- bash -il

# List contents of /usr from the first container of pod mypod and sort by modification time
# If the command you want to execute in the pod has any flags in common (e.g. -i)
# you must use two dashes (--) to separate your command's flags/arguments
# Also note, do not surround your command and its flags/arguments with quotes
# unless that is how you would execute it normally (i.e., do ls -t /usr, not "ls -t /usr")
kubectl exec mypod -i -t -- ls -t /usr

# Get output from running 'date' command from the first pod of the deployment mydeployment
kubectl exec deploy/mydeployment -- date

# Get output from running 'date' command from the first pod of the service myservice
kubectl exec svc/myservice -- date
```

Options

-c, --container string

Container name. If omitted, use the `kubectrl.kubernetes.io/default-container` annotation for selecting the container to be attached or the first container in the pod will be chosen

`-f, --filename strings`

to use to exec into the resource

`-h, --help`

help for exec

`--pod-running-timeout duration` Default: 1m0s

The length of time (like 5s, 2m, or 3h, higher than zero) to wait until at least one pod is running

`-q, --quiet`

Only print output from the remote session

`-i, --stdin`

Pass stdin to the container

`-t, --tty`

Stdin is a TTY

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.24 - kubectl explain

Get documentation for a resource

Synopsis

Describe fields and structure of various resources.

This command describes the fields associated with each supported API resource. Fields are identified via a simple JSONPath identifier:

```
TYPE.FIELDNAME[.FIELDNAME]
```

Information about each field is retrieved from the server in OpenAPI format.

Use "kubectl api-resources" for a complete list of supported resources.

```
kubectl explain TYPE [--recursive=FALSE|TRUE] [--api-version=api-version-group] [-c
```



Examples

```
# Get the documentation of the resource and its fields
kubectl explain pods

# Get all the fields in the resource
kubectl explain pods --recursive

# Get fields in the resource up to a specific recursive depth
kubectl explain pods --recursive --max-depth=2

# Get the explanation for deployment in supported api versions
kubectl explain deployments --api-version=apps/v1

# Get the documentation of a specific field of a resource
kubectl explain pods.spec.containers

# Get the documentation of resources in different format
kubectl explain deployment --output=plaintext-openapi2
```


Options

`--api-version string`

Get different explanations for particular API version (API group/version)

`-h, --help`

help for explain

`--max-depth int`

Maximum recursion depth when printing nested fields with `--recursive`. 0 means no limit. Requires `--recursive` when greater than 0.

`-o, --output string` Default: "plaintext"

Format in which to render the schema (plaintext, plaintext-openapi2)

`-R, --recursive`

Print the fields of fields. Use `--max-depth` to cap the recursion depth.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.25 - kubectl expose

Take a replication controller, service, deployment or pod and expose it as a new Kubernetes service

Synopsis

Expose a resource as a new Kubernetes service.

Looks up a deployment, service, replica set, replication controller or pod by name and uses the selector for that resource as the selector for a new service on the specified port. A deployment or replica set will be exposed as a service only if its selector is convertible to a selector that service supports, i.e. when the selector contains only the matchLabels component. Note that if no port is specified via --port and the exposed resource has multiple ports, all will be re-used by the new service. Also if no labels are specified, the new service will re-use the labels from the resource it exposes.

Possible resources include (case insensitive):

pod (po), service (svc), replicationcontroller (rc), deployment (deploy), replicaset (rs)

```
kubectl expose (-f FILENAME | TYPE NAME) [--port=port] [--protocol=TCP|UDP|SCTP] [...]
```

Examples

```
# Create a service for a replicated nginx, which serves on port 80 and connects to the back-end server on port 8000
kubectl expose rc nginx --port=80 --target-port=8000
```

```
# Create a service for a replication controller identified by type and name specified in a yaml file
kubectl expose -f nginx-controller.yaml --port=80 --target-port=8000
```

```
# Create a service for a pod valid-pod, which serves on port 444 with the name "frontend"
kubectl expose pod valid-pod --port=444 --name=frontend
```

```
# Create a second service based on the above service, exposing the container port 8443
kubectl expose service nginx --port=443 --target-port=8443 --name=nginx-https
```

```
# Create a service for a replicated streaming application on port 4100 balancing across 3 replicas
kubectl expose rc streamer --port=4100 --protocol=UDP --name=video-stream
```

```
# Create a service for a replicated nginx using replica set, which serves on port 80
```

```
kubectl expose rs nginx --port=80 --target-port=8000
```

```
# Create a service for an nginx deployment, which serves on port 80 and connects  
kubectl expose deployment nginx --port=80 --target-port=8000
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--cluster-ip` string

ClusterIP to be assigned to the service. Leave empty to auto-allocate, or set to 'None' to create a headless service.

`--dry-run` string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--external-ip` string

Additional external IP address (not managed by Kubernetes) to accept for the service. If this IP is routed to a node, the service can be accessed by this IP in addition to its generated service IP.

`--field-manager` string Default: "kubectl-expose"

Name of the manager used to track field ownership.

`-f, --filename` strings

Filename, directory, or URL to files identifying the resource to expose a service

`-h, --help`

help for expose

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-l, --labels string`

Labels to apply to the service created by this call.

`--load-balancer-ip string`

IP to assign to the LoadBalancer. If empty, an ephemeral IP will be created and used (cloud-provider specific).

`--name string`

The name for the newly created object.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--override-type string` Default: "merge"

The method used to override the generated object: json, merge, or strategic.

`--overrides string`

An inline JSON override for the generated object. If this is non-empty, it is used to override the generated object. Requires that the object supply a valid `apiVersion` field.

`--port string`

The port that the service should serve on. Copied from the resource being exposed, if unspecified

`--protocol string`

The network protocol for the service to be created. Default is 'TCP'.

`-R, --recursive`

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform `kubectl apply` on this object in the future.

`--selector string`

A label selector to use for this service. Only equality-based selector requirements are supported. If empty (the default) infer the selector from the resource being exposed.

`--session-affinity string`

If non-empty, set the session affinity for the service to this; legal values: 'None', 'ClientIP'

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--target-port string`

Name or number for the port on the container that the service should direct traffic to. Optional.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--type string`

Type for this service: ClusterIP, NodePort, LoadBalancer, or ExternalName. Default is 'ClusterIP'.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.26 - kubectl get

Display one or many resources

Synopsis

Display one or many resources.

Prints a table of the most important information about the specified resources. You can filter the list using a label selector and the `--selector` flag. If the desired resource type is namespaced you will only see results in the current namespace if you don't specify any namespace.

By specifying the output as 'template' and providing a Go template as the value of the `--template` flag, you can filter the attributes of the fetched resources.

Use "kubectl api-resources" for a complete list of supported resources.

```
kubectl get [(-o|--output=json|yaml|kyaml|name|go-template|go-template-file|template)
```

Examples

```
# List all pods in ps output format
kubectl get pods
```

```
# List all pods in ps output format with more information (such as node name)
kubectl get pods -o wide
```

```
# List a single replication controller with specified NAME in ps output format
kubectl get replicationcontroller web
```

```
# List deployments in JSON output format, in the "v1" version of the "apps" API group
kubectl get deployments.v1.apps -o json
```

```
# List a single pod in JSON output format
kubectl get -o json pod web-pod-13je7
```

```
# List a pod identified by type and name specified in "pod.yaml" in JSON output format
kubectl get -f pod.yaml -o json
```

```
# List resources from a directory with kustomization.yaml - e.g. dir/kustomization.yaml
```

```
kubectl get -k dir/

# Return only the phase value of the specified pod
kubectl get -o template pod/web-pod-13je7 --template={{.status.phase}}

# List resource information in custom columns
kubectl get pod test-pod -o custom-columns=CONTAINER:.spec.containers[0].name,IM/

# List all replication controllers and services together in ps output format
kubectl get rc,services

# List one or more resources by their type and names
kubectl get rc/web service/frontend pods/web-pod-13je7

# List the 'status' subresource for a single pod
kubectl get pod web-pod-13je7 --subresource status

# List all deployments in namespace 'backend'
kubectl get deployments.apps --namespace backend

# List all pods existing in all namespaces
kubectl get pods --all-namespaces
```

Options

-A, --all-namespaces

If present, list the requested object(s) across all namespaces. Namespace in current context is ignored even if specified with `--namespace`.

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--chunk-size int Default: 500

Return large lists in chunks rather than all at once. Pass 0 to disable.

--field-selector string

Selector (field query) to filter on, supports '=', '==', and '!='.(e.g. --field-selector key1=value1,key2=value2). The server only supports a limited number of field queries per type.

-f, --filename strings

Filename, directory, or URL to files identifying the resource to get from a server.

-h, --help

help for get

--ignore-not-found

If set to true, suppresses NotFound error for specific objects that do not exist. Using this flag with commands that query for collections of resources has no effect when no resources are found.

-k, --kustomize string

Process the kustomization directory. This flag can't be used together with -f or -R.

-L, --label-columns strings

Accepts a comma separated list of labels that are going to be presented as columns. Names are case-sensitive. You can also use multiple flag options like -L label1 -L label2...

--no-headers

When using the default or custom-column output format, don't print headers (default print headers).

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file, custom-columns, custom-columns-file, wide). See custom columns [<https://kubernetes.io/docs/reference/kubectl/#custom-columns>], go lang template [<http://golang.org/pkg/text/template/#pkg-overview>] and jsonpath template [<https://kubernetes.io/docs/reference/kubectl/jsonpath/>].

--output-watch-events

Output watch event objects when --watch or --watch-only is used. Existing objects are output as initial ADDED events.

--raw string

Raw URI to request from the server. Uses the transport specified by the kubeconfig file.

-R, --recursive

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

-l, --selector string

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

--server-print Default: true

If true, have the server return the appropriate table output. Supports extension APIs and CRDs.

--show-kind

If present, list the resource type for the requested object(s).

--show-labels

When printing, show all labels as the last column (default hide labels column)

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--sort-by string

If non-empty, sort list types using this field specification. The field specification is expressed as a JSONPath expression (e.g. '{.metadata.name}'). The field in the API resource specified by this JSONPath expression must be an integer or a string.

--subresource string

If specified, gets the subresource of the requested object.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`-w, --watch`

After listing/getting the requested object, watch for changes.

`--watch-only`

Watch for changes to the requested object(s), without listing/getting first.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.27 - kubectl kuberc

Manage kuberc configuration files

Synopsis

Manage user preferences (kuberc) file.

The kuberc file allows you to customize your kubectl experience.

```
kubectl kuberc SUBCOMMAND
```

Examples

```
# View the current kuberc configuration
kubectl kuberc view

# Set a default value for a command flag
kubectl kuberc set --section defaults --command get --option output=wide

# Create an alias for a command
kubectl kuberc set --section aliases --name getn --command get --prependarg nodes
```

Options

```
-h, --help
```

help for kuberc

Parent Options Inherited

```
--as string
```

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl kuberc set](#) - Set values in the kuberc configuration
- [kubectl kuberc view](#) - Display the current kuberc configuration

3.27.1 - kubectl kuberc set

Set values in the kuberc configuration

Synopsis

Set values in the kuberc configuration file.

Use --section to specify whether to set defaults or aliases.

For defaults: Sets default flag values for kubectl commands. The --command flag should specify only the command (e.g., "get", "create", "set env"), not resources.

For aliases: Creates command aliases with optional default flag values and arguments. Use --prependarg and --appendarg to include resources or other arguments.

```
kubectl kuberc set --section (defaults|aliases) --command COMMAND
```

Examples

```
# Set default output format for 'get' command
kubectl kuberc set --section defaults --command get --option output=wide

# Set default output format for a subcommand
kubectl kuberc set --section defaults --command "set env" --option output=yaml

# Create an alias 'getn' for 'get' command with prepended 'nodes' resource
kubectl kuberc set --section aliases --name getn --command get --prependarg nodes

# Create an alias 'runx' for 'run' command with appended arguments
kubectl kuberc set --section aliases --name runx --command run --option image=nginx

# Overwrite an existing default
kubectl kuberc set --section defaults --command get --option output=json --overwrite

# Set the credential plugin policy and allowlist
kubectl kuberc set --section credentialplugin --policy Allowlist --allowlist-entries
```

Options

`--allowlist-entry strings`

Allowlist entry the form field=value (can be specified multiple times)

`--appendarg strings`

Argument to append to the command (can be specified multiple times, for aliases only)

`--command string`

Command to configure (e.g., 'get', 'create', 'set env')

`-h, --help`

help for set

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--name string`

Alias name (required for --section=aliases)

`--option strings`

Flag option in the form flag=value (can be specified multiple times)

`--overwrite`

Allow overwriting existing entries

`--policy string`

Plugin policy to use for exec credential plugins, must be one of 'AllowAll', 'DenyAll' or 'Allowlist'

`--prependarg strings`

Argument to prepend to the command (can be specified multiple times, for aliases only)

--section string

Section to modify: 'defaults', 'aliases', or 'credentialplugin'

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

--cache-dir string Default: "\$HOME/.kube/cache"

Default cache directory

--certificate-authority string

Path to a cert file for the certificate authority

--client-certificate string

Path to a client certificate file for TLS

--client-key string

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl kuberc](#) - Manage kuberc configuration files

3.27.2 - kubectl kuberc view

Display the current kuberc configuration

Synopsis

Display the contents of the kuberc file in the specified output format.

```
kubectl kuberc view
```

Examples

```
# View kuberc configuration in YAML format (default)
kubectl kuberc view

# View kuberc configuration in JSON format
kubectl kuberc view --output json

# View a specific kuberc file
kubectl kuberc view --kuberc /path/to/kuberc
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

-h, --help

help for view

--kuberc string

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

-o, --output string Default: "yaml"

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none|cpu|heap|goroutine|threadcreate|block|mutex|trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect! kuberc](#) - Manage kuberc configuration files

3.28 - kubectl kustomize

Build a kustomization target from a directory or URL

Synopsis

Build a set of KRM resources using a 'kustomization.yaml' file. The DIR argument must be a path to a directory containing 'kustomization.yaml', or a git repository URL with a path suffix specifying same with respect to the repository root. If DIR is omitted, '.' is assumed.

```
kubectl kustomize DIR [flags]
```

Examples

```
# Build the current working directory
kubectl kustomize

# Build some shared configuration directory
kubectl kustomize /home/config/production

# Build from github
kubectl kustomize https://github.com/kubernetes-sigs/kustomize.git/examples/hello
```

Options

--as-current-user

use the uid and gid of the command executor to run the function in the container

--enable-alpha-plugins

enable kustomize plugins

--enable-helm

Enable use of the Helm chart inflator generator.

`-e, --env strings`

a list of environment variables to be used by functions

`--helm-api-versions strings`

Kubernetes api versions used by Helm for Capabilities.APIVersions

`--helm-command string` Default: "helm"

helm command (path to executable)

`--helm-debug`

Enable debug output from the Helm chart inflator generator.

`--helm-kube-version string`

Kubernetes version used by Helm for Capabilities.KubeVersion

`-h, --help`

help for kustomize

`--load-restrictor string` Default: "LoadRestrictionsRootOnly"

if set to 'LoadRestrictionsNone', local kustomizations may load files from outside their root. This does, however, break the relocatability of the kustomization.

`--mount strings`

a list of storage options read from the filesystem

`--network`

enable network access for functions that declare it

`--network-name string` Default: "bridge"

the docker network to run the container in

`-o, --output string`

If specified, write output to this path.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectrl](#) - kubectrl controls the Kubernetes cluster manager

3.29 - kubectl label

Update the labels on a resource

Synopsis

Update the labels on a resource.

- A label key and value must begin with a letter or number, and may contain letters, numbers, hyphens, dots, and underscores, up to 63 characters each.
- Optionally, the key can begin with a DNS subdomain prefix and a single '/', like example.com/my-app.
- If --overwrite is true, then existing labels can be overwritten, otherwise attempting to overwrite a label will result in an error.
- If --resource-version is specified, then updates will use this resource version, otherwise the existing resource-version will be used.

```
kubectl label [--overwrite] (-f FILENAME | TYPE NAME) KEY_1=VAL_1 ... KEY_N=VAL_N
```

Examples

```
# Update pod 'foo' with the label 'unhealthy' and the value 'true'
```

```
kubectl label pods foo unhealthy=true
```

```
# Update pod 'foo' with the label 'status' and the value 'unhealthy', overwriting
```

```
kubectl label --overwrite pods foo status=unhealthy
```

```
# Update all pods in the namespace
```

```
kubectl label pods --all status=unhealthy
```

```
# Update a pod identified by the type and name in "pod.json"
```

```
kubectl label -f pod.json status=unhealthy
```

```
# Update pod 'foo' only if the resource is unchanged from version 1
```

```
kubectl label pods foo status=unhealthy --resource-version=1
```

```
# Update pod 'foo' by removing a label named 'bar' if it exists
```

```
# Does not require the --overwrite flag
kubect1 label pods foo bar-
```

Options

`--all`

Select all resources, in the namespace of the specified resource types

`-A, --all-namespaces`

If true, check the specified action in all namespaces.

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goolang and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubect1-label"

Name of the manager used to track field ownership.

`--field-selector string`

Selector (field query) to filter on, supports '=', '==', and '!='.(e.g. `--field-selector key1=value1,key2=value2`). The server only supports a limited number of field queries per type.

`-f, --filename strings`

Filename, directory, or URL to files identifying the resource to update the labels

`-h, --help`

help for label

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`--list`

If true, display the labels for a given resource.

`--local`

If true, label will NOT contact api-server but run locally.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--overwrite`

If true, allow labels to be overwritten, otherwise reject label updates that overwrite existing labels.

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--resource-version string`

If non-empty, the labels update will only succeed if this is the current resource-version for the object. Only valid when specifying a single resource.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [http://golang.org/pkg/text/template/#pkg-overview].

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

--cache-dir string Default: "\$HOME/.kube/cache"

Default cache directory

--certificate-authority string

Path to a cert file for the certificate authority

--client-certificate string

Path to a client certificate file for TLS

--client-key string

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output` string Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url` string

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectrl](#) - kubectrl controls the Kubernetes cluster manager

3.30 - kubectl logs

Print the logs for a container in a pod

Synopsis

Print the logs for a container in a pod or specified resource. If the pod has only one container, the container name is optional.

```
kubectl logs [-f] [-p] (POD | TYPE/NAME) [-c CONTAINER]
```

Examples

```
# Return snapshot logs from pod nginx with only one container
kubectl logs nginx
```

```
# Return snapshot logs from pod nginx, prefixing each line with the source pod and container name
kubectl logs nginx --prefix
```

```
# Return snapshot logs from pod nginx, limiting output to 500 bytes
kubectl logs nginx --limit-bytes=500
```

```
# Return snapshot logs from pod nginx, waiting up to 20 seconds for it to start running
kubectl logs nginx --pod-running-timeout=20s
```

```
# Return snapshot logs from pod nginx with multi containers
kubectl logs nginx --all-containers=true
```

```
# Return snapshot logs from all pods in the deployment nginx
kubectl logs deployment/nginx --all-pods=true
```

```
# Return snapshot logs from all containers in pods defined by label app=nginx
kubectl logs -l app=nginx --all-containers=true
```

```
# Return snapshot logs from all pods defined by label app=nginx, limiting concurrent log requests
kubectl logs -l app=nginx --max-log-requests=10
```

```
# Return snapshot of previous terminated ruby container logs from pod web-1
kubectl logs -p -c ruby web-1
```

```
# Begin streaming the logs from pod nginx, continuing even if errors occur
kubectl logs nginx -f --ignore-errors=true
```

```
# Begin streaming the logs of the ruby container in pod web-1
kubectl logs -f -c ruby web-1

# Begin streaming the logs from all containers in pods defined by label app=nginx
kubectl logs -f -l app=nginx --all-containers=true

# Display only the most recent 20 lines of output in pod nginx
kubectl logs --tail=20 nginx

# Show all logs from pod nginx written in the last hour
kubectl logs --since=1h nginx

# Show all logs with timestamps from pod nginx starting from August 30, 2024, at
kubectl logs nginx --since-time=2024-08-30T06:00:00Z --timestamps=true

# Show logs from a kubelet with an expired serving certificate
kubectl logs --insecure-skip-tls-verify-backend nginx

# Return snapshot logs from first container of a job named hello
kubectl logs job/hello

# Return snapshot logs from container nginx-1 of a deployment named nginx
kubectl logs deployment/nginx -c nginx-1
```

Options

`--all-containers`

Get all containers' logs in the pod(s).

`--all-pods`

Get logs from all pod(s). Sets prefix to true.

`-c, --container string`

Print the logs of this container

`-f, --follow`

Specify if the logs should be streamed.

`-h, --help`

help for logs

`--ignore-errors`

If watching / following pod logs, allow for any errors that occur to be non-fatal

`--insecure-skip-tls-verify-backend`

Skip verifying the identity of the kubelet that logs are requested from. In theory, an attacker could provide invalid log content back. You might want to use this if your kubelet serving certificates have expired.

`--limit-bytes int`

Maximum bytes of logs to return. Defaults to no limit.

`--max-log-requests int` Default: 5

Specify maximum number of concurrent logs to follow when using by a selector. Defaults to 5.

`--pod-running-timeout duration` Default: 20s

The length of time (like 5s, 2m, or 3h, higher than zero) to wait until at least one pod is running

`--prefix`

Prefix each log line with the log source (pod name and container name)

`-p, --previous`

If true, print the logs for the previous instance of the container in a pod if it exists.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

`--since duration`

Only return logs newer than a relative duration like 5s, 2m, or 3h. Defaults to all logs. Only one of since-time / since may be used.

--since-time string

Only return logs after a specific date (RFC3339). Defaults to all logs. Only one of since-time / since may be used.

--tail int Default: -1

Lines of recent log file to display. Defaults to -1 with no selector, showing all log lines otherwise 10, if a selector is provided.

--timestamps

Include timestamps on each line in the log output

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

--cache-dir string Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.31 - kubectl options

Print the list of flags inherited by all commands

Synopsis

Print the list of flags inherited by all commands

```
kubectl options [flags]
```

Examples

```
# Print flags inherited by all commands  
kubectl options
```

Options

-h, --help

help for options

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.32 - kubectl patch

Update fields of a resource

Synopsis

Update fields of a resource using strategic merge patch, a JSON merge patch, or a JSON patch.

JSON and YAML formats are accepted.

Note: Strategic merge patch is not supported for custom resources.

```
kubectl patch (-f FILENAME | TYPE NAME) [-p PATCH|--patch-file FILE]
```

Examples

```
# Partially update a node using a strategic merge patch, specifying the patch as
kubectl patch node k8s-node-1 -p '{"spec":{"unschedulable":true}}'

# Partially update a node using a strategic merge patch, specifying the patch as
kubectl patch node k8s-node-1 -p '$spec:\n unschedulable: true'

# Partially update a node identified by the type and name specified in "node.json"
kubectl patch -f node.json -p '{"spec":{"unschedulable":true}}'

# Update a container's image; spec.containers[*].name is required because it's a
kubectl patch pod valid-pod -p '{"spec":{"containers":[{"name":"kubernetes-serve-

# Update a container's image using a JSON patch with positional arrays
kubectl patch pod valid-pod --type='json' -p='[{"op": "replace", "path": "/spec/containers/0/image", "value": "kubernetes-serve-

# Update a deployment's replicas through the 'scale' subresource using a merge patch
kubectl patch deployment nginx-deployment --subresource='scale' --type='merge' -p '{"spec":{"replicas": 3}}'
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goolang and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-patch"

Name of the manager used to track field ownership.

`-f, --filename strings`

Filename, directory, or URL to files identifying the resource to update

`-h, --help`

help for patch

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with -f or -R.

`--local`

If true, patch will operate on the content of the file, not the server-side resource.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-p, --patch string`

The patch to be applied to the resource JSON file.

`--patch-file string`

A file containing a patch to be applied to the resource.

`-R, --recursive`

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--subresource string

If specified, patch will operate on the subresource of the requested object.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

--type string Default: "strategic"

The type of patch being provided; one of [json merge strategic]

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.33 - kubectl plugin

Provides utilities for interacting with plugins

Synopsis

Provides utilities for interacting with plugins.

Plugins provide extended functionality that is not part of the major command-line distribution. Please refer to the documentation and examples for more information about how write your own plugins.

The easiest way to discover and install plugins is via the kubernetes sub-project krew: [krew.sigs.k8s.io]. To install krew, visit <https://krew.sigs.k8s.io/docs/user-guide/setup/install>

```
kubectl plugin [flags]
```

Examples

```
# List all available plugins
kubectl plugin list

# List only binary names of available plugins without paths
kubectl plugin list --name-only
```

Options

```
-h, --help
```

```
help for plugin
```

Parent Options Inherited

```
--as string
```


Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl plugin list](#) - List all visible plugin executables on a user's PATH

3.33.1 - kubectl plugin list

List all visible plugin executables on a user's PATH

Synopsis

List all available plugin files on a user's PATH. To see plugins binary names without the full path use --name-only flag.

Available plugin files are those that are: - executable - anywhere on the user's PATH - begin with "kubectl-"

```
kubectl plugin list [flags]
```

Examples

```
# List all available plugins
kubectl plugin list

# List only binary names of available plugins without paths
kubectl plugin list --name-only
```

Options

-h, --help

help for list

--name-only

If true, display only the binary name of each plugin, rather than its full path

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl plugin](#) - Provides utilities for interacting with plugins

3.34 - kubectl port-forward

Forward one or more local ports to a pod

Synopsis

Forward one or more local ports to a pod.

Use resource type/name such as deployment/mydeployment to select a pod. Resource type defaults to 'pod' if omitted.

If there are multiple pods matching the criteria, a pod will be selected automatically. The forwarding session ends when the selected pod terminates, and a rerun of the command is needed to resume forwarding.

```
kubectl port-forward TYPE/NAME [options] [LOCAL_PORT:]REMOTE_PORT [...[LOCAL_PORT_M
```

Examples

```
# Listen on ports 5000 and 6000 locally, forwarding data to/from ports 5000 and 6000 in the pod
kubectl port-forward pod/mypod 5000 6000
```

```
# Listen on ports 5000 and 6000 locally, forwarding data to/from ports 5000 and 6000 in the pod
kubectl port-forward deployment/mydeployment 5000 6000
```

```
# Listen on port 8443 locally, forwarding to the targetPort of the service's port
kubectl port-forward service/myservice 8443:https
```

```
# Listen on port 8888 locally, forwarding to 5000 in the pod
kubectl port-forward pod/mypod 8888:5000
```

```
# Listen on port 8888 on all addresses, forwarding to 5000 in the pod
kubectl port-forward --address 0.0.0.0 pod/mypod 8888:5000
```

```
# Listen on port 8888 on localhost and selected IP, forwarding to 5000 in the pod
kubectl port-forward --address localhost,10.19.21.23 pod/mypod 8888:5000
```

```
# Listen on a random port locally, forwarding to 5000 in the pod
kubectl port-forward pod/mypod :5000
```

Options

`--address strings` Default: "localhost"

Addresses to listen on (comma separated). Only accepts IP addresses or localhost as a value. When localhost is supplied, kubectl will try to bind on both 127.0.0.1 and ::1 and will fail if neither of these addresses are available to bind.

`-h, --help`

help for port-forward

`--pod-running-timeout duration` Default: 1m0s

The length of time (like 5s, 2m, or 3h, higher than zero) to wait until at least one pod is running

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.35 - kubectl proxy

Run a proxy to the Kubernetes API server

Synopsis

Creates a proxy server or application-level gateway between localhost and the Kubernetes API server. It also allows serving static content over specified HTTP path. All incoming data enters through one port and gets forwarded to the remote Kubernetes API server port, except for the path matching the static content path.

```
kubectl proxy [--port=PORT] [--www=static-dir] [--www-prefix=prefix] [--api-prefix=prefix]
```

Examples

```
# To proxy all of the Kubernetes API and nothing else
```

```
kubectl proxy --api-prefix=/
```

```
# To proxy only part of the Kubernetes API and also some static files
```

```
# You can get pods info with 'curl localhost:8001/api/v1/pods'
```

```
kubectl proxy --www=/my/files --www-prefix=/static/ --api-prefix=/api/
```

```
# To proxy the entire Kubernetes API at a different root
```

```
# You can get pods info with 'curl localhost:8001/custom/api/v1/pods'
```

```
kubectl proxy --api-prefix=/custom/
```

```
# Run a proxy to the Kubernetes API server on port 8011, serving static content from /www
```

```
kubectl proxy --port=8011 --www=./local/www/
```

```
# Run a proxy to the Kubernetes API server on an arbitrary local port
```

```
# The chosen port for the server will be output to stdout
```

```
kubectl proxy --port=0
```

```
# Run a proxy to the Kubernetes API server, changing the API prefix to k8s-api
```

```
# This makes e.g. the pods API available at localhost:8001/k8s-api/v1/pods/
```

```
kubectl proxy --api-prefix=/k8s-api
```


Options

`--accept-hosts string` Default: "`^localhost$,^127\.\0\.\0\1$,^\[:1\]$\`"

Regular expression for hosts that the proxy should accept.

`--accept-paths string` Default: "`^\.*\`"

Regular expression for paths that the proxy should accept.

`--address string` Default: "`127.0.0.1\`"

The IP address on which to serve on.

`--api-prefix string` Default: "`/\`"

Prefix to serve the proxied API under.

`--append-server-path`

If true, enables automatic path appending of the kube context server path to each request.

`--disable-filter`

If true, disable request filtering in the proxy. This is dangerous, and can leave you vulnerable to XSRF attacks, when used with an accessible port.

`-h, --help`

help for proxy

`--keepalive duration`

keepalive specifies the keep-alive period for an active network connection. Set to 0 to disable keepalive.

`-p, --port int` Default: 8001

The port on which to run the proxy. Set to 0 to pick a random port.

`--reject-methods string` Default: "`^\$\`"

Regular expression for HTTP methods that the proxy should reject (example --reject-methods='POST,PUT,PATCH').

--reject-paths string Default: "^/api/.*/pods/.*/exec,
^/api/.*/pods/.*/attach"

Regular expression for paths that the proxy should reject. Paths specified here will be rejected even accepted by --accept-paths.

-u, --unix-socket string

Unix socket on which to run the proxy.

-w, --www string

Also serve static files from the given directory under the specified prefix.

-P, --www-prefix string Default: "/static/"

Prefix to serve static files under, if static file directory is specified.

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.36 - kubectl replace

Replace a resource by file name or stdin

Synopsis

Replace a resource by file name or stdin.

JSON and YAML formats are accepted. If replacing an existing resource, the complete resource spec must be provided. This can be obtained by

```
$ kubectl get TYPE NAME -o yaml
```

```
kubectl replace -f FILENAME
```

Examples

```
# Replace a pod using the data in pod.json
kubectl replace -f ./pod.json

# Replace a pod based on the JSON passed into stdin
cat pod.json | kubectl replace -f -

# Update a single-container pod's image version (tag) to v4
kubectl get pod mypod -o yaml | sed 's/\(image: myimage\):.*$/\1:v4/' | kubectl r

# Force replace, delete and then re-create the resource
kubectl replace --force -f ./pod.json
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--cascade string[="background"]` Default: "background"

Must be "background", "orphan", or "foreground". Selects the deletion cascading strategy for the dependents (e.g. Pods created by a ReplicationController). Defaults to background.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-replace"

Name of the manager used to track field ownership.

`-f, --filename strings`

The files, directories or URLs that contain the configurations to replace.

`--force`

If true, immediately remove resources from API and bypass graceful deletion. Note that immediate deletion of some resources may result in inconsistency or data loss and requires confirmation.

`--grace-period int` Default: -1

Period of time in seconds given to the resource to terminate gracefully. Ignored if negative. Set to 1 for immediate shutdown. Can only be set to 0 when --force is true (force deletion).

`-h, --help`

help for replace

`-k, --kustomize string`

Process a kustomization directory. This flag can't be used together with -f or -R.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--raw string`

Raw URI to PUT to the server. Uses the transport specified by the kubeconfig file.

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform `kubectl apply` on this object in the future.

`--show-managed-fields`

If true, keep the `managedFields` when printing objects in JSON or YAML format.

`--subresource string`

If specified, `replace` will operate on the subresource of the requested object.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--timeout duration`

The length of time to wait before giving up on a delete, zero means determine a timeout from the size of the object

`--validate string[="strict"]` Default: "strict"

Must be one of: `strict` (or `true`), `warn`, `ignore` (or `false`). `"true"` or `"strict"` will use a schema to validate the input and fail the request if invalid. It will perform server side validation if `ServerSideFieldValidation` is enabled on the api-server, but will fall back to less reliable client-side validation if not. `"warn"` will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as `"ignore"` otherwise. `"false"` or `"ignore"` will not perform any schema validation, silently dropping any unknown or duplicate fields.

`--wait`

If true, wait for resources to be gone before returning. This waits for finalizers.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectrl](#) - kubectrl controls the Kubernetes cluster manager

3.37 - kubectl rollout

Manage the rollout of a resource

Synopsis

Manage the rollout of one or many resources.

Valid resource types include:

- deployments
- daemonsets
- statefulsets

```
kubectl rollout SUBCOMMAND
```

Examples

```
# Rollback to the previous deployment
kubectl rollout undo deployment/abc

# Check the rollout status of a daemonset
kubectl rollout status daemonset/foo

# Restart a deployment
kubectl rollout restart deployment/abc

# Restart deployments with the 'app=nginx' label
kubectl rollout restart deployment --selector=app=nginx
```

Options

```
-h, --help
```

```
help for rollout
```

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl rollout history](#) - View rollout history
- [kubectl rollout pause](#) - Mark the provided resource as paused
- [kubectl rollout restart](#) - Restart a resource
- [kubectl rollout resume](#) - Resume a paused resource
- [kubectl rollout status](#) - Show the status of the rollout
- [kubectl rollout undo](#) - Undo a previous rollout

3.37.1 - kubectl rollout history

View rollout history

Synopsis

View previous rollout revisions and configurations.

```
kubectl rollout history (TYPE NAME | TYPE/NAME) [flags]
```

Examples

```
# View the rollout history of a deployment
kubectl rollout history deployment/abc

# View the details of daemonset revision 3
kubectl rollout history daemonset/abc --revision=3
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to golang and jsonpath output formats.

-f, --filename strings

Filename, directory, or URL to files identifying the resource to get from a server.

-h, --help

help for history

-k, --kustomize string

Process the kustomization directory. This flag can't be used together with -f or -R.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--revision int`

See the details, including podTemplate of the revision specified

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl rollout](#) - Manage the rollout of a resource

3.37.2 - kubectl rollout pause

Mark the provided resource as paused

Synopsis

Mark the provided resource as paused.

Paused resources will not be reconciled by a controller. Use "kubectl rollout resume" to resume a paused resource. Currently only deployments support being paused.

```
kubectl rollout pause RESOURCE
```

Examples

```
# Mark the nginx deployment as paused
# Any current state of the deployment will continue its function; new updates
# to the deployment will not have an effect as long as the deployment is paused
kubectl rollout pause deployment/nginx
```



Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--field-manager` string Default: "kubectl-rollout"

Name of the manager used to track field ownership.

`-f, --filename` strings

Filename, directory, or URL to files identifying the resource to get from a server.

`-h, --help`

help for pause

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl rollout](#) - Manage the rollout of a resource

3.37.3 - kubectl rollout restart

Restart a resource

Synopsis

Restart a resource.

```
Resource rollout will be restarted.
```

```
kubectl rollout restart RESOURCE
```

Examples

```
# Restart all deployments in the test-namespace namespace
kubectl rollout restart deployment -n test-namespace

# Restart a deployment
kubectl rollout restart deployment/nginx

# Restart a daemon set
kubectl rollout restart daemonset/abc

# Restart deployments with the app=nginx label
kubectl rollout restart deployment --selector=app=nginx
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--field-manager` string Default: "kubectl-rollout"

Name of the manager used to track field ownership.

`-f, --filename strings`

Filename, directory, or URL to files identifying the resource to get from a server.

`-h, --help`

help for restart

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl rollout](#) - Manage the rollout of a resource

3.37.4 - kubectl rollout resume

Resume a paused resource

Synopsis

Resume a paused resource.

Paused resources will not be reconciled by a controller. By resuming a resource, we allow it to be reconciled again. Currently only deployments support being resumed.

```
kubectl rollout resume RESOURCE
```

Examples

```
# Resume an already paused deployment
kubectl rollout resume deployment/nginx
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--field-manager string Default: "kubectl-rollout"

Name of the manager used to track field ownership.

-f, --filename strings

Filename, directory, or URL to files identifying the resource to get from a server.

-h, --help

help for resume

-k, --kustomize string

Process the kustomization directory. This flag can't be used together with -f or -R.

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

-R, --recursive

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

-l, --selector string

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl rollout](#) - Manage the rollout of a resource

3.37.5 - kubectl rollout status

Show the status of the rollout

Synopsis

Show the status of the rollout.

By default 'rollout status' will watch the status of the latest rollout until it's done. If you don't want to wait for the rollout to finish then you can use `--watch=false`. Note that if a new rollout starts in-between, then 'rollout status' will continue watching the latest revision. If you want to pin to a specific revision and abort if it is rolled over by another revision, use `--revision=N` where N is the revision you need to watch for.

```
kubectl rollout status (TYPE NAME | TYPE/NAME) [flags]
```

Examples

```
# Watch the rollout status of a deployment
kubectl rollout status deployment/nginx
```

Options

`-f, --filename strings`

Filename, directory, or URL to files identifying the resource to get from a server.

`-h, --help`

help for status

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-R, --recursive`

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

--revision int

Pin to a specific revision for showing its status. Defaults to 0 (last revision).

-l, --selector string

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

--timeout duration

The length of time to wait before ending watch, zero means never. Any other values should contain a corresponding time unit (e.g. 1s, 2m, 3h).

-w, --watch Default: true

Watch the status of the rollout until it's done.

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl rollout](#) - Manage the rollout of a resource

3.37.6 - kubectl rollout undo

Undo a previous rollout

Synopsis

Roll back to a previous rollout.

```
kubectl rollout undo (TYPE NAME | TYPE/NAME) [flags]
```

Examples

```
# Roll back to the previous deployment
kubectl rollout undo deployment/abc

# Roll back to daemonset revision 3
kubectl rollout undo daemonset/abc --to-revision=3

# Roll back to the previous deployment with dry-run
kubectl rollout undo --dry-run=server deployment/abc
```

Options

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string["unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

-f, --filename strings

Filename, directory, or URL to files identifying the resource to get from a server.

`-h, --help`

help for undo

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--to-revision int`

The revision to rollback to. Default to 0 (last revision).

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl rollout](#) - Manage the rollout of a resource

3.38 - kubectl run

Run a particular image on the cluster

Synopsis

Create and run a particular image in a pod.

```
kubectl run NAME --image=image [--env="key=value"] [--port=port] [--dry-run=server]
```

Examples

```
# Start a nginx pod
kubectl run nginx --image=nginx

# Start a hazelcast pod and let the container expose port 5701
kubectl run hazelcast --image=hazelcast/hazelcast --port=5701

# Start a hazelcast pod and set environment variables "DNS_DOMAIN=cluster" and "env=prod"
kubectl run hazelcast --image=hazelcast/hazelcast --env="DNS_DOMAIN=cluster" --env="env=prod"

# Start a hazelcast pod and set labels "app=hazelcast" and "env=prod" in the container
kubectl run hazelcast --image=hazelcast/hazelcast --labels="app=hazelcast,env=prod"

# Dry run; print the corresponding API objects without creating them
kubectl run nginx --image=nginx --dry-run=client

# Start a nginx pod, but overload the spec with a partial set of values parsed from a file
kubectl run nginx --image=nginx --overrides='{ "apiVersion": "v1", "spec": { ...

# Start a busybox pod and keep it in the foreground, don't restart it if it exits
kubectl run -i -t busybox --image=busybox --restart=Never

# Start the nginx pod using the default command, but use custom arguments (arg1, arg2, ..., argN)
kubectl run nginx --image=nginx -- <arg1> <arg2> ... <argN>

# Start the nginx pod using a different command and custom arguments
kubectl run nginx --image=nginx --command -- <cmd> <arg1> ... <argN>
```

Options

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to go lang and jsonpath output formats.

`--annotations strings`

Annotations to apply to the pod.

`--attach`

If true, wait for the Pod to start running, and then attach to the Pod as if 'kubectl attach ...' were called. Default false, unless '-i/--stdin' is set, in which case the default is true. With '--restart=Never' the exit code of the container process is returned.

`--cascade string[="background"]` Default: "background"

Must be "background", "orphan", or "foreground". Selects the deletion cascading strategy for the dependents (e.g. Pods created by a ReplicationController). Defaults to background.

`--command`

If true and extra arguments are present, use them as the 'command' field in the container, rather than the 'args' field which is the default.

`--detach-keys string` Default: "ctrl-p,ctrl-q"

Override the key sequence for detaching a container.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--env strings`

Environment variables to set in the container.

`--expose --port`

If true, create a ClusterIP service associated with the pod. Requires --port.

--field-manager string Default: "kubectl-run"

Name of the manager used to track field ownership.

--force

If true, immediately remove resources from API and bypass graceful deletion. Note that immediate deletion of some resources may result in inconsistency or data loss and requires confirmation.

--grace-period int Default: -1

Period of time in seconds given to the resource to terminate gracefully. Ignored if negative. Set to 1 for immediate shutdown. Can only be set to 0 when --force is true (force deletion).

-h, --help

help for run

--image string

The image for the container to run.

--image-pull-policy string

The image pull policy for the container. If left empty, this value will not be specified by the client and defaulted by the server.

-k, --kustomize string

Process a kustomization directory. This flag can't be used together with -f or -R.

-l, --labels string

Comma separated labels to apply to the pod. Will override previous values.

--leave-stdin-open

If the pod is started in interactive mode or with stdin, leave stdin open after the first attach completes. By default, stdin will be closed after the first attach completes.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--override-type string` Default: "merge"

The method used to override the generated object: json, merge, or strategic.

`--overrides string`

An inline JSON override for the generated object. If this is non-empty, it is used to override the generated object. Requires that the object supply a valid apiVersion field.

`--pod-running-timeout duration` Default: 1m0s

The length of time (like 5s, 2m, or 3h, higher than zero) to wait until at least one pod is running

`--port string`

The port that this container exposes.

`--privileged`

If true, run the container in privileged mode.

`-q, --quiet`

If true, suppress prompt messages.

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--restart string` Default: "Always"

The restart policy for this Pod. Legal values [Always, OnFailure, Never].

`--rm`

If true, delete the pod after it exits. Only valid when attaching to the container, e.g. with '--attach' or with '-i/--stdin'.

`--save-config`

If true, the configuration of current object will be saved in its annotation. Otherwise, the annotation will be unchanged. This flag is useful when you want to perform kubectl apply on this object in the future.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`-i, --stdin`

Keep stdin open on the container in the pod, even if nothing is attached.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--timeout duration`

The length of time to wait before giving up on a delete, zero means determine a timeout from the size of the object

`-t, --tty`

Allocate a TTY for the container in the pod.

`--wait`

If true, wait for resources to be gone before returning. This waits for finalizers.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.39 - kubectl scale

Set a new size for a deployment, replica set, or replication controller

Synopsis

Set a new size for a deployment, replica set, replication controller, or stateful set.

Scale also allows users to specify one or more preconditions for the scale action.

If `--current-replicas` or `--resource-version` is specified, it is validated before the scale is attempted, and it is guaranteed that the precondition holds true when the scale is sent to the server.

```
kubectl scale [--resource-version=version] [--current-replicas=count] --replicas=COUNT
```

Examples

```
# Scale a replica set named 'foo' to 3
kubectl scale --replicas=3 rs/foo

# Scale a resource identified by type and name specified in "foo.yaml" to 3
kubectl scale --replicas=3 -f foo.yaml

# If the deployment named mysql's current size is 2, scale mysql to 3
kubectl scale --current-replicas=2 --replicas=3 deployment/mysql

# Scale multiple replication controllers
kubectl scale --replicas=5 rc/example1 rc/example2 rc/example3

# Scale stateful set named 'web' to 3
kubectl scale --replicas=3 statefulset/web
```

Options

`--all`

Select all resources in the namespace of the specified resource types

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--current-replicas` int Default: -1

Precondition for current size. Requires that the current size of the resource match this value in order to scale. -1 (default) for no condition.

`--dry-run` string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`-f, --filename` strings

Filename, directory, or URL to files identifying the resource to set a new size

`-h, --help`

help for scale

`-k, --kustomize` string

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`-o, --output` string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--replicas` int

The new desired number of replicas. Required.

`--resource-version` string

Precondition for resource version. Requires that the current resource version match this value in order to scale.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--timeout duration`

The length of time to wait before giving up on a scale operation, zero means don't wait. Any other values should contain a corresponding time unit (e.g. 1s, 2m, 3h).

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

--match-server-version

Require server version to match client version

-n, --namespace string

If present, the namespace scope for this CLI request

--password string

Password for basic authentication to the API server

--profile string Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.40 - kubectl set

Set specific features on objects

Synopsis

Configure application resources.

These commands help you make changes to existing application resources.

```
kubectl set SUBCOMMAND
```

Options

`-h, --help`

help for set

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

--storage-driver-user string Default: "root"

database username

--tls-server-name string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

--token string

Bearer token for authentication to the API server

--user string

The name of the kubeconfig user to use

--username string

Username for basic authentication to the API server

--version version[=true]

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

--warnings-as-errors

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl set env](#) - Update environment variables on a pod template
- [kubectl set image](#) - Update the image of a pod template
- [kubectl set resources](#) - Update resource requests/limits on objects with pod templates
- [kubectl set selector](#) - Set the selector on a resource
- [kubectl set serviceaccount](#) - Update the service account of a resource
- [kubectl set subject](#) - Update the user, group, or service account in a role binding or cluster role binding

3.40.1 - kubectl set env

Update environment variables on a pod template

Synopsis

Update environment variables on a pod template.

List environment variable definitions in one or more pods, pod templates. Add, update, or remove container environment variable definitions in one or more pod templates (within replication controllers or deployment configurations). View or modify the environment variable definitions on all containers in the specified pods or pod templates, or just those that match a wildcard.

If "--env -" is passed, environment variables can be read from STDIN using the standard env syntax.

Possible resources include (case insensitive):

pod (po), replicationcontroller (rc), deployment (deploy), daemonset (ds), statefulset (st)

```
kubectl set env RESOURCE/NAME KEY_1=VAL_1 ... KEY_N=VAL_N
```

Examples

```
# Update deployment 'registry' with a new environment variable
kubectl set env deployment/registry STORAGE_DIR=/local

# List the environment variables defined on a deployments 'sample-build'
kubectl set env deployment/sample-build --list

# List the environment variables defined on all pods
kubectl set env pods --all --list

# Output modified deployment in YAML, and does not alter the object on the server
kubectl set env deployment/sample-build STORAGE_DIR=/data -o yaml

# Update all containers in all replication controllers in the project to have ENV
kubectl set env rc --all ENV=prod
```

```
# Import environment from a secret
kubectl set env --from=secret/mysecret deployment/myapp

# Import environment from a config map with a prefix
kubectl set env --from=configmap/myconfigmap --prefix=MYSQL_ deployment/myapp

# Import specific keys from a config map
kubectl set env --keys=my-example-key --from=configmap/myconfigmap deployment/myapp

# Remove the environment variable ENV from container 'c1' in all deployment configs
kubectl set env deployments --all --containers="c1" ENV-

# Remove the environment variable ENV from a deployment definition on disk and
# update the deployment config on the server
kubectl set env -f deploy.json ENV-

# Set some of the local shell environment into a deployment config on the server
env | grep RAILS_ | kubectl set env -e - deployment/registry
```

Options

--all

If true, select all resources in the namespace of the specified resource types

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

-c, --containers string Default: "*"

The names of containers in the selected pod templates to change - may use wildcards

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

-e, --env strings

Specify a key-value pair for an environment variable to set into each container.

`--field-manager string` Default: "kubectl-set"

Name of the manager used to track field ownership.

`-f, --filename strings`

Filename, directory, or URL to files the resource to update the env

`--from string`

The name of a resource from which to inject environment variables

`-h, --help`

help for env

`--keys strings`

Comma-separated list of keys to import from specified resource

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`--list`

If true, display the environment and any changes in the standard format. this flag will removed when we have `kubectl view env`.

`--local`

If true, set env will NOT contact api-server but run locally.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--overwrite` Default: true

If true, allow environment to be overwritten, otherwise reject updates that overwrite existing environment.

`--prefix string`

Prefix to append to variable names

`-R, --recursive`

Process the directory used in `-f`, `--filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--resolve`

If true, show secret or configmap references when listing variables

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl set](#) - Set specific features on objects

3.40.2 - kubectl set image

Update the image of a pod template

Synopsis

Update existing container image(s) of resources.

Possible resources include (case insensitive):

```
pod (po), replicationcontroller (rc), deployment (deploy), daemonset (ds), statefulset (st)
```

```
kubectl set image (-f FILENAME | TYPE NAME) CONTAINER_NAME_1=CONTAINER_IMAGE_1 ...
```

Examples

```
# Set a deployment's nginx container image to 'nginx:1.9.1', and its busybox container image to 'busybox:1.24.0'
kubectl set image deployment/nginx busybox=busybox:1.24.0 nginx=nginx:1.9.1
```

```
# Update all deployments' and rc's nginx container's image to 'nginx:1.9.1'
kubectl set image deployments,rc nginx=nginx:1.9.1 --all
```

```
# Update image of all containers of daemonset abc to 'nginx:1.9.1'
kubectl set image daemonset abc *=nginx:1.9.1
```

```
# Print result (in yaml format) of updating nginx container image from local file
kubectl set image -f path/to/file.yaml nginx=nginx:1.9.1 --local -o yaml
```

Options

--all

Select all resources, in the namespace of the specified resource types

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-set"

Name of the manager used to track field ownership.

`-f, --filename strings`

Filename, directory, or URL to files identifying the resource to get from a server.

`-h, --help`

help for image

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`--local`

If true, set image will NOT contact api-server but run locally.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl set](#) - Set specific features on objects

3.40.3 - kubectl set resources

Update resource requests/limits on objects with pod templates

Synopsis

Specify compute resource requirements (CPU, memory) for any resource that defines a pod template. If a pod is successfully scheduled, it is guaranteed the amount of resource requested, but may burst up to its specified limits.

For each compute resource, if a limit is specified and a request is omitted, the request will default to the limit.

Possible resources include (case insensitive): Use "kubectl api-resources" for a complete list of supported resources..

```
kubectl set resources (-f FILENAME | TYPE NAME) ([--limits=LIMITS & --requests=REQ
```

Examples

```
# Set a deployments nginx container cpu limits to "200m" and memory to "512Mi"
kubectl set resources deployment nginx -c=nginx --limits=cpu=200m,memory=512Mi

# Set the resource request and limits for all containers in nginx
kubectl set resources deployment nginx --limits=cpu=200m,memory=512Mi --requests=cpu=100m,memory=256Mi

# Remove the resource requests for resources on containers in nginx
kubectl set resources deployment nginx --limits=cpu=0,memory=0 --requests=cpu=0,memory=0

# Print the result (in yaml format) of updating nginx container limits from a local file
kubectl set resources -f path/to/file.yaml --limits=cpu=200m,memory=512Mi --local
```

Options

--all

Select all resources, in the namespace of the specified resource types

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`-c, --containers string` Default: "*"

The names of containers in the selected pod templates to change, all containers are selected by default - may use wildcards

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-set"

Name of the manager used to track field ownership.

`-f, --filename strings`

Filename, directory, or URL to files identifying the resource to get from a server.

`-h, --help`

help for resources

`-k, --kustomize string`

Process the kustomization directory. This flag can't be used together with -f or -R.

`--limits string`

The resource requirement requests for this container. For example, 'cpu=100m,memory=256Mi'. Note that server side components may assign requests depending on the server configuration, such as limit ranges.

`--local`

If true, set resources will NOT contact api-server but run locally.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--requests string`

The resource requirement requests for this container. For example, 'cpu=100m,memory=256Mi'. Note that server side components may assign requests depending on the server configuration, such as limit ranges.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template, -o=go-template-file`. The template format is go lang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl set](#) - Set specific features on objects

3.40.4 - kubectl set selector

Set the selector on a resource

Synopsis

Set the selector on a resource. Note that the new selector will overwrite the old selector if the resource had one prior to the invocation of 'set selector'.

A selector must begin with a letter or number, and may contain letters, numbers, hyphens, dots, and underscores, up to 63 characters. If --resource-version is specified, then updates will use this resource version, otherwise the existing resource-version will be used. Note: currently selectors can only be set on Service objects.

```
kubectl set selector (-f FILENAME | TYPE NAME) EXPRESSIONS [--resource-version=version]
```

Examples

```
# Set the labels and selector before creating a deployment/service pair
kubectl create service clusterip my-svc --clusterip="None" -o yaml --dry-run=client
kubectl create deployment my-dep --image=nginx -o yaml --dry-run=client | kubectl apply -f -
```

Options

--all

Select all resources in the namespace of the specified resource types

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-set"

Name of the manager used to track field ownership.

`-f, --filename strings`

identifying the resource.

`-h, --help`

help for selector

`--local`

If true, annotation will NOT contact api-server but run locally.

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive` Default: true

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--resource-version string`

If non-empty, the selectors update will only succeed if this is the current resource-version for the object. Only valid when specifying a single resource.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [http://golang.org/pkg/text/template/#pkg-overview].

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

--cache-dir string Default: "\$HOME/.kube/cache"

Default cache directory

--certificate-authority string

Path to a cert file for the certificate authority

--client-certificate string

Path to a client certificate file for TLS

--client-key string

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

--profile-output string Default: "profile.pprof"

Name of the file to write the profile to

--proxy-url string

Proxy URL to use for requests to the API server

--request-timeout string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

-s, --server string

The address and port of the Kubernetes API server

--storage-driver-buffer-duration duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

--storage-driver-db string Default: "cadvisor"

database name

--storage-driver-host string Default: "localhost:8086"

database host:port

--storage-driver-password string Default: "root"

database password

--storage-driver-secure

use secure connection with database

--storage-driver-table string Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl set](#) - Set specific features on objects

3.40.5 - kubectl set serviceaccount

Update the service account of a resource

Synopsis

Update the service account of pod template resources.

Possible resources (case insensitive) can be:

replicationcontroller (rc), deployment (deploy), daemonset (ds), job, replicaset (rs), statefulset

```
kubectl set serviceaccount (-f FILENAME | TYPE NAME) SERVICE_ACCOUNT
```

Examples

```
# Set deployment nginx-deployment's service account to serviceaccount1
kubectl set serviceaccount deployment nginx-deployment serviceaccount1

# Print the result (in YAML format) of updated nginx deployment with the service
kubectl set sa -f nginx-deployment.yaml serviceaccount1 --local --dry-run=client
```

Options

--all

Select all resources, in the namespace of the specified resource types

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string["unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request

without persisting the resource.

`--field-manager` string Default: "kubectl-set"

Name of the manager used to track field ownership.

`-f, --filename` strings

Filename, directory, or URL to files identifying the resource to get from a server.

`-h, --help`

help for serviceaccount

`-k, --kustomize` string

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`--local`

If true, set serviceaccount will NOT contact api-server but run locally.

`-o, --output` string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template` string

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl set](#) - Set specific features on objects

3.40.6 - kubectl set subject

Update the user, group, or service account in a role binding or cluster role binding

Synopsis

Update the user, group, or service account in a role binding or cluster role binding.

```
kubectl set subject (-f FILENAME | TYPE NAME) [--user=username] [--group=groupname]
```

Examples

```
# Update a cluster role binding for serviceaccount1
kubectl set subject clusterrolebinding admin --serviceaccount=namespace:serviceaccount1

# Update a role binding for user1, user2, and group1
kubectl set subject rolebinding admin --user=user1 --user=user2 --group=group1

# Print the result (in YAML format) of updating rolebinding subjects from a local file
kubectl create rolebinding admin --role=admin --user=admin -o yaml --dry-run=client
```

Options

--all

Select all resources, in the namespace of the specified resource types

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--dry-run string["unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager` string Default: "kubectl-set"

Name of the manager used to track field ownership.

`-f, --filename` strings

Filename, directory, or URL to files the resource to update the subjects

`--group` strings

Groups to bind to the role

`-h, --help`

help for subject

`-k, --kustomize` string

Process the kustomization directory. This flag can't be used together with `-f` or `-R`.

`--local`

If true, set subject will NOT contact api-server but run locally.

`-o, --output` string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`-R, --recursive`

Process the directory used in `-f, --filename` recursively. Useful when you want to manage related manifests organized within the same directory.

`-l, --selector` string

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--serviceaccount strings`

Service accounts to bind to the role

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

`--template string`

Template string or path to template file to use when `-o=go-template`, `-o=go-template-file`. The template format is golang templates [<http://golang.org/pkg/text/template/#pkg-overview>].

`--user strings`

Username to bind to the role

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cAdvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token` string

Bearer token for authentication to the API server

`--username` string

Username for basic authentication to the API server

`--version` version[=true]

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl set](#) - Set specific features on objects

3.41 - kubectl taint

Update the taints on one or more nodes

Synopsis

Update the taints on one or more nodes.

- A taint consists of a key, value, and effect. As an argument here, it is expressed as key=value:effect.
- The key must begin with a letter or number, and may contain letters, numbers, hyphens, dots, and underscores, up to 253 characters.
- Optionally, the key can begin with a DNS subdomain prefix and a single '/', like example.com/my-app.
- The value is optional. If given, it must begin with a letter or number, and may contain letters, numbers, hyphens, dots, and underscores, up to 63 characters.
- The effect must be NoSchedule, PreferNoSchedule or NoExecute.
- Currently taint can only apply to node.

```
kubectl taint NODE NAME KEY_1=VAL_1:TAINT_EFFECT_1 ... KEY_N=VAL_N:TAINT_EFFECT_N
```

Examples

```
# Update node 'foo' with a taint with key 'dedicated' and value 'special-user' and effect 'NoSchedule'
# If a taint with that key and effect already exists, its value is replaced as specified
kubectl taint nodes foo dedicated=special-user:NoSchedule

# Remove from node 'foo' the taint with key 'dedicated' and effect 'NoSchedule'
kubectl taint nodes foo dedicated:NoSchedule-

# Remove from node 'foo' all the taints with key 'dedicated'
kubectl taint nodes foo dedicated-

# Add a taint with key 'dedicated' on nodes having label myLabel=X
kubectl taint node -l myLabel=X dedicated=foo:PreferNoSchedule

# Add to node 'foo' a taint with key 'bar' and no value
kubectl taint nodes foo bar:NoSchedule
```

Options

`--all`

Select all nodes in the cluster

`--allow-missing-template-keys` Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

`--dry-run string[="unchanged"]` Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

`--field-manager string` Default: "kubectl-taint"

Name of the manager used to track field ownership.

`-h, --help`

help for taint

`-o, --output string`

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

`--overwrite`

If true, allow taints to be overwritten, otherwise reject taint updates that overwrite existing taints.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

`--show-managed-fields`

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is golang templates [http://golang.org/pkg/text/template/#pkg-overview].

--validate string[="strict"] Default: "strict"

Must be one of: strict (or true), warn, ignore (or false). "true" or "strict" will use a schema to validate the input and fail the request if invalid. It will perform server side validation if ServerSideFieldValidation is enabled on the api-server, but will fall back to less reliable client-side validation if not. "warn" will warn about unknown or duplicate fields without blocking the request if server-side field validation is enabled on the API server, and behave as "ignore" otherwise. "false" or "ignore" will not perform any schema validation, silently dropping any unknown or duplicate fields.

Parent Options Inherited

--as string

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

--as-group strings

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

--as-uid string

UID to impersonate for the operation.

--as-user-extra strings

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

--cache-dir string Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager

3.42 - kubectl top

Display resource (CPU/memory) usage

Synopsis

Display resource (CPU/memory) usage.

This command provides a view of recent resource consumption for nodes and pods. It fetches metrics from the Metrics Server, which aggregates this data from the kubelet on each node. The Metrics Server must be installed and running in the cluster for this command to work.

The metrics shown are specifically optimized for Kubernetes autoscaling decisions, such as those made by the Horizontal Pod Autoscaler (HPA) and Vertical Pod Autoscaler (VPA). Because of this, the values may not match those from standard OS tools like 'top', as the metrics are designed to provide a stable signal for autoscalers rather than for pinpoint accuracy.

FAQ for Metrics Server: <https://github.com/kubernetes-sigs/metrics-server/blob/master/FAQ.md>

When to use this command:

- For on-the-fly spot-checks of resource usage (e.g. identify which pods are consuming the most resources at a glance, or get a quick sense of the load on your nodes)
- Understand current resource consumption patterns
- Validate the behavior of your HPA or VPA configurations by seeing the metrics they use for scaling decisions.

It is not intended to be a replacement for full-featured monitoring solutions. Its primary design goal is to provide a low-overhead signal for autoscalers, not to be a perfectly accurate monitoring tool. For high-accuracy reporting, historical analysis, dashboarding, or alerting, you should use a dedicated monitoring solution.

```
kubectl top [flags]
```

Options

```
-h, --help
```

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl](#) - kubectl controls the Kubernetes cluster manager
- [kubectl top node](#) - Display resource (CPU/memory) usage of nodes
- [kubectl top pod](#) - Display resource (CPU/memory) usage of pods

3.42.1 - kubectl top node

Display resource (CPU/memory) usage of nodes

Synopsis

Display resource (CPU/memory) usage of nodes.

The top-node command allows you to see the resource consumption of nodes.

```
kubectl top node [NAME | -l label]
```

Examples

```
# Show metrics for all nodes
kubectl top node

# Show metrics for a given node
kubectl top node NODE_NAME
```

Options

-h, --help

help for node

--no-headers

If present, print output without headers

-l, --selector string

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

--show-capacity

Print node resources based on Capacity instead of Allocatable(default) of the nodes.

`--show-swap`

Print node resources related to swap memory.

`--sort-by string`

If non-empty, sort nodes list using specified field. The field can be either 'cpu' or 'memory'.

`--use-protocol-buffers` Default: true

Enables using protocol-buffers to access Metrics API.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

`--version`, `--version=raw` prints version information and quits; `--version=vX.Y.Z...` sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl top](#) - Display resource (CPU/memory) usage

3.42.2 - kubectl top pod

Display resource (CPU/memory) usage of pods

Synopsis

Display resource (CPU/memory) usage of pods.

The 'top pod' command allows you to see the resource consumption of pods.

Due to the metrics pipeline delay, they may be unavailable for a few minutes since pod creation.

```
kubectl top pod [NAME | -l label]
```

Examples

```
# Show metrics for all pods in the default namespace
kubectl top pod

# Show metrics for all pods in the given namespace
kubectl top pod --namespace=NAMESPACE

# Show metrics for a given pod and its containers
kubectl top pod POD_NAME --containers

# Show metrics for the pods defined by label name=myLabel
kubectl top pod -l name=myLabel
```

Options

-A, --all-namespaces

If present, list the requested object(s) across all namespaces. Namespace in current context is ignored even if specified with --namespace.

--containers

If present, print usage of containers within a pod.

`--field-selector string`

Selector (field query) to filter on, supports '=', '==', and '!='.(e.g. `--field-selector key1=value1,key2=value2`). The server only supports a limited number of field queries per type.

`-h, --help`

help for pod

`--no-headers`

If present, print output without headers.

`-l, --selector string`

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. `-l key1=value1,key2=value2,key3 in (value3)`). Matching objects must satisfy all of the specified label constraints.

`--show-swap`

Print pod resources related to swap memory.

`--sort-by string`

If non-empty, sort pods list using specified field. The field can be either 'cpu' or 'memory'.

`--sum`

Print the sum of the resource usage

`--use-protocol-buffers` Default: true

Enables using protocol-buffers to access Metrics API.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubectl top](#) - Display resource (CPU/memory) usage

3.43 - kubectl uncordon

Mark node as schedulable

Synopsis

Mark node as schedulable.

```
kubectl uncordon NODE
```

Examples

```
# Mark node "foo" as schedulable
kubectl uncordon foo
```

Options

--dry-run string[="unchanged"] Default: "none"

Must be "none", "server", or "client". If client strategy, only print the object that would be sent, without sending it. If server strategy, submit server-side request without persisting the resource.

-h, --help

help for uncordon

-l, --selector string

Selector (label query) to filter on, supports '=', '==', '!=', 'in', 'notin'.(e.g. -l key1=value1,key2=value2,key3 in (value3)). Matching objects must satisfy all of the specified label constraints.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout` string Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server` string

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration` duration Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db` string Default: "cadvisor"

database name

`--storage-driver-host` string Default: "localhost:8086"

database host:port

`--storage-driver-password` string Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table` string Default: "stats"

table name

`--storage-driver-user` string Default: "root"

database username

`--tls-server-name` string

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.44 - kubectl version

Print the client and server version information

Synopsis

Print the client and server version information for the current context.

```
kubectl version [flags]
```

Examples

```
# Print the client and server versions for the current context
kubectl version
```

Options

`--client`

If true, shows client version only (no server required).

`-h, --help`

help for version

`-o, --output string`

One of 'yaml' or 'json'.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting KUBECTL_KUBERC=false feature gate or turning off the feature KUBERC=off.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

3.45 - kubectl wait

Wait for a specific condition on one or many resources

Synopsis

Wait for a specific condition on one or many resources.

The command takes multiple resources and waits until the specified condition is seen in the Status field of every given resource.

Alternatively, the command can wait for the given set of resources to be created or deleted by providing the "create" or "delete" keyword as the value to the --for flag.

A successful message will be printed to stdout indicating when the specified condition has been met. You can use -o option to change to output destination.

```
kubectl wait ([ -f FILENAME ] | resource.group/resource.name | resource.group [(-1 1)
```

Examples

```
# Wait for the pod "busybox1" to contain the status condition of type "Ready"
kubectl wait --for=condition=Ready pod/busybox1

# The default value of status condition is true; you can wait for other targets &
kubectl wait --for=condition=Ready=false pod/busybox1

# Wait for the pod "busybox1" to contain the status phase to be "Running"
kubectl wait --for=jsonpath='{.status.phase}'=Running pod/busybox1

# Wait for pod "busybox1" to be Ready
kubectl wait --for=jsonpath='{.status.conditions[?(@.type=="Ready")].status}'=True pod/busybox1

# Wait for the service "loadbalancer" to have ingress
kubectl wait --for=jsonpath='{.status.loadBalancer.ingress}' service/loadbalancer

# Wait for the secret "busybox1" to be created, with a timeout of 30s
kubectl create secret generic busybox1
kubectl wait --for=create secret/busybox1 --timeout=30s

# Wait for the pod "busybox1" to be deleted, with a timeout of 60s, after having
kubectl delete pod/busybox1
```

```
kubectl wait --for=delete pod/busybox1 --timeout=60s

# Wait for pod "busybox1" to be created AND reach the "Ready" status condition
kubectl wait --for=condition=Ready --for=create pod/busybox1

# Wait for pod "busybox1" to reach the "Ready" status OR for its containers to re
until kubectl wait pod/busybox1 --for=condition=Ready --timeout=1s 2>/dev/null |
kubectl wait pod/busybox1 --for=condition=ContainersReady=False --timeout=1s 2>/c
do echo "Checking conditions..."; sleep 1; done
```

Options

--all

Select all resources in the namespace of the specified resource types

-A, --all-namespaces

If present, list the requested object(s) across all namespaces. Namespace in current context is ignored even if specified with `--namespace`.

--allow-missing-template-keys Default: true

If true, ignore any errors in templates when a field or map key is missing in the template. Only applies to goyaml and jsonpath output formats.

--field-selector string

Selector (field query) to filter on, supports '=', '==', and '!='.(e.g. `--field-selector key1=value1,key2=value2`). The server only supports a limited number of field queries per type.

-f, --filename strings

identifying the resource.

--for strings

The condition to wait on: `[create | delete | condition=condition-name[=condition-value]] | jsonpath='{JSONPath expression}'=[JSONPath value]`. The default condition-value is true. Condition values are compared after Unicode simple case folding, which is a more general form of case-insensitivity. Multiple conditions are

supported and AND'ed to each other in a sequential order. If --for=create is passed, it is always waited first.

-h, --help

help for wait

--local

If true, annotation will NOT contact api-server but run locally.

-o, --output string

Output format. One of: (json, yaml, kyaml, name, go-template, go-template-file, template, templatefile, jsonpath, jsonpath-as-json, jsonpath-file).

-R, --recursive Default: true

Process the directory used in -f, --filename recursively. Useful when you want to manage related manifests organized within the same directory.

-l, --selector string

Selector (label query) to filter on, supports '=', '==', and '!='.(e.g. -l key1=value1,key2=value2)

--show-managed-fields

If true, keep the managedFields when printing objects in JSON or YAML format.

--template string

Template string or path to template file to use when -o=go-template, -o=go-template-file. The template format is go lang templates [http://golang.org/pkg/text/template/#pkg-overview].

--timeout duration Default: 30s

The length of time to wait before giving up. Zero means check once and don't wait, negative means wait for a week.

Parent Options Inherited

`--as string`

Username to impersonate for the operation. User could be a regular user or a service account in a namespace.

`--as-group strings`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--as-uid string`

UID to impersonate for the operation.

`--as-user-extra strings`

User extras to impersonate for the operation, this flag can be repeated to specify multiple values for the same key.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--disable-compression`

If true, opt-out of response compression for all requests to the server

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--kuberc string`

Path to the kuberc file to use for preferences. This can be disabled by exporting `KUBECTL_KUBERC=false` feature gate or turning off the feature `KUBERC=off`.

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex | trace)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--proxy-url string`

Proxy URL to use for requests to the API server

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--storage-driver-buffer-duration duration` Default: 1m0s

Writes in the storage driver will be buffered for this duration, and committed to the non memory backends as a single transaction

`--storage-driver-db string` Default: "cadvisor"

database name

`--storage-driver-host string` Default: "localhost:8086"

database host:port

`--storage-driver-password string` Default: "root"

database password

`--storage-driver-secure`

use secure connection with database

`--storage-driver-table string` Default: "stats"

table name

`--storage-driver-user string` Default: "root"

database username

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`--version version[=true]`

--version, --version=raw prints version information and quits; --version=vX.Y.Z... sets the reported version

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

See Also

- [kubect](#)l - kubectl controls the Kubernetes cluster manager

4 - kubectl Commands

[kubectl Command Reference](#)

5 - kubectl

Synopsis

Command line tool for communicating with a Kubernetes cluster's control plane, using the Kubernetes API.

Find more information in [Command line tool](#) (`kubectl`).

```
kubectl [flags]
```

Options

`--add-dir-header`

If true, adds the file directory to the header of the log messages

`--alsologtostderr`

log to standard error as well as files

`--as string`

Username to impersonate for the operation

`--as-group stringArray`

Group to impersonate for the operation, this flag can be repeated to specify multiple groups.

`--azure-container-registry-config string`

Path to the file containing Azure container registry configuration information.

`--cache-dir string` Default: "\$HOME/.kube/cache"

Default cache directory

`--certificate-authority string`

Path to a cert file for the certificate authority

`--client-certificate string`

Path to a client certificate file for TLS

`--client-key string`

Path to a client key file for TLS

`--cloud-provider-gce-l7lb-src-cidrs cidrs` Default: 130.211.0.0/22,35.191.0.0/16

CIDRs opened in GCE firewall for L7 LB traffic proxy & health checks

`--cloud-provider-gce-lb-src-cidrs cidrs` Default:
130.211.0.0/22,209.85.152.0/22,209.85.204.0/22,35.191.0.0/16

CIDRs opened in GCE firewall for L4 LB traffic proxy & health checks

`--cluster string`

The name of the kubeconfig cluster to use

`--context string`

The name of the kubeconfig context to use

`--default-not-ready-toleration-seconds int` Default: 300

Indicates the tolerationSeconds of the toleration for notReady:NoExecute that is added by default to every pod that does not already have such a toleration.

`--default-unreachable-toleration-seconds int` Default: 300

Indicates the tolerationSeconds of the toleration for unreachable:NoExecute that is added by default to every pod that does not already have such a toleration.

`-h, --help`

help for kubectl

`--insecure-skip-tls-verify`

If true, the server's certificate will not be checked for validity. This will make your HTTPS connections insecure

`--kubeconfig string`

Path to the kubeconfig file to use for CLI requests.

`--log-backtrace-at traceLocation` Default: :0

when logging hits line file:N, emit a stack trace

`--log-dir string`

If non-empty, write log files in this directory

`--log-file string`

If non-empty, use this log file

`--log-file-max-size uint` Default: 1800

Defines the maximum size a log file can grow to. Unit is megabytes. If the value is 0, the maximum file size is unlimited.

`--log-flush-frequency duration` Default: 5s

Maximum number of seconds between log flushes

`--logtostderr` Default: true

log to standard error instead of files

`--match-server-version`

Require server version to match client version

`-n, --namespace string`

If present, the namespace scope for this CLI request

`--one-output`

If true, only write logs to their native severity level (vs also writing to each lower severity level)

`--password string`

Password for basic authentication to the API server

`--profile string` Default: "none"

Name of profile to capture. One of
(none | cpu | heap | goroutine | threadcreate | block | mutex)

`--profile-output string` Default: "profile.pprof"

Name of the file to write the profile to

`--request-timeout string` Default: "0"

The length of time to wait before giving up on a single server request. Non-zero values should contain a corresponding time unit (e.g. 1s, 2m, 3h). A value of zero means don't timeout requests.

`-s, --server string`

The address and port of the Kubernetes API server

`--skip-headers`

If true, avoid header prefixes in the log messages

`--skip-log-headers`

If true, avoid headers when opening log files

`--stderrthreshold severity` Default: 2

logs at or above this threshold go to stderr

`--tls-server-name string`

Server name to use for server certificate validation. If it is not provided, the hostname used to contact the server is used

`--token string`

Bearer token for authentication to the API server

`--user string`

The name of the kubeconfig user to use

`--username string`

Username for basic authentication to the API server

`-v, --v Level`

number for the log level verbosity

`--version version[=true]`

Print version information and quit

`--vmodule moduleSpec`

comma-separated list of pattern=N settings for file-filtered logging

`--warnings-as-errors`

Treat warnings received from the server as errors and exit with a non-zero exit code

Environment variables

KUBECONFIG

Path to the kubectl configuration ("kubeconfig") file. Default: "\$HOME/.kube/config"

KUBECTL_EXPLAIN_OPENAPIV3

Toggles whether calls to `kubectl explain` use the new OpenAPIv3 data source available. OpenAPIv3 is enabled by default since Kubernetes 1.24.

KUBECTL_ENABLE_CMD_SHADOW

When set to true, external plugins can be used as subcommands for builtin commands if subcommand does not exist. In alpha stage, this feature can only be used for create command(e.g. `kubectl create networkpolicy`).

KUBECTL_PORT_FORWARD_WEBSOCKETS

When set to true, the kubectl port-forward command will attempt to stream using the websockets protocol. If the upgrade to websockets fails, the commands will fallback to use the current SPDY protocol.

KUBECTL_REMOTE_COMMAND_WEBSOCKETS

When set to true, the kubectl exec, cp, and attach commands will attempt to stream using the websockets protocol. If the upgrade to websockets fails, the commands will fallback to use the current SPDY protocol.

KUBECTL_KUBERC

When set to true, kuberc file is taken into account to define user specific preferences.

See Also

- [kubectl annotate](#) - Update the annotations on a resource
- [kubectl api-resources](#) - Print the supported API resources on the server
- [kubectl api-versions](#) - Print the supported API versions on the server, in the form of "group/version"
- [kubectl apply](#) - Apply a configuration to a resource by filename or stdin
- [kubectl attach](#) - Attach to a running container
- [kubectl auth](#) - Inspect authorization
- [kubectl autoscale](#) - Auto-scale a Deployment, ReplicaSet, or ReplicationController
- [kubectl certificate](#) - Modify certificate resources.
- [kubectl cluster-info](#) - Display cluster info

- [kubectl completion](#) - Output shell completion code for the specified shell (bash or zsh)
- [kubectl config](#) - Modify kubeconfig files
- [kubectl cordon](#) - Mark node as unschedulable
- [kubectl cp](#) - Copy files and directories to and from containers.
- [kubectl create](#) - Create a resource from a file or from stdin.
- [kubectl debug](#) - Create debugging sessions for troubleshooting workloads and nodes
- [kubectl delete](#) - Delete resources by filenames, stdin, resources and names, or by resources and label selector
- [kubectl describe](#) - Show details of a specific resource or group of resources
- [kubectl diff](#) - Diff live version against would-be applied version
- [kubectl drain](#) - Drain node in preparation for maintenance
- [kubectl edit](#) - Edit a resource on the server
- [kubectl events](#) - List events
- [kubectl exec](#) - Execute a command in a container
- [kubectl explain](#) - Documentation of resources
- [kubectl expose](#) - Take a replication controller, service, deployment or pod and expose it as a new Kubernetes Service
- [kubectl get](#) - Display one or many resources
- [kubectl kustomize](#) - Build a kustomization target from a directory or a remote url.
- [kubectl label](#) - Update the labels on a resource
- [kubectl logs](#) - Print the logs for a container in a pod
- [kubectl options](#) - Print the list of flags inherited by all commands
- [kubectl patch](#) - Update field(s) of a resource
- [kubectl plugin](#) - Provides utilities for interacting with plugins.
- [kubectl port-forward](#) - Forward one or more local ports to a pod
- [kubectl proxy](#) - Run a proxy to the Kubernetes API server
- [kubectl replace](#) - Replace a resource by filename or stdin
- [kubectl rollout](#) - Manage the rollout of a resource
- [kubectl run](#) - Run a particular image on the cluster
- [kubectl scale](#) - Set a new size for a Deployment, ReplicaSet or Replication Controller
- [kubectl set](#) - Set specific features on objects
- [kubectl taint](#) - Update the taints on one or more nodes
- [kubectl top](#) - Display Resource (CPU/Memory/Storage) usage.
- [kubectl uncordon](#) - Mark node as schedulable
- [kubectl version](#) - Print the client and server version information

- [kubectl wait](#) - Experimental: Wait for a specific condition on one or many resources.

6 - JSONPath Support

The kubectl tool supports JSONPath templates as an output format.

A *JSONPath template* is composed of JSONPath expressions enclosed by curly braces: `{` and `}`. Kubectl uses JSONPath expressions to filter on specific fields in the JSON object and format the output. In addition to the original JSONPath template syntax, the following functions and syntax are valid:

1. Use double quotes to quote text inside JSONPath expressions.
2. Use the `range`, `end` operators to iterate lists.
3. Use negative slice indices to step backwards through a list.
Negative indices do *not* "wrap around" a list and are valid as long as $(- \text{index} + \text{listLength}) \geq 0$.

Note:

- The `$` operator is optional since the expression always starts from the root object by default.
- The result object is printed as its `string()` function.

Functions in Kubernetes JSONPath

Given the JSON input:

```
{
  "kind": "List",
  "items": [
    {
      "kind": "None",
      "metadata": {
        "name": "127.0.0.1",
        "labels": {
          "kubernetes.io/hostname": "127.0.0.1"
        }
      },
      "status": {
        "capacity": { "cpu": "4" },
        "addresses": [ { "type": "LegacyHostIP", "address": "127.0.0.1" } ]
      }
    },
  ],
}
```

```

{
  "kind": "None",
  "metadata": {"name": "127.0.0.2"},
  "status": {
    "capacity": {"cpu": "8"},
    "addresses": [
      {"type": "LegacyHostIP", "address": "127.0.0.2"},
      {"type": "another", "address": "127.0.0.3"}
    ]
  }
},
"users": [
  {
    "name": "myself",
    "user": {}
  },
  {
    "name": "e2e",
    "user": {"username": "admin", "password": "secret"}
  }
]
}

```

Function	Description	Example
text	the plain text	kind is { <code>.kind</code> }
@	the current object	{ <code>@</code> }
<code>.</code> or [<code>]</code>	child operator	{ <code>.kind</code> } , {[<code>'kind'</code>]} or {[<code>'name.type'</code>]}
<code>..</code>	recursive descent	{ <code>..name</code> }
*	wildcard. Get all objects	{ <code>.items[*].metadata.name</code> }
[start:end:step]	subscript operator	{ <code>.users[0].name</code> }

Function	Description	Example
[,]	union operator	<code>{.items[*]['metadata.name', 'status.capacity']}</code>
?()	filter	<code>{.users[?(@.name=="e2e")].user.password}</code>
range , end	iterate list	<code>{range .items[*]}[{.metadata.name}, {.status.capacity}] {end}</code>
''	quote interpreted string	<code>{range .items[*]}{.metadata.name}'\t'{.status.start}</code>
\	escape termination character	<code>{.items[0].metadata.labels.kubernetes\.io}</code>

Using JSONPath expressions with kubectl

Examples using `kubectl` and JSONPath expressions:

```
kubectl get pods -o json
kubectl get pods -o=jsonpath='{@}'
kubectl get pods -o=jsonpath='{.items[0]}'
kubectl get pods -o=jsonpath='{.items[0].metadata.name}'
kubectl get pods -o=jsonpath='{.items[*]['metadata.name', 'status.capacity']}'
kubectl get pods -o=jsonpath='{range .items[*]}{.metadata.name}'\t'{.status.start}'
kubectl get pods -o=jsonpath='{.items[0].metadata.labels.kubernetes\.io/hostname}'
```

Or, with a "my_pod" and "my_namespace" (adjust these names to your environment):

```
kubectl get pod/my_pod -n my_namespace -o=jsonpath='{@}'
kubectl get pod/my_pod -n my_namespace -o=jsonpath='{.metadata.name}'
kubectl get pod/my_pod -n my_namespace -o=jsonpath='{.status}'
```

Note:

On Windows, you must *double* quote any JSONPath template that contains spaces (not single quote as shown above for bash). This in turn means that you must use a single quote or escaped double quote around any literals in the template. For example:

```
kubectl get pods -o=jsonpath="{range .items[*]}{.metadata.name}{'\t'}{.status.
kubectl get pods -o=jsonpath="{range .items[*]}{.metadata.name}{\"\\t\"}{.statu
```

Regular expressions in JSONPath

JSONPath regular expressions are not supported. If you want to match using regular expressions, you can use a tool such as `jq`.

```
# kubectl does not support regular expressions for JSONpath output
# The following command does not work
kubectl get pods -o jsonpath='{.items[?(@.metadata.name=~/^test$/)].metadata.name}'

# The following command achieves the desired result
kubectl get pods -o json | jq -r '.items[] | select(.metadata.name | test("test-"))'
```

7 - kubectl for Docker Users

You can use the Kubernetes command line tool `kubectl` to interact with the API Server. Using `kubectl` is straightforward if you are familiar with the Docker command line tool. However, there are a few differences between the Docker commands and the `kubectl` commands. The following sections show a Docker sub-command and describe the equivalent `kubectl` command.

docker run

To run an nginx Deployment and expose the Deployment, see [kubectl create deployment](#).

docker:

```
docker run -d --restart=always -e DOMAIN=cluster --name nginx-app -p 80:80 nginx
```

```
55c103fa129692154a7652490236fee9be47d70a8dd562281ae7d2f9a339a6db
```

```
docker ps
```

CONTAINER ID	IMAGE	COMMAND	CREATED
55c103fa1296	nginx	"nginx -g 'daemon of...'"	9 seconds ago



kubectl:

```
# start the pod running nginx
kubectl create deployment --image=nginx nginx-app
```

```
deployment.apps/nginx-app created
```



```
# add env to nginx-app
kubectl set env deployment/nginx-app DOMAIN=cluster
```

```
deployment.apps/nginx-app env updated
```

Note:

kubectl commands print the type and name of the resource created or mutated, which can then be used in subsequent commands. You can expose a new Service after a Deployment is created.

```
# expose a port through with a service
kubectl expose deployment nginx-app --port=80 --name=nginx-http
```

```
service "nginx-http" exposed
```

By using kubectl, you can create a [Deployment](#) to ensure that N pods are running nginx, where N is the number of replicas stated in the spec and defaults to 1. You can also create a [service](#) with a selector that matches the pod labels. For more information, see [Use a Service to Access an Application in a Cluster](#).

By default images run in the background, similar to `docker run -d ...`. To run things in the foreground, use `kubectl run` to create pod:

```
kubectl run [-i] [--tty] --attach <name> --image=<image>
```

Unlike `docker run ...`, if you specify `--attach`, then you attach `stdin`, `stdout` and `stderr`. You cannot control which streams are attached (`docker -a ...`). To detach from the container, you can type the escape sequence Ctrl+P followed by Ctrl+Q.

docker ps

To list what is currently running, see [kubectl get](#).

docker:

```
docker ps -a
```

CONTAINER ID	IMAGE	COMMAND	CREATED
14636241935f	ubuntu:16.04	"echo test"	5 seconds ago
55c103fa1296	nginx	"nginx -g 'daemon of...'"	About a minute ago

kubect!

```
kubect! get po
```

NAME	READY	STATUS	RESTARTS	AGE
nginx-app-8df569cb7-4gd89	1/1	Running	0	3m
ubuntu	0/1	Completed	0	20s

docker attach

To attach a process that is already running in a container, see [kubect! attach](#).

docker:

```
docker ps
```

CONTAINER ID	IMAGE	COMMAND	CREATED
55c103fa1296	nginx	"nginx -g 'daemon of...'"	5 minutes ago

```
docker attach 55c103fa1296
...
```

kubect!

```
kubectl get pods
```

NAME	READY	STATUS	RESTARTS	AGE
nginx-app-5jyvm	1/1	Running	0	10m

```
kubectl attach -it nginx-app-5jyvm  
...
```

To detach from the container, you can type the escape sequence Ctrl+P followed by Ctrl+Q.


docker exec

To execute a command in a container, see [kubectl exec](#).

docker:

```
docker ps
```

CONTAINER ID	IMAGE	COMMAND	CREATED
55c103fa1296	nginx	"nginx -g 'daemon of...'"	6 minutes ago



```
docker exec 55c103fa1296 cat /etc/hostname
```

```
55c103fa1296
```

kubectl:

```
kubectl get po
```

NAME	READY	STATUS	RESTARTS	AGE
nginx-app-5jyvm	1/1	Running	0	10m

```
kubectl exec nginx-app-5jyvm -- cat /etc/hostname
```

```
nginx-app-5jyvm
```

To use interactive commands.

docker:

```
docker exec -ti 55c103fa1296 /bin/sh
# exit
```

kubectl:

```
kubectl exec -ti nginx-app-5jyvm -- /bin/sh
# exit
```

For more information, see [Get a Shell to a Running Container](#).


docker logs

To follow stdout/stderr of a process that is running, see [kubectl logs](#).

docker:

```
docker logs -f a9e
```

```
192.168.9.1 - - [14/Jul/2015:01:04:02 +0000] "GET / HTTP/1.1" 200 612 "-" "curl/7.3
192.168.9.1 - - [14/Jul/2015:01:04:03 +0000] "GET / HTTP/1.1" 200 612 "-" "curl/7.3
```



kubectl:

```
kubectl logs -f nginx-app-zibvs
```

```
10.240.63.110 - - [14/Jul/2015:01:09:01 +0000] "GET / HTTP/1.1" 200 612 "-" "curl/7.28.1"
10.240.63.110 - - [14/Jul/2015:01:09:02 +0000] "GET / HTTP/1.1" 200 612 "-" "curl/7.28.1"
```

There is a slight difference between pods and containers; by default pods do not terminate if their processes exit. Instead the pods restart the process. This is similar to the docker run option `--restart=always` with one major difference. In docker, the output for each invocation of the process is concatenated, but for Kubernetes, each invocation is separate. To see the output from a previous run in Kubernetes, do this:

```
kubectl logs --previous nginx-app-zibvs
```

```
10.240.63.110 - - [14/Jul/2015:01:09:01 +0000] "GET / HTTP/1.1" 200 612 "-" "curl/7.28.1"
10.240.63.110 - - [14/Jul/2015:01:09:02 +0000] "GET / HTTP/1.1" 200 612 "-" "curl/7.28.1"
```

For more information, see [Logging Architecture](#).

docker stop and docker rm

To stop and delete a running process, see [kubectl delete](#).

docker:

```
docker ps
```

CONTAINER ID	IMAGE	COMMAND	CREATED
a9ec34d98787	nginx	"nginx -g 'daemon of"	22 hours ago

```
docker stop a9ec34d98787
```

```
a9ec34d98787
```

```
docker rm a9ec34d98787
```

```
a9ec34d98787
```

kubectl:

```
kubectl get deployment nginx-app
```

NAME	READY	UP-TO-DATE	AVAILABLE	AGE
nginx-app	1/1	1	1	2m

```
kubectl get po -l app=nginx-app
```

NAME	READY	STATUS	RESTARTS	AGE
nginx-app-2883164633-aklf7	1/1	Running	0	2m

```
kubectl delete deployment nginx-app
```

```
deployment "nginx-app" deleted
```

```
kubectl get po -l app=nginx-app  
# Return nothing
```

Note:

When you use `kubectl`, you don't delete the pod directly. You have to first delete the Deployment that owns the pod. If you delete the pod directly, the Deployment recreates the pod.

docker login

There is no direct analog of `docker login` in `kubectl`. If you are interested in using Kubernetes with a private registry, see [Using a Private Registry](#).

docker version

To get the version of client and server, see [kubectl version](#).

docker:

```
docker version
```

```
Client version: 1.7.0
Client API version: 1.19
Go version (client): go1.4.2
Git commit (client): 0baf609
OS/Arch (client): linux/amd64
Server version: 1.7.0
Server API version: 1.19
Go version (server): go1.4.2
Git commit (server): 0baf609
OS/Arch (server): linux/amd64
```

kubectl:

```
kubectl version
```

```
Client Version: version.Info{Major:"1", Minor:"6", GitVersion:"v1.6.9+a3d1dfa6f4335", GitCommit:"a3d1dfa6f4335", BuildDate:"2017-09-28T13:08:57Z", GoVersion:"go1.7.3", Compiler:"gc", Platform:"linux/amd64"}
```

```
Server Version: version.Info{Major:"1", Minor:"6", GitVersion:"v1.6.9+a3d1dfa6f4335"
```

docker info

To get miscellaneous information about the environment and configuration, see [kubectl cluster-info](#).

docker:

```
docker info
```

```
Containers: 40
Images: 168
Storage Driver: aufs
 Root Dir: /usr/local/google/docker/aufs
 Backing Filesystem: extfs
 Dirs: 248
 Dirperm1 Supported: false
Execution Driver: native-0.2
Logging Driver: json-file
Kernel Version: 3.13.0-53-generic
Operating System: Ubuntu 14.04.2 LTS
CPUs: 12
Total Memory: 31.32 GiB
Name: k8s-is-fun.mtv.corp.google.com
ID: ADUV:GCYR:B3VJ:HMPQ:KDS5:YKFQ:76VN:IANZ:7TFV:ZBF4:BYJO
WARNING: No swap limit support
```

kubectl:

```
kubectl cluster-info
```

```
Kubernetes master is running at https://203.0.113.141
CoreDNS is running at https://203.0.113.141/api/v1/namespaces/kube-system/services/
kubernetes-dashboard is running at https://203.0.113.141/api/v1/namespaces/kube-sys
Grafana is running at https://203.0.113.141/api/v1/namespaces/kube-system/services/
```


Heapster is running at <https://203.0.113.141/api/v1/namespaces/kube-system/services>
InfluxDB is running at <https://203.0.113.141/api/v1/namespaces/kube-system/services>



8 - kubectl Usage Conventions

Recommended usage conventions for `kubectl` .

Using kubectl in Reusable Scripts

For a stable output in a script:

- Request one of the machine-oriented output forms, such as `-o name` , `-o json` , `-o yaml` , `-o go-template` , Or `-o jsonpath` .
- Fully-qualify the version. For example, `jobs.v1.batch/myjob` . This will ensure that `kubectl` does not use its default version that can change over time.
- Don't rely on context, preferences, or other implicit states.

Subresources

- You can use the `--subresource` argument for `kubectl` subcommands such as `get` , `patch` , `edit` , `apply` and `replace` to fetch and update subresources for all resources that support them. In Kubernetes version 1.37, only the `status` , `scale` and `resize` subresources are supported.
 - For `kubectl edit` , the `scale` subresource is not supported. If you use `--subresource` with `kubectl edit` and specify `scale` as the subresource, the command will error out.
- The API contract against a subresource is identical to a full resource. While updating the `status` subresource to a new value, keep in mind that the subresource could be potentially reconciled by a controller to a different value.

Best Practices

`kubectl run`

For `kubectl run` to satisfy infrastructure as code:

- Tag the image with a version-specific tag and don't move that tag to a new version. For example, use `:v1234` , `v1.2.3` , `r03062016-1-4` , rather than `:latest` (For more information, see [Kubernetes Configuration Good Practices](#)).
- Check in the script for an image that is heavily parameterized.
- Switch to configuration files checked into source control for features that are needed, but not expressible via `kubectl run` flags.

You can use the `--dry-run=client` flag to preview the object that would be sent to your cluster, without really submitting it.

kubectl proxy

Caution:

Browsing untrusted pod or service endpoints through `kubectl proxy` is dangerous, as the served content has implicit access to the Kubernetes API using the proxy's credentials. Use caution and avoid accessing untrusted endpoints while using privileged credentials.

To reduce risk:

- Avoid browsing to untrusted pods or services through `kubectl proxy` .
- Use `--reject-methods='POST,PUT,PATCH,DELETE'` to restrict the proxy to read-only operations when you only need to view resources.
- Use `--reject-paths` to limit which API paths the proxy exposes.
- Do not run `kubectl proxy` with cluster-admin credentials unless necessary.

kubectl apply

- You can use `kubectl apply` to create or update resources. For more information about using `kubectl apply` to update resources, see [Kubectl Book](#).

9 - Kubectl user preferences (kuberc)

① **Feature State:** **Beta** since Kubernetes v1.34

A Kubernetes `kuberc` configuration file allows you to define preferences for `kubectl`, such as default options and command aliases. Unlike the `kubeconfig` file, a `kuberc` configuration file does **not** contain cluster details, usernames or passwords.

On Linux / POSIX computers, the default location of this configuration file is

`$HOME/.kube/kuberc` . The default path on Windows is similar:

`%USERPROFILE%\kube\kuberc` . To provide `kubectl` with a path to a custom `kuberc` file, use the `--kuberc` command line option, or set the `KUBERC` environment variable.

A `kuberc` using the `kubectl.config.k8s.io/v1beta1` format allows you to define the following types of user preferences:

1. [Aliases](#) - allow you to create shorter versions of your favorite commands, optionally setting options and arguments.
2. [Defaults](#) - allow you to configure default option values for your favorite commands.
3. [Credential Plugin Policy](#) - allow you to configure a policy for exec credential plugins.

aliases

Within a `kuberc` configuration, the *aliases* section allows you to define custom shortcuts for `kubectl` commands, optionally with preset command line arguments and flags.

This next example defines a `kubectl getn` alias for the `kubectl get` subcommand, additionally specifying JSON output format: `--output=json` .

```
apiVersion: kubectl.config.k8s.io/v1beta1
kind: Preference
aliases:
- name: getn
  command: get
  options:
  - name: output
    default: json
```

In this example, the following settings were used:

1. `name` - Alias name must not collide with the built-in commands.
2. `command` - Specify the underlying built-in command that your alias will execute. This includes support for subcommands like `create role` .
3. `options` - Specify default values for options. If you explicitly specify an option when you run `kubect1` , the value you provide takes precedence over the default one defined in `kuberc` .

With this alias, running `kubect1 getn pods` will default JSON output. However, if you execute `kubect1 getn pods -oyaml` , the output will be in YAML format.

Full `kuberc` schema is available [here](#).

prependArgs

This next example, will expand the previous one, introducing `prependArgs` section, which allows inserting arbitrary arguments immediately after the `kubect1` command and its subcommand (if any).

```
apiVersion: kubect1.config.k8s.io/v1beta1
kind: Preference
aliases:
  - name: getn
    command: get
    options:
      - name: output
        default: json
    prependArgs:
      - namespace
```

In this example, the following settings were used:

1. `name` - Alias name must not collide with the built-in commands.
2. `command` - Specify the underlying built-in command that your alias will execute. This includes support for subcommands like `create role` .
3. `options` - Specify default values for options. If you explicitly specify an option when you run `kubect1` , the value you provide takes precedence over the default one defined in `kuberc` .
4. `prependArgs` - Specify explicit argument that will be placed right after the command. Here, this will be translated to `kubect1 get namespace test-ns --output json` .

appendArgs

This next example, will introduce a mechanism similar to prepending arguments, this time, though, we will append arguments to the end of the `kubectl` command.

```
apiVersion: kubectl.config.k8s.io/v1beta1
kind: Preference
aliases:
- name: runx
  command: run
  options:
    - name: image
      default: busybox
    - name: namespace
      default: test-ns
  appendArgs:
    - --
    - custom-arg
```

In this example, the following settings were used:

1. `name` - Alias name must not collide with the built-in commands.
2. `command` - Specify the underlying built-in command that your alias will execute. This includes support for subcommands like `create role`.
3. `options` - Specify default values for options. If you explicitly specify an option when you run `kubectl`, the value you provide takes precedence over the default one defined in `kuberc`.
4. `appendArgs` - Specify explicit arguments that will be placed at the end of the command. Here, this will be translated to `kubectl run test-pod --namespace test-ns --image busybox -- custom-arg`.

defaults

Within a `kuberc` configuration, `defaults` section lets you specify default values for command line arguments.

This next example makes the interactive removal the default mode for invoking `kubectl delete`:

```
apiVersion: kubectl.config.k8s.io/v1beta1
```

```
kind: Preference
defaults:
- command: delete
  options:
  - name: interactive
    default: "true"
```

In this example, the following settings were used:

1. `command` - Built-in command, this includes support for subcommands like `create role` .
2. `options` - Specify default values for options. If you explicitly specify an option when you run `kubectl` , the value you provide takes precedence over the default one defined in `kuberc` .

With this setting, running `kubectl delete pod/test-pod` will default to prompting for confirmation. However, `kubectl delete pod/test-pod --interactive=false` will bypass the confirmation.

Credential plugin policy

 **Feature State:** **Beta** since Kubernetes v1.35

Editors of a `kubeconfig` can specify an executable plugin that will be used to acquire credentials to authenticate the client to the cluster. Within a `kuberc` configuration, you can set the execution policy for such plugins by the use of two top-level fields. Both fields are optional.

credentialPluginPolicy

You can configure a policy for credentials plugins, using the optional `credentialPluginPolicy` field. There are three valid values for this field:

1. `"AllowAll"`

When the policy is set to `"AllowAll"` , there will be no restrictions on which plugins may run. This behavior is identical to that of Kubernetes versions prior to 1.35.

2. `"DenyAll"`

When the policy is set to `"DenyAll"` , no exec plugins will be permitted to run.

3. "Allowlist"

When the policy is set to "Allowlist", the user can selectively allow execution of credential plugins. When the policy is "Allowlist", you **must** also provide the `credentialPluginAllowlist` field (also in the top-level). That field is described below.

Note:

In order to maintain backward compatibility, an unspecified or empty `credentialPluginPolicy` is identical to explicitly setting the policy to "AllowAll".

credentialPluginAllowlist

Note:

Setting this field when `credentialPluginPolicy` is not Allowlist (including when that field is missing or empty) is considered a configuration error.

The `credentialPluginAllowlist` field specifies a list of criteria-sets (sets of *requirements*) for permission to execute credential plugins. Each set of requirements will be attempted in turn; once the plugin meets all requirements in at least one set, the plugin will be permitted to execute. That is, the overall result of an application of the allowlist to plugin `my-binary-plugin` is the *logical OR* of the decisions rendered by each item in the list.

As an example, consider the following allowlist configuration:

```
apiVersion: kubernetes.config.k8s.io/v1beta1
kind: Preference
credentialPluginPolicy: Allowlist
credentialPluginAllowlist:
  - command: foo
  - command: bar
  - command: baz
```

In the above example, the allowlist will allow plugins that have the command "foo", "bar", OR "baz".

Note:

For a set of requirements to be valid it **must** have at least one field that is nonempty and explicitly specified. If all fields are empty or unspecified, it is considered a configuration error and the plugin will not be allowed to execute. Likewise if the `credentialPluginAllowlist` field is unspecified, or if it is specified explicitly as the empty list. This is in order to prevent scenarios where the user misspells the `credentialPluginAllowlist` key -- thinking they have specified an allowlist when they actually haven't.

For example, the following is invalid:

```
apiVersion: kubectl.config.k8s.io/v1beta1
kind: Preference
credentialPluginPolicy: Allowlist
credentialPluginAllowlist:
  - command: ""
```

command

`command` names a credential plugin which may be executed. It can be specified as either the basename of the desired plugin, or the full path. If specified as a basename, the decision rendered by this field is "allow" if one of the following two conditions is met:

1. The `command` field is exactly equal to the plugin's `command` field.
2. Full path resolution is performed on both the allowlist `command` and the plugin's `command`, and the results are equal.

If specified as a full path, the decision rendered by this field is "allow" if one of the following conditions is met:

1. The `command` field is exactly equal to the plugin's `command` field (i.e. the plugin's `command` is also a full path).
2. Full path resolution is performed on the plugin's `command` and the allowlist `command` field is an exact match.

With regard to *full path resolution* mentioned earlier in this page, neither symlinks nor shell globs are resolved.

For example, consider an allowlist entry with the `command` `/usr/local/bin/my-binary`, where `/usr/local/bin/my-binary` is a symlink to `/this/is/a/target`. If `command` specified in the kubeconfig is `/this/is/a/target`, it will not be allowed. In order to make that work, you would need to add `/this/is/a/target` to the allowlist explicitly. On the other

hand, if the kubeconfig has the `command` as `/usr/local/bin/my-binary`, then the allowlist would permit it to run.

Note:

While kuberc is in beta, `name` may be used as an alias for `command` in allowlist entries. From Kubernetes 1.36 onward, `name` is deprecated in favor of `command`. Supplying **both** `name` and `command` in the same allowlist entry is considered an error, because these are security-sensitive settings. The `name` field will be removed entirely when kuberc reaches GA.

Example

The following example shows an "Allowlist" policy with its allowlist:

POSIX

Windows

```
apiVersion: kubect1.config.k8s.io/v1beta1
kind: Preference
credentialPluginPolicy: Allowlist
credentialPluginAllowlist:
  - command: my-trusted-binary
  - command: /usr/local/bin/my-other-trusted-binary
```

Managing credential plugin policy with `kubect1 kuberc set`

Rather than editing the kuberc file directly, you can use `kubect1 kuberc set` to configure the credential plugin policy from the command line.

```
# Set the policy to deny all credential plugins
kubect1 kuberc set --section credentialplugin --policy DenyAll

# Set the policy to allow all credential plugins
kubect1 kuberc set --section credentialplugin --policy AllowAll

# Allow only specific credential plugins
kubect1 kuberc set --section credentialplugin \
  --policy Allowlist \
  --allowlist-entry command=my-trusted-binary \
  --allowlist-entry command=my-other-trusted-binary
```

In this example, the following flags were used:

1. `--section credentialplugin` - Select the credential plugin configuration section.
2. `--policy` - Required. Set the policy to `AllowAll` , `DenyAll` , Or `Allowlist` .
3. `--allowlist-entry` - Required when `--policy=Allowlist` . Specify a plugin to allow using comma-separated `key=value` pairs. Currently `command` is the only supported key (for example, `command=<binary-name>`), but the format anticipates future additions such as digest or public-key verification. Repeat this flag to allow multiple plugins.

Suggested defaults

The kubectl maintainers encourage you to adopt kuberc with the following defaults:

Caution:

If you are using a managed Kubernetes provider, check your provider's documentation about what exec plugins are needed in your environment, and use the ["Allowlist"](#) policy instead.

If you encounter problems after setting the ["DenyAll"](#) policy as illustrated below, observe `kubectl` 's error messages to discover which plugins have been prevented from running and cross-reference them with your provider's documentation. Finally, change the policy to "Allowlist" and add the necessary plugins in the [credentialPluginAllowlist](#) field.

```
apiVersion: kubectl.config.k8s.io/v1beta1
kind: Preference
defaults:
  # (1) default server-side apply
  - command: apply
    options:
      - name: server-side
        default: "true"

  # (2) default interactive deletion
  - command: delete
    options:
      - name: interactive
        default: "true"
```

```
# See the above note about managed providers before selecting DenyAll  
credentialPluginPolicy: DenyAll
```

In this example, the following settings are enforced:

1. Defaults to using [Server-Side Apply](#).
2. Defaults to interactive removal whenever invoking `kubectl delete` to prevent accidental removal of resources from the cluster.
3. No executable credential plugins will be permitted to execute.

Disable kuberc

To temporarily disable the `kuberc` functionality, set (and export) the environment variable `KUBERC` with the value `off` :

```
export KUBERC=off
```

or disable the feature gate:

```
export KUBECTL_KUBERC=false
```

This might be useful for troubleshooting whether your `kuberc` is causing a problem.