# Service06 rsync 同步 inotify 同步 cobbler

# 一 客户端开机启动,引导项

1.本机磁盘 2.光驱设备 3.U 盘 4.网卡进行网络安装

二 rsync

2.1 rsyn:remote sync 远程同步

支持本地复制,或与其他 SSH\rsync 主机同步

官网 http://rsync.samba.org/

#### 2.2 rsync 同步传输

命令:rsync [选项...] 源目录 目标目录

同步与复制的差异

复制:完全拷贝源到目标

同步:增量拷贝.只传输变化过的数据

## 2.3 操作选项

-n: 测试同步过程,不做实际修改

--delete: 删除目标文件夹内多余的文档

-a: 归档模式相当于-rlotgoD

-v: 显示详细操作信息

-z: 传输过程中启用压缩/解压 [建议 1G 以上启用]

·r: 递归.包括目录/子目录及所有文件

-l: 保留符号链接文件

-p\-t: 保留文件的权限\时间标记

-o\-g: 保留文件的属主\属组标记

-D: 保留设备文件及其他特殊文件

#### 2.4 操作示例

[root@svr7~]# mkdir /nsd19

[root@svr7 ~]# mkdir /todir

[root@svr7 ~]# cp /etc/passwd /nsd19

[root@svr7~]# touch /nsd19/1.txt

[root@svr7~]# rsync -av /nsd19 /todir //同步 nsd19 目录及其内容到/todir

sending incremental file list

nsd19/

//同步的内容

nsd19/1.txt

nsd19/passwd

sent 1,157 bytes received 58 bytes 2,430.00 bytes/sec

total size is 968 speedup is 0.80

[root@svr7 ~]# rm -rf /todir/\*

[root@svr7~]# rsync -av /nsd19/ /todir //同步 nsd19 的内容到/todir

sending incremental file list

./

#### passwd

sent 1,142 bytes received 57 bytes 2,398.00 bytes/sec

total size is 968 speedup is 0.81

[root@svr7~]# echo haha >> /nsd19/1.txt //修改 /nsd19 的内容

[root@svr7 ~]# cat /nsd19/1.txt

haha

[root@svr7 ~]# rsync -av /nsd19/ /todir/

//同步/nsd19 目录内修改的内容到/todir 目录内,两个目录后都接

"/"符号,此符号可用 TAB 键自动补齐

sending incremental file list

1.txt

sent 137 bytes received 35 bytes 344.00 bytes/sec

total size is 973 speedup is 5.66

[root@svr7 ~]# ls /todir

1.txt passwd

[root@svr7~]# mkdir /todir/abcdefg // /todir 内增加内容

[root@svr7 ~]# ls /todir

```
1.txt abcdefg passwd

[root@svr7~]# rsync-av -delete /nsd19/ /todir/

//删除/todir 内相对于/nsd19 内多余的内容

sending incremental file list

deleting abcdefg/

/
sent 88 bytes received 27 bytes 230.00 bytes/sec

total size is 973 speedup is 8.46
```

#### 2.5 远程同步

rsync + SSH 同步

与远程的 SSH 目录保持同步

下行: rsync [...] user@host:远程目录 本地目录

上行: rsync [...] 本地目录 user@host:远程目录

[root@svr7 ~]# rsync -av --delete /nsd19/ root@192.168.4.207:/opt/

//虚拟机 A 上将/nsd19 内数据上传到虚拟机 B /opt 目录内 Warning: Permanently added '192.168.4.207' (ECDSA) to the list of known hosts. root@192.168.4.207's password: sending file list

/ //上行的内容

1.txt

abc1.txt

abc2.txt

abc3.txt

abc4.txt

abc5.txt

passwd

total size is 973 speedup is 0.61

[root@pc207~]# ls /opt //查看虚拟机 B 上 /opt 内容 1.txt abc1.txt abc2.txt abc3.txt abc4.txt abc5.txt passwd

sent 1,435 bytes received 152 bytes 352.67 bytes/sec

# 三 实时远程同步

实时 rsync + SSH,其中 SSH 需要密码.

解决方案:通过公钥 私钥(两个文件)的配对性,实现 SSH 无密码验证.

# 3.1 生成 公钥 私钥

虚拟机 A

[root@svr7~]# ssh-keygen //生成公钥 私钥命令

Generating public/private rsa key pair.

Enter file in which to save the key (/root/.ssh/id rsa): //默认

Enter passphrase (empty for no passphrase): //不输入密码

Enter same passphrase again:

//确认不输入密码

Your identification has been saved in /root/.ssh/id rsa.

Your public key has been saved in /root/ssh/id rsa.pub.

The key fingerprint is:

SHA256:bdW27JFW0n28LTeUBHy+5XFKN7lVtzC1VlYnqsdXQFc root@svr7.tedu.cn

The key's randomart image is:

authorized keys: 记录公钥

authorized\_keys id\_rsa id\_rsa.pub known\_hosts

id\_rsa: 私钥 id\_rsa.pub: 公钥 known\_hosts:记录连接过的远程主机

```
3.2 将公钥上传到虚拟机 B
```

一台主机上可以存储多个公钥

[root@svr7 ~]# ssh-copy-id root@192.168.4.207

//虚拟机 A 上将公钥传递给虚拟机 B

/usr/bin/ssh-copy-id: INFO: Source of key(s) to be installed: "/root/.ssh/id\_rsa.pub"

/usr/bin/ssh-copy-id: INFO: attempting to log in with the new key(s), to filter out any

that are already installed

/usr/bin/ssh-copy-id: INFO: 1 key(s) remain to be installed -- if you are prompted now

it is to install the new keys

root@192.168.4.207's password:

Number of key(s) added: 1

Now try logging into the machine, with: "ssh 'root@192.168.4.207"

and check to make sure that only the key(s) you wanted were added.

[root@svr7~]# rsync -av --delete /nsd19/ root@192.168.4.207:/opt/ //验证

sending incremental file list //验证,无需再输入密码

deletina 2.txt

1

sent 177 bytes received 24 bytes 134.00 bytes/sec

total size is 973 speedup is 4.84

拥有私钥的主机,能无密码登录拥有公钥的机器,

# 3.3 监控/nsd19 目录变化

```
Linux 内核的 inotify 机制
```

提供 inotify-tools 控制工具可条用此机制实现监控

找到 inotify-tools

真机

[student@room9pc01 ~]\$ scp /linux-soft/01/tools.tar.gz root@192.168.4.7:/root/

虚拟机 A

[root@svr7 ~]# ls /root/

Desktop tools.tar.gz

tar -xf /root/tools.tar.gz -C /

ls /tools/

安装 gcc 与 make

解包

[root@svr7 ~]# ls /root/

Desktop tools.tar.qz

[root@svr7 ~]# tar -xf tools.tar.gz -C /

[root@svr7 ~]# ls /

bin dev home lib64 mnt opt root sbin sys todir usr boot etc lib media nsd19 proc run srv tmp **tools** var

[root@svr7~]# ls /tools

inotify-tools-3.13.tar.gz other

[root@svr7 ~]# tar -xf /tools/inotify-tools-3.13.tar.gz -C /opt

[root@svr7~]# cd /opt/inotify-tools-3.13/

运行 configure 脚本进行配置检测

[root@svr7 inotify-tools-3.13]# /configure

运行 make 进行编译

[root@svr7 inotify-tools-3.13]#make

运行 make install 进行安装

[root@svr7 inotify-tools-3.13]#make install

验证

[root@svr7 inotify-tools-3.13]# ls /usr/local/bin/inotifywait

/usr/local/bin/inotifywait //此路径下有 inotifywait 在表示成功

## inotify 命令

-m:持续监控,捕获一个事件后不退出

-r:递归监控,包括子目录及文件

-q:减少屏幕输出信息

e:指定监视的 modify\move\create\delete\attrib(属性) 等事件类别

-e 不写默认监控所有

## 3.4 编写脚本实现监视与同步的结合

inotifywait -rg /nsd19/

```
rsync -av --delete /nsd19/ root@192.168.4.207:/opt/
书写脚本 rsync.sh
循环 for 循环话合写有次数的循环
死循环while 循环适合写无限次数的循环
while [条件]
      do
             重复执行的代码
      done
while 命令
      do
             重复执行的代码
      done
虚拟机 A
      [root@svr7~]# vim rsync.sh //创建 shell 脚本并编写
      #!/bin/bash
      while inotifywait -rqq /nsd19/
        do
          rsync -a --delete /nsd19/ root@192.168.4.207:/opt/
        done
      [root@svr7~]# ll /root/rsync.sh //查看并修改 rsync.sh 的权限并修改
```

-rw-r--r-- 1 root root 112 7 月 22 11:36 /root/rsync.sh

[root@svr7~]# chmod +x /root/rsync.sh

froot@svr7 ~1# ll /root/rsvnc.sh

-rwxr-xr-x 1 root root 112 7 月 22 11:36 /root/rsync.sh

[root@svr7~]# /root/rsync.sh & //放入后台执行

[root@svr7~]# jobs //查看后台运行的进程

[1]+ 运行中

/root/rsync.sh &

#### 四 cobbler 装机平台(看笔记能搭)

## 41 基本概念

是一款快速的网络系统部署工具

集中管理所需服务.如 DHCP\DNS\TFTP\WEB

内部集成了一个镜像版本仓库

内部集成了一个 ks 应答文件仓库

提供了 yum 源管理\web 界面管理\API 接口\电源管理

与 PXE 相比,比 PXE 简单,多版本系统部署简单, 没 PXE 自动化自定义度高

## 4.2 手动设置一个包含图形功能的虚拟机

root 1 lisi 1

主机名 cobbler.tedu.cn

hostname cobbler.tedu.cn

echo cobbler.tedu.cn > /etc/hostname

```
设置 IP 192.168.4.123/24
```

4.1 基本概念

nmcli connection modify eth0 ipv4.method manual ipv4.addresses '192.16

8.4.123/24' connection.autoconnect yes //设置 IP 和子掩

nmcli connection up eth0

防火墙设置为 trusted firewall-cmd --set-default-zone=trusted

关闭 selinux

setenforce 0

getenforce

vim /etc/selinux/config

SELINUX=permissive

## 搭建 yum

[root@cobbler ~]#cd /etc/yum.repos.d

[root@cobbler ~]#mkdir repo

[root@cobbler ~]#mv \*repo repo

[root@cobbler ~]#vim /etc/yum.repos.d/local\_repo.repo

//修改 yum 配置文件

[local\_repo]

name=centos1804

baseurl="ftp://192.168.4.254/centos-1804"

```
enabled=1
```

gpgcheck=0

[root@cobbler~]#yum repolist //验证

[root@cobbler ~]#yum -y install xeyes //验证

# 4.3 真机传输 cobbler 到虚拟机

[student@room9pc01 ~]\$ scp /home/student/桌面/cobbler.zip root@192.168.4.123;/root/ [root@cobbler ~]# Is

#### 4.4 解压 cobbler.zip

[root@cobbler ~]# unzip cobbler.zip -d /

[root@cobbler ~]# ls /cobbler/

cobbler boot.tar.gz cobbler rpm.zip cobbler web.png

froot@cobbler cobbler1# unzip /cobbler/cobbler rpm.zip -d /opt/

[root@cobbler cobbler]# ls /opt/cobbler/

#### 4.5 安装 cobbler 主程序\工具包等

[root@cobbler cobbler]# yum -y install dhcp httpd mod\_ssl

[root@cobbler cobbler]# yum -y install /opt/cobbler/\*.rpm //安装所有 rpm 包

[root@cobbler cobbler]# rpm -q cobbler //验证 cobbler 是否安装

cobbler-2.8.2-1.el7.x86 64

cobbler cobbler 主程序

cobbler-web cobbler 的 web 服务包

pykickstart cobbler 检查 kickstart 语法错误

httpd apache web 服务

httpd http 服务

mod ssl 为 apache web 提供密码保护

## 4.6 设置 cobbler 配置文件

[root@cobbler cobbler]# vim /etc/cobbler/settings

: set nu

272 next server: 192.168.4.123 //设置下一个服务器为本机

384 server: 192.168.4.123 //设置本机为 cobbler 服务器

242 manage\_dhcp: 1 //设置 cobbler 管理 dhcp 服务

292 pxe just once: 1 //防止客户端重复安装操作系统

## 4.7 配置 cobbler 的 DHCP

[root@cobbler cobbler]# vim /etc/cobbler/dhcp.template

末行模式:%s/旧/新/g //全文替换旧为新

末行模式:%s /192.168.1/192.168.4/g //全文替换 192.168.1 为 192.168.4

## 4.8 绝对路径解压 cobbler\_boot.tar.gz //众多的引导文件

[root@cobbler cobbler]# tar -tf /cobbler/cobbler\_boot.tar.gz //查看包内容

[root@cobbler cobbler]# tar -xPf /cobbler/cobbler\_boot.tar.gz //绝对路径释放文件

[root@cobbler cobbler]# ls /var/lib/cobbler/loaders/ //查看绝对路径下的文件

# 4.9 启动相关服务并设置开机自启

[root@cobbler ~]# systemctl restart cobblerd

[root@cobbler ~]# systenctl enable cobblerd

[root@cobbler ~]# systemctl restart httpd

[root@cobbler ~]# systemctl enable httpd

[root@cobbler ~]# systemctl restart tftp

[root@cobbler ~]# systemctl enable tftp

[root@cobbler ~]# systemctl restart rsyncd //rsyncd 为同步服务

[root@cobbler ~]# systemctl enable rsyncd

# 4.10 同步刷新 cobbler 配置

[root@cobbler~]# cobbler sync //检测所有配置是否正确

#### 4.11 cobbler 应用

cobbler import --path=挂载点 --name=导入系统命名(随意起)

[root@cobbler ~]# mkdir dvd

froot@cobbler ~1# mount /dev/cdrom /dvd/

[root@cobbler ~]# ls /dvd

[root@cobbler ~]# cobbler import --path=/dvd --name=centos7

cobbler 导入的镜像放在:/var/www/cobbler/ks\_mirror

## 4.12 KVM 新机安装系统

步骤同 PXE: root 密码:cobbler

#### 五 环境变量

都为大写

#### PATH:存放执行命令程序的搜寻路径

[root@cobbler /]# vim /opt/hello.sh

[root@cobbler /]# chmod +x /opt/hello.sh

[root@cobbler /]# /opt/hello.sh

hello

[root@cobbler/]# echo \$PATH

/usr/local/sbin:/usr/local/bin:/usr/sbin:/usr/bin:/root/bin //路径任选一个

[root@cobbler /l# cp /opt/hello.sh /usr/bin/ //拷贝后即刻生效

[root@cobbler/]# hello.sh //测试

hello

### 六 权限的掩码 umask 值: 与目录默认权限有关

[root@cobbler ~]# umask

0022

影响所有新建目录的权限值

新建日录的默认权限值=777-022=755

新建文件的默认权限 644(目录基础上减去了执行权限)

修改 umask 命令: umask 值