forum.xpdfreader.com Register **U** Login ★ Board index < Xpdf open source</p>

Segmentation fault in xpdf-4.04/xpdf/TextOutputDev.cc:988 in TextLine::TextLine()



Mon Apr 25, 2022 11:56 pm

Hello.

In Xpdf 4.04, I crashed pdftotext with the provided test case. There is a Segmentation fault on pdftotext. It can be triggered by sending a crafted PDF file to the pdftotext(verson 4.0.4) binary.

Enviroment:

- --Tested on Ubuntu 20.04.2 LTS x86_64,AFL++
- --gcc version 9.3.0
- --xpdf version xpdf 4.04

https://dl.xpdfreader.com/xpdf-4.04.tar.gz

run in the terminal:

gdb --args \$HOME/fuzzing_xpdf/install/bin/pdftotext \$HOME/fuzzing_xpdf/test/poc1 \$HOME/fuzzing_xpdf/output The stack straces are as follow:

Program received signal SIGSEGV, Segmentation fault.

0x00000000050154d in TextLine::TextLine (this=<optimized out>, wordsA=<optimized out>,

wordsA@entry=0x6030000101b0, xMinA=xMinA@entry=0, yMinA=yMinA@entry=0, xMaxA=xMaxA@entry=0,

yMaxA=yMaxA@entry=0, fontSizeA=fontSizeA@entry=0)

at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:988

988 hyphenated = text[len - 1] == (Unicode)'-';

(gdb) bt

#0 0x0000000050154d in TextLine::TextLine (this=<optimized out>, wordsA=<optimized out>, wordsA@entry=0x6030000101b0, xMinA=xMinA@entry=0, yMinA=yMinA@entry=0, xMaxA=xMaxA@entry=0,

yMaxA=yMaxA@entry=0,

fontSizeA=fontSizeA@entry=0) at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:988

#1 0x000000000541917 in TextPage::buildLine (this=<optimized out>, this@entry=0x612000000640, charsA=<optimized out>, charsA@entry=0x603000010180, rot=<optimized out>, xMin=<optimized out>, yMin=<optimized out>,

xMax=<optimized out>, yMax=<optimized out>) at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:5162

#2 0x00000000053f260 in TextPage::buildLine (this=this@entry=0x612000000640, blk=blk@entry=0x606000004340) at

/home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:5084

#3 0x00000000053eab2 in TextPage::buildLines (this=this@entry=0x612000000640, blk=0x606000004340,

lines=lines@entry=0x603000010150, splitSuperLines=splitSuperLines@entry=0)

at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:4884


#4 0x00000000053e9dc in TextPage::buildLines (this=this@entry=0x612000000640, blk=<optimized out>,

blk@entry=0x6060000041c0, lines=lines@entry=0x603000010150, splitSuperLines=splitSuperLines@entry=0)

at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:4892

#5 0x00000000053c2e0 in TextPage::buildColumn (this=this@entry=0x612000000640, blk=blk@entry=0x6060000041c0) at

```
/home/elva/fuzzing xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:4708
#6 0x00000000053c1d6 in TextPage::buildColumns2 (this=this@entry=0x612000000640, blk=0x6060000041c0,
columns=columns@entry=0x603000010120, primaryLR=primaryLR@entry=1)
at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:4678
#7 0x00000000053c11c in TextPage::buildColumns2 (this=this@entry=0x612000000640, blk=<optimized out>,
blk@entry=0x606000005120, columns=columns@entry=0x603000010120, primaryLR=primaryLR@entry=1)
at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:4690
#8 0x00000000050a6b5 in TextPage::buildColumns (this=0x612000000640, tree=0x606000005120, primaryLR=1) at
/home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:4666
#9 TextPage::writeReadingOrder (this=0x612000000640, outputStream=outputStream@entry=0x615000001200,
outputFunc=outputFunc@entry=0x550c10 <outputToFile(void*, char const*, int)>, uMap=uMap@entry=0x606000001dc0,
space=space@entry=0x7ffffffdde0 " ", spaceLen=spaceLen@entry=1, eol=0x7ffffffdde0 "\n6\340E", eolLen=1) at
/home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:1754
#10 0x0000000050a0d9 in TextPage::write (this=<optimized out>, outputStream=<optimized out>, outputFunc=
<optimized out>) at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/TextOutputDev.cc:1686
#11 0x0000000000602264 in Gfx::~Gfx (this=0x60f0000008b0) at /home/elva/fuzzing xpdf/xpdf-4.04/xpdf/Gfx.cc:618
#12 0x00000000075700b in Page::displaySlice (this=<optimized out>, out=<optimized out>, hDPI=<optimized out>, vDPI=
<optimized out>, rotate=<optimized out>, useMediaBox=<optimized out>, crop=<optimized out>, sliceX=<optimized out>,
sliceY=<optimized out>, sliceW=<optimized out>, sliceH=<optimized out>, printing=<optimized out>, abortCheckCbk=
<optimized out>, abortCheckCbkData=<optimized out>) at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/Page.cc:455
#13 0x00000000007563f2 in Page::display (this=0xfffffffffff, out=0x8, hDPI=-1.8325506472120096e-06, vDPI=0,
rotate=8193, useMediaBox=0, crop=-134463488, printing=<optimized out>, abortCheckCbk=0x0, abortCheckCbkData=0x0)
at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/Page.cc:368
#14 0x0000000007659af in PDFDoc::displayPage (this=<optimized out>, out=<optimized out>, page=1, hDPI=<optimized
out>, vDPI=<optimized out>, rotate=<optimized out>, useMediaBox=<optimized out>, crop=<optimized out>,
printing=<optimized out>, abortCheckCbk=<optimized out>, abortCheckCbkData=<optimized out>) at
/home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/PDFDoc.cc:442
#15 PDFDoc::displayPages (this=<optimized out>, out=<optimized out>, firstPage=<optimized out>, lastPage=<optimized
out>, hDPI=<optimized out>, vDPI=<optimized out>, rotate=<optimized out>, useMediaBox=<optimized out>,
crop=<optimized out>, printing=<optimized out>, abortCheckCbk=<optimized out>, abortCheckCbkData=<optimized out>)
at /home/elva/fuzzing_xpdf/xpdf-4.04/xpdf/PDFDoc.cc:460
#16 0x0000000005564b0 in main (argc=<optimized out>, argv=<optimized out>) at /home/elva/fuzzing_xpdf/xpdf-
4.04/xpdf/pdftotext.cc:306
you can reproduced the bug by the follow step:
cmake -DCMAKE_BUILD_TYPE=Debug $HOME/fuzzing_xpdf/xpdf-4.04 -
DCMAKE_INSTALL_PREFIX=$HOME/fuzzing_xpdf/install/ -DCMAKE_CXX_COMPILER=afl-clang-fast++
AFL_USE_ASAN=1 make
Sudo AFL_USE_ASAN=1 make install
$HOME/fuzzing_xpdf/install/bin/pdftotext $HOME/fuzzing_xpdf/test/poc1 $HOME/fuzzing_xpdf/output
you can download this POC file at ATTACHMENTS
Thank you.
 ATTACHMENTS
 poc1.rar
 (1.06 KiB) Downloaded 194 times
```



Powered by phpBB® Forum Software © phpBB Limited Privacy | Terms