Talos Vulnerability Report

TALOS-2020-1163

SoftMaker Office TextMaker Document Record 0x002a integer overflow vulnerability

JANUARY 5, 202

CVE NUMBER

CVE-2020-13546

Summary

An exploitable integer overflow vulnerability exists in the TextMaker document parsing functionality of SoftMaker Office 2021's TextMaker application. A specially crafted document can cause the document parser to miscalculate a length used to allocate a buffer, later upon usage of this buffer the application will write outside its bounds resulting in a heap-based buffer overflow.

An attacker can entice the victim to open a document to trigger this vulnerability.

Tested Versions

SoftMaker Software GmbH SoftMaker Office TextMaker 2021 (revision 1014)

Product URLs

https://www.softmaker.com/en/softmaker-office

CVSSv3 Score

8.8 - CVSS:3.0/AV:N/AC:L/PR:N/UI:R/S:U/C:H/I:H/A:H

CWE

CWE-190 - Integer Overflow or Wraparound

Details

SoftMaker Software GmbH is a German software company that develops and releases office software. Their flagship product, SoftMaker Office, is supported on a variety of platforms and contains a handful of components which can allow the user to perform a multitude of tasks such as word processing, spreadsheets, presentation design, and even allows for scripting. Thus the SoftMaker Office suite supports a variety of common office file formats, as well as a number of internal formats that the user may choose to use when performing their necessary work.

The TextMaker component of SoftMaker's suite is designed as an all-around word-processing tool, and supports of a number of features that allow it to remain competitive with similar office suites that are developed by its competitors. Although the application includes a number of parsers that enable the user to interact with these common document types or templates, a native document format is also included. This undocumented format is labeled as a TextMaker Document, and will typically have the extension ".tmd" when saved as a file.

When the application needs to read a file in order to allow the user to interact with the desired document, it will load the document by executing the following function. This function will take an object containing information about the document and the path to load the document from its parameters. After determining which particular flags are set, the function call at [1] will be made in order to determine what type of document the file is.

```
0x7c2ef0:
                        push
                                   %rbp
0x7c2ef1:
0x7c2ef4:
0x7c2efb:
                                   %rsp,%rbp
$0x260,%rsp
%rdi,-0x248(%rbp)
                        mov
sub
                                                                   ; documentObject
                        mov
0x7c2f02:
0x7c2f09:
0x7c2f10:
                                  %rsi,-0x250(%rbp)
%rdx,-0x258(%rbp)
%ecx,-0x25c(%rbp)
                                                                   ; path name
; flags
                        moν
                        mov
0x7c314a:
0x7c3150:
                                   -0x234(%rbp),%edx
-0x258(%rbp),%rcx
                                                                   ; flags
; path name
                        moν
                        mov
0x7c3157:
                                    -0x248(%rbp),%rax
                                                                   ; documentObject
                        mov
0x7c315e:
0x7c3161:
                        mov
                                   %rcx,%rsi
%rax,%rdi
                        mov
0x7c3164:
0x7c3169:
                        callq
                                  0x60b4b8
                                                                   ; [1] ReadDocument
                                   %eax,%eax
                        test
0x7c316b:
                        setne %al
0x7c316e:
0x7c3170:
                         test
                        ie
                                   0x7c319e
```

First the application will take its parameters consisting of the object containing the document, and the path the file to read the document from onto the stack. The path will then be passed to the function call at [2] which is responsible for fingerprinting the document to try and identify which document parser to use. Upon returning, the function call at address 0x60b703 will be made to actually read the file.

```
%rbp
%rsp,%rbp
0x60h4h8.
                       push
0x60b4b9:
                      mov
0x60b4bc:
                      sub
                                $0xbb0,%rsp
                      mov
                                %rdi,-0xb98(%rbp)
%rsi,-0xba0(%rbp)
                                                              ; document object ; document path
0x60b4c3:
0x60h4d1 ·
                      mov
                                %edx.-0xba4(%rbp)
                                                              : flags
0x60b654:
                      lea
                                 -0x640(%rbp),%rax
                                                              ; path
                                %rax,%rdi
0x627cb8
%eax,-0xb6c(%rbp)
0x60h65h.
                      mov
0x60b65e:
0x60b663:
                       callq
                                                              ; [2] \setminus Fingerprint the document
                      mov
0x60b669:
                      movl
                                $0x1,-0xb7c(%rbp)
0x60b6d2:
                                 -0xb84(%rbp),%r8d
                      mov
                                -0xba4(%rbp),%edi
-0x640(%rbp),%rcx
-0xb70(%rbp),%edx
0x60b6d9:
0x60b6df:
                                                              ; flags
; document path
                       mov
lea
0x60b6e6:
                      mov
0x60b6ec:
0x60b6f3:
                                 -0xb58(%rbp),%rsi
-0xb98(%rbp),%rax
                      mov
                                                              ; FILE* ; document object
                      moν
0x60b6fa:
                      mov
                                %r8d,%r9d
                                %edi,%r8d
%rax,%rdi
0x6273fe
0x60b6fd:
0x60b700:
                      mov
                      callo
                                                              : [3] read the TextMaker document
0x60b703:
0x60b708:
0x60b70a:
                                %eax,%eax
0x60c2d1
                      jе
```

To fingerprint the file, the application will first open up the file at [4]. Following this at [5], the application then reads 12 bytes from its header to take a sample of the bytes near the beginning of the file. This is then used by the application in order to identify which document type the user is trying to open. The first signature, however, is for the *.tmd (TextMaker Document) file format. In order to verify that the signature corresponds to a TextMaker Document, the first 32-bits are read from the file at [5]. These bits are then compared against the integer, 0xff00564d. After verifying the initial 32-bits, the application will then skip over 16-bits which represent an offset to the index table which will be described later, and then check if the 16-bits that follow are either of the values 0x000e or 0x000f.

```
0x627cb8:
                   push
                           %rbp
0x627cb9:
                   mov
                            %rsp,%rbp
$0x50,%rsp
0x627cbc:
                   sub
0x627cc0:
                   mov
                            %rdi,-0x48(%rbp)
                                                     ; path
Ox627cda:
                   mov
                            -0x48(%rbp).%rax
0x627cde:
                            $0x16ba78a,%esi
                   mov
0x627ce3:
                   mov
                            %rax.%rdi
0x627ce6
                   callq
                           0x12f51h7
                                                     ; [3] open up file as a FILE*
                            %rax,-0x38(%rbp)
0x627ceb:
                   moν
0x627cff:
                   mov
lea
                            $0xc,%edx
-0x30(%rbp),%rcx
-0x38(%rbp),%rax
                                                     ; length
; buffer containing header to fingerprint
0x627d04:
0x627d08:
                   mov
0x627d0c:
0x627d0f:
                            %rcx,%rsi
                                                     ; destination
                           %rax,%rdi
0x62733d
                                                     ; FILE*
; [4]
                   callq
0x627d12:
0x627d17:
0x627d19:
                           %eax,%eax
%al
                   sete
0x627d24:
                   mov
                             -0x30(%rbp),%eax
                                                     ; [5] read first uint32_t from file
0x627d27:
0x627d2c:
                   cmp
jne
                            $0xff00564d,%eax
0x627d49
0x627d2e:
0x627d32:
                           -0x2a(%rbp),%eax
$0xe,%ax
                   movzwl
                                                     ; [5] read uint16_t from offset +6
                   cmp
0x627d36:
                   ie
                            0x627d42
0x627d38:
                   movzwl -0x2a(%rbp),%eax
                                                     ; [5] read uint16_t from offset +6
                            $0xf.%ax
0x627d3c:
                   cmp
                            0x627d49
0x627d40:
                   ine
0x627dfc:
               leaved
0x627dfd:
                retq
```

Upon using the fingerprint to determine the file format type, the application will return to the caller. As previously mentioned, the function call at [6] will be used to actually parse the TextMaker Document file format.

```
0x60h6d2.
                 mov
                         -Axh84(%rhn),%r8d
0x60b6d9:
                         -0xba4(%rbp),%edi
                 mov
                                                ; flags
0x60b6df:
                 lea
                         -0x640(%rbp).%rcx
                                                ; document path
                         -0xb70(%rbp),%edx
-0xb58(%rbp),%rsi
0x60b6e6:
                 mov
0x60b6ec:
                                                : FILE*
                 mov
0x60h6f3.
                 mov
                         -0xb98(%rbp),%rax
                                                ; document object
0x60b6fa:
                         %r8d,%r9d
0x60b6fd:
                 mov
                         %edi.%r8d
                 mov
callq
0x60h700
                         %rax.%rdi
0x60b703:
                                                ; [6] read the TextMaker document
                         %eax,%ea6
0x60b708:
                 test
0x60b70a:
                 jе
                         0x60c2d1
```

When reading the document, the application will re-read the 12-byte header in order to extract the 16-bit field that was previously skipped over during the fingerprint process. As the stream was previously opened and passed to this function, it is used to seek to the beginning of the file at [7]. Afterwards at [8] the same 12 bytes that container the header that was used during fingerprinting are read. At offset +4 of this header, a uint16_t is read which is used as a file offset. This 16-bit offset is then passed to the function call at [9] to seek the stream to the index table for the document. Once the stream's offset has been set correctly, the function call at [10] is made which will begin to parse the index table of the document.

```
%rbp
%rsp,%rbp
0x6273fe:
                    push
0x6273ff:
                    mov
0x627402:
                    sub
                             $0x60.%rsp
                    mov
mov
                             %rdi,-0x38(%rbp)
%rsi,-0x40(%rbp)
0x627406
                                                        ; document object
0x62740a:
                             %edx,-0x44(%rbp)
%rcx,-0x50(%rbp)
%r8d,-0x48(%rbp)
0x62740e
                    mov
0x627411:
0x627415:
                                                        ; document path
                    mov
0x627419:
                    moν
                             %r9d,-0x54(%rbp)
0x627437:
                              -0x40(%rbp),%rax
                    mov
                             $0x0,%edx
$0x0,%esi
%rax,%rdi
0x62743b:
                    mov
mov
                                                       ; SEEK SET
0x627440:
0x627445:
                    mov
0x627448:
                    callq
                            0x410fe0 <fseek@plt> ; [7] seek to beginning of file
0x62744d:
                             $0xc,%edx
                                                       ; length
                    mov
0x627452:
0x627456:
                              -0x20(%rbp),%rcx
-0x40(%rbp),%rax
                                                       ; destination
; FILE*
                    lea
                    moν
0x62745a:
                    mov
                             %rcx,%rsi
0x62745d:
0x627460:
0x627465:
                    mov
callq
                                                       ; [8] fread
                    test
                             %eax.%eax
0x627467:
0x62746a:
                             %al
%al,%al
                     sete
                    test
0x62746c:
                    jе
                             0x627484
0x627484:
                    movzwl -0x1c(%rbp),%eax
                                                       ; uint16_t offset
0x627488:
                    movzwl %ax,%ecx
mov -0x40(%rbp),%rax
0x62748b:
                                                       ; SEEK_SET
0x62748f:
                    mov
                             $0x0.%edx
0x627494:
                    mov
                             %rcx,%rsi
0x627497:
                                                          FILE*
                             %rax,%rdi
                    mov %rax,%rdi ; FILE*
callq 0x410fe0 <fseek@plt> ; [9] seek to uint16_t
0x62749a:
0x6274a7:
                             -0x50(%rbp),%rdx
                                                        ; filename
0x6274ab:
                    mov
                              -0x40(%rbn).%rsi
                                                          stream
0x6274af:
0x6274b3:
                              -0x38(%rbp),%rax
                                                        ; document object
                             %rax,%rdi
                            0x626b0f
%eax,-0x24(%rbp)
0x6274b6:
                    callq
                                                       ; [10] parse index table
0x6274bb:
```

Before parsing the index table containing all of the records that compose the TextMaker Document, the function call at [11] is used to read 10-bytes from the current position of the file. Then at [12], 32-bits are read and used to verify the signature of the index table by comparing it with the integer 0x314592d which corresponds to the value for π. After validating the signature, the application will read two 16-bit integers from the file which correspond to the version. At [14], both version components are read and then combined into a 12-bit version. This version is then checked to ensure it's between the values 310 and 325 which are the versions that are supported by the application.

```
0x626b0f:
0x626b10:
                               %rbp
%rsp,%rbp
                     mov
0x626b13:
0x626b1a:
                               $0x180,%rsp
%rdi,-0x168(%rbp)
%rsi,-0x170(%rbp)
                     sub
                                                           ; document object
                     moν
0x626b21:
                     mov
                                                           ; FILE*
0x626b28:
0x626b2f:
                               %rdx,-0x178(%rbp)
%ecx,-0x17c(%rbp)
                                                           ; document path
; flags
                     mov
                     moν
0x626c3e:
                     mov
lea
                              $0xa,%edx
-0x130(%rbp),%rcx
-0x170(%rbp),%rax
                                                           ; length
; buffer
; FILE*
0x626c4a:
                     mov
0x626c51:
                     mov
                               %rcx,%rsi
0x626c54:
                               %rax,%rdi
                     mov
                                                           : [11] read 0xa bytes from file
0x626c57:
                     callq
                              0x62738a
0x626c5c:
                               %eax,%eax
0x626c5e:
                     sete
0x626c69:
                               -0x130(%rbp),%eax
$0x3141592d,%eax
                                                           ; [12] read uint32_t and check signature
0x626c6f:
                     cmp
0x626c74:
                     jе
                               0x626c98
0x626c98:
                     movzwl -0x12c(%rbp),%eax
                                                           ; [13] read uint16 t for major component of version
                     movzwl wax,%eax
imul $0x64,%eax,%edx
movzwl -0x12a(%rbp),%eax
0x626c9f:
0x626ca2:
                                                           : [13] read wint16 t for minor component of version
0x626ca5:
0x626cac:
0x626caf:
                     movzwl %ax,%eax
add %eax,%edx
0x626cb1:
0x626cb8:
                     mov
mov
                              -0x168(%rbp),%rax
%edx,0x38(%rax)
                                                           : [13] store version
0x626cbb:
                               -0x168(%rbp).%rax
                                                           : [14] read version
                     mov
0x626cc2:
0x626cc5:
                     mov
cmp
                               0x38(%rax),%eax
$0x136,%eax
                                                           ; [14] compare against 310
0x626cca:
                     jе
                               0x6272e2
0x626cd0:
                                -0x168(%rbp),%rax
                                                           ; [14] read version
                     mov
                     mov
cmp
jle
                               0x38(%rax),%eax
$0x145,%eax
0x626d03
0x626cd7:
                                                           ; [14] compare against 325
0x626cdf:
```

Once the version has been verified, the index table will be allocated. This is done at [15] by first reading the number of records from the 10-byte buffer, and then multiplying by 8. Afterwards the resulting size will be passed to the function call at [16] to round the size and allocate space for it. After the space for the index table has been successfully allocated, the call at [17] will read data from the file into it.

```
0x626d03 ·
                   movzwl -0x128(%rbp).%eax
                                                     : [15] read number of records from index header
0x626d0a:
                   movzwl %ax,%eax
0x626d0d:
                   mov
                            $0x8.%edx
                            %edx,%eax
%eax,-0x154(%rbp)
                                                      ; [15] multiply by 8
0x626d12
                    imul
0x626d15:
                            -0x154(%rbp),%edx
-0x168(%rbp),%rax
                                                      ; [16] use size
; document object
0v626d1h+
                   mov
0x626d21:
                   mov
0x626d28.
                   mov
                            %edx.%esi
0x626d2a:
0x626d2d:
                   mov %rax,%rdi
callq 0x1267124
                                                      ; [16] allocate space for index table
0x626d32:
                   mov
                            %rax,-0x150(%rbp)
                                                      ; allocated index table buffer
0x626d4c:
                            -0x154(%rbp),%edx
                                                     ; index table size
                   mov
0x626d52:
0x626d59:
0x626d60:
                            -0x150(%rbp),%rcx
-0x170(%rbp),%rax
                                                      ; index table buffer
; FILE*
                   mov
                   moν
                   mov
                            %rcx,%rsi
0x626d63:
0x626d66:
                           %rax,%rdi
0x62738a
                   mov
callq
                                                      ; [17] read index table into buffer
0x626d6b:
                   test
                            %eax,%eax
0x626d6d:
                            %al
                   sete
```

Once the index table has been allocated and read from the file, the following loop will be executed. This loop is responsible for scanning the index table for a record of type 0x0026. After initializing an index used to select the entry in the index table, at [18] the index will be compared with the number of elements in the index table in order to determine when the loop should exit. At [19], the type at the current index of the index table is loaded into the %eax register, and then compared against the value 0x0026. If the type of the entry corresponds to the value of 0x0026, then the record will be parsed at [20]. It is suspected by the author that this record type is used to extend the index record table.

```
0x626dfc:
                   movl $0x0,-0x15c(%rbp)
0x626e06:
                   movzwl -0x128(%rbp),%eax
                                                    ; number of elements in table
                   movzwl %ax,%eax
                   cmp
jle
                            -0x15c(%rbp),%eax
                                                    ; [18] check against current index into index table
0x626e10:
0x626e16:
                           0x626ec6
0x626e1c:
                           -0x15c(%rbp).%eax
                                                     : current index into index table
                   mov
0x626e22:
0x626e24:
                    cltq
                           0x0(,%rax,8),%rdx
0x626e2c:
                   mov
                            -0x150(%rbp),%rax
                                                     : index table buffer
0x626e33:
0x626e36:
                   add %rdx,%rax
movzwl (%rax),%eax
                                                     ; [19] read index record type
                   cmp
jne
0x626e39 ·
                           $0x26.%ax
                                                     ; [19] compare against 0x0026
0x626e3d:
                   mov -0x140(%rbp),%rax
movzwl 0x2(%rax),%eax
movzwl %ax,%esi
0x626e83:
                                                     ; current index record
; current index record size
0x626e8a:
0x626e8e:
                   mov
mov
0x626e91:
                           -0x170(%rbp),%rcx
                                                     ; FILE*
0x626e98:
0x626e9e:
                            -0x17c(%rbp),%edx
-0x168(%rbp),%rax
                                                    ; flag
; document object
                   mov
0x626ea5:
0x626ea8:
                   mov %rax,%rdi
callq 0x61feac
                                                     ; [20] read record 0x0026
0x626ead:
                   test
                            %eax,%eax
0x626eaf:
                           %al
                   sete
0x626eba:
                   addl
                           $0x1,-0x15c(%rbp)
0x626ec1:
                   jmpq
                            0x626e06
```

After scanning for record type 0x0026, the application will then enter the following loop. This loop will translate the record types in the index table by adding 2 to the record type. After initializing the index for the loop, at [21] the application will check this index against the total number of records to determine when the loop should be executed. For each index of the loop, the pointer to the current record will be calculated at [22]. Once a pointer to the current record has been determined, the loop will check if its type is larger than 0x000f at [23]. This will be used at [24] to determine whether the record type should be increased by +2.

```
0x626ee8:
                   movl $0x0,-0x158(%rbp)
                                                   ; index of current record
0x626ef2:
                   movzwl -0x128(%rbp),%eax
                                                   ; total number of records
                   movzwl %ax,%eax
cmp -0x158(%rbp),%eax
0x626ef9:
0x626efc:
                   cmp
jle
                                                   ; [21] check current index against total number of records
0x626f02:
                           0x626f55
0x626f04:
                           -0x158(%rbp).%eax
                   mov
                                                    : current index
0x626f0a:
                   cltq
                           0x0(,%rax,8),%rdx
0x626f0c:
                   lea
                                                    ; pointer to index table
0x626f14:
                   mov
                            -0x150(%rbp),%rax
                           %rdx,%rax
%rax,-0x138(%rbp)
0x626f1b:
                    hhs
0x626f1e:
                   mov
                                                    ; [22] calculate pointer to current record in index
                   mov -0x138(%rbp),%rax
movzwl (%rax),%eax
                                                   ; current record in index
; read uint16_t record type
0x626f25.
0x626f2c:
0x626f2f:
                   cmp
jbe
                            $0xf.%ax
                                                     ; [23] check type against 0x000f
0x626f33:
                            0x626f4c
                                                     ; current record in index
0x626f35:
                   mov
                            -0x138(%rbp),%rax
0x626f3c:
0x626f3f:
                   movzwl (%rax),%eax
lea 0x2(%rax),%edx
                                                     ; read uint16_t record type
; [24] add 2 to it
0x626f42:
0x626f49:
                            -0x138(%rbp),%rax
%dx,(%rax)
                                                     ; current record in index
; [24] write it back
                   moν
                           $0x1,-0x158(%rbp)
0x626ef2
0x626f4c:
0x626f53:
                   addl
                   jmp
```

Finally, the application will enter the following loop. This loop is responsible for scanning the index table for a list of record types in an array as a global. This is performed by two nested loops. The outermost loop iterates through each element in the aforementioned global array. This loop terminates at [25] by checking to see if the current loop's index is larger than 0x3a. The innermost loop is responsible for iterating through each record in the index table. Similar to the prior described loops, at [26] the outermost loop's index is checked against the total number of elements. At [27] a pointer is calculated to point to the current record in the index table. At [28], the type is read from the current record and then checked against the current element in the global array selected by the index of the outermost loop.

```
; initialize index for loop
0x626f55.
                 movl $0x0.-0x15c(%rbp)
0x626f5f:
                        -0x15c(%rbp),%eax
                 mov
                                                       : index for loop
0x626f65:
0x626f67:
                 cltq
mov
                         $0x3a,%edx
Ax626f6c.
                 cmp
jae
                        %rdx,%rax
0x627097
                                                       ; [25] check current index against 0x3a
0x626f6f:
0x626f75.
                 movl
                        $0x0,-0x158(%rbp)
                                                       ; initialize index for current record of table ; total number of records in table
0x626f7f:
0x626f86:
                          -0x128(%rbp),%eax
                 movzwl
                 movzwl %ax,%eax
0x626f89:
                         -0x158(%rbp),%eax
                                                       ; [26] check index for current record against total
0x626f8f:
0x626f95:
                 mov
cltq
                         -0x158(%rbp),%eax
                                                        ; index of current record in table
0x626f9b:
0x626f9d:
                        0x0(,%rax,8),%rdx
                 lea
0x626fa5:
                 mov
                          -0x150(%rbp),%rax
                                                       ; pointer to index table
0x626fac:
                 add
                         %rdx,%rax
                        %rax,-0x138(%rbp)
0x626faf:
                 mov
                                                       ; [27] calculate pointer to current record
0x626fb6:
                 mov
                          -0x138(%rbp),%rax
                                                        ; current record in table
                 movzwl (%rax).%edx
                                                        : [28] read type from index table record
0x626fbd:
0x626fc0:
0x626fc6:
                        -0x15c(%rbp),%eax
                                                       ; index for outer loop
                 cltq
                 movzwl 0x1ca43c0(%rax,%rax,1),%eax ; [28] index into global array
0x626fc8:
0x626fd0:
                 cmp
                        %ax,%dx
0x62707f
0x626fd3:
                 ine
0x62707f:
                 addl
                        $0x1,-0x158(%rbp)
                                                       ; next iteration for current record
0x627086:
                 jmpq
                        0x626f7f
0x62708b:
                 addl
                         $0x1,-0x15c(%rbp)
                                                       ; [25] next iteration for index into global
0x627092:
                 jmpq
                        0x626f5f
```

The table of record types that the index table is scanned can be found at the following address.

Once a record in the index table with a type corresponding to the current element in the global has been found, the following block of code is executed. The function call at [26] in the following code is directly responsible for parsing an individual record within the index table based on the record type extracted from the current record.

```
: parse record flag
0x627035:
                   mov
                            -0x17c(%rbp),%edi
0x62703b:
0x627042:
                   mov
                           -0x178(%rbp),%rcx
-0x170(%rbp),%rdx
-0x138(%rbp),%rsi
                                                     ; document path
; FILE*
                                                     ; current record in index table
0x627049:
                   mov
0x627050:
0x627057:
                            -0x168(%rbp),%rax
                   moν
                                                    ; document object
                   mov
                            %edi,%r8d
0x62705a:
                   mov
                           %rax.%rdi
0x62705d:
                   callq 0x624d1e
                                                     ; [26] parse record
0x627062:
                   test
                           %eax.%eax
0x627064:
                   sete
                           %al
```

After the prior-mentioned loops have scanned and discovered a record that corresponds to the type in the global array, the following function is executed. This function is responsible for reading the data associated with the record type and passing the data as a parameter to the function responsible for parsing it. At [27], the offset for the current record is read from the index table and then used to set the offset for the current file stream containing the document. Then at [28], the 16-bit record type is read from the current index table record and used to determine the case responsible for parsing the record type.

```
0x624d1e •
                       nush
0x624d1f:
                       mov
                                  %rsp,%rbp
0x624d22:
                       sub
                                  $0x160.%rsp
                       mov
mov
                                  %rdi,-0x138(%rbp)
%rsi,-0x140(%rbp)
                                                                 ; document object
; current record in index table
0x624d29:
0x624d30:
                                                                 ; FILE*
                                 %rdx,-0x148(%rbp)
%rcx,-0x150(%rbp)
%r8d,-0x154(%rbp)
0x624d37 ·
                       mov
0x624d3r:
0x624d3e:
0x624d45:
                                                                ; document path
; parse record flag
                       mov
0x624d69:
0x624d70:
                                   -0x118(%rbp),%rax
                                                                 ; current record in index table ; [27] uint32_t offset of record
                                  0x4(%rax),%eax
                       moν
                                  %eax,%ecx
-0x148(%rbp),%rax
$0x0,%edx
                       mov
mov
0x624d73:
0x624d75:
0x624d7c:
                                                                 ; SEEK_SET
                       mov
                       mov %rcx,%rsi
mov %rax,%rdi
callq 0x410fe0 <fseek@plt> ; [27] seek to offset
0x624d81:
0x624d84:
0x624d87:
0x624d8c:
0x624d93:
                       mov -0x118(%rbp),%rax
movzwl (%rax),%eax
                                                              ; current record in index table
; [28] uint16_t record type
0x624d96:
0x624d99:
                       movzwl %ax,%eax
cmp $0x43,%eax
0x624d9c:
                       ia
                                  0x625f7f
0x624da2:
                       mov
                                  %eax,%eax
0x16ba520(,%rax,8),%rax
0x624da4:
                       mov
                                                                ; [28] branch to case responsible for record type
0x624dac:
                       jmpq
                                 *%rax
```

```
-0x148(%rbp),%rdx
-0x138(%rbp),%rax
                                                 : FILF*
0x625h78 ·
                 mov
0x625b7f:
                 mov
                                                 ; document object
0x625b86:
                 mov
                         %rdx.%rsi
0x625h89
                         %rax %rdi
0x625b8c:
                 callq 0x62183e
                                                 ; [29] handle record 0x002a
0x625h91 ·
                 test
                         %eax.%eax
0x625b93:
                         %al
```

The following function is then entered and is directly responsible for parsing records with the type of 0x002a. When this function is entered, it is assumed that the stream that was passed as a parameter is presently pointing at the data representing the record's contents. At [30], the function will read 32-bits from the file and store it onto the stack. This will later be used as a length when allocating space on the heap. At [31], the function will then validate that the length is non-zero.

```
0x62183e:
                 push
                         %rbp
0x62183f:
0x621842:
                 mov
push
                         %rsp,%rbp
%r12
0x621844:
                 push
                         %rbx
                         $0x1e0,%rsp
%rdi,-0x1e8(%rbp)
0x621845:
                  sub
                                                 ; document object
0x62184c:
                 mov
                                                 : FILE*
0x621853:
                 mov
                         %rsi,-0x1f0(%rbp)
0x6218c4:
                         -0x1e0(%rbp),%rcx
                 lea
                                                 : result
0x6218cb:
                 mov
                          -0x1f0(%rbp),%rax
                                                 : FILE*
0x6218d2:
                          $0x4,%edx
                 mov
                                                 ; length
0x6218d7:
                 mov
                         %rcx,%rsi
0x6218da:
                 mov
                         %rax.%rdi
0x6218dd:
                 callq
                         0x62738a
                                                 ; [30] fread
0x6218e2:
                  test
                         %eax,%eax
0x6218e4:
                 sete
                         %a1
0x6218ef:
                          -0x1e0(%rbp),%eax
                 mov
                         %eax,%eax
0x621f88
0x6218f5:
                                                 ; [31] check nonzero
0x6218f7:
                 jе
```

Immediately following the validation of the length, the function will take this 32-bit length and multiply it by the value of 0x23c at [32]. Due to the length being a total of 32-bits and its operand of up to 10-bits, this multiplication can overflow resulting in the allocation being of a smaller size than expected. Once the result of the multiplication has been obtained, it is then truncated to 32-bits and then passed to the function call at [33] which is responsible for allocating space from the heap. At [34], the original length that was used prior the multiplication containing the integer overflow is then stored into a variable on the stack.

```
0x6218fd:
                             $0x23c,%edx
                                                       ; multiplication operand
                    moν
                                                       ; uint32_t
; [32] multiplication
0x621902:
                             -0x1e0(%rbp),%eax
0x621908:
0x62190b:
                             %edx,%eax
$0x1,%esi
                    imul
                    mov
                            %eax,%edi
0xc483ec
%rax,-0x174(%rbp)
0x621910:
0x621912:
                    callq
                                                       ; [33] allocation
                                                       ; store pointer to allocation
0x621917:
                    mov
                            -0x1e0(%rbp),%eax
%eax,-0x178(%rbp)
0x62191e:
                                                       ; [34] original length
                    moν
0x621924:
                    mov
```

The original length that was stored on the stack is then treated by the function as a terminator for the following loop. This loop is used to treat the space allocated on the heap as an array and will terminate at [35] by comparing the loop's index against the original length. In order to write directly into the correct element of the array, the application will take the current index and multiply it by the array element's size at [36]. This calculation will result in a pointer that is targeting the particular element. At this point for each iteration of the loop, file data will be read into this target pointer depending on the document's version which is checked at [37].

```
0x621938: movl $0x0.-0x1d8(%rbn)
                                             ; index
0x621942:
                           -0x1d8(%rbp),%edx
                  mov
                                                   ; index
; [35] sentinel
                  mov
cmp
0x621948:
                           -0x1e0(%rbp),%eax
0x62194e:
0x621950:
                  jae
                          0x621cf9
0×621956:
                  mov
                          -0x174(%rbp),%rdx
                                                   ; heap buffer
0x62195d:
                  mov
                          -0x1d8(%rbp).%eax
                                                   : index
0x621963 ·
                   clta
0x621965:
                          $0x23c,%rax,%rax
                                                  ; multplication by 0x23c
0x62196c:
                  add
                          %rdx,%rax
%rax,-0x1b8(%rbp)
0x62196f:
                  mov
                                                  ; [36] calculate pointer into heap buffer
0x621976 ·
                           -0x1e8(%rhn), %rax
                  mov
                                                   : document object
0x62197d:
0x621980:
                  mov
cmp
                          0x38(%rax),%eax
$0x13a,%eax
                                                   ; document version
; [37] compare document version
0x621985:
                  jg
                          0x621b22
0x621ce0:
                      $0x0,%eax
0x621ce5:
0x621ce7:
              test
                      %al,%al
                      0x62205a
$0x1,-0x1d8(%rbp)
              jne
addl
                                              ; index
0x621ced:
0x621cf4:
                      0x621942
```

If the document version is earlier than 314, the following case will be executed. This case is executed for each iteration of the loop, and will read 0x122 bytes from the file into a buffer on the stack at [38]. After the data has been read, it will then be written into the array that was allocated using the previously calculated pointer. This occurs in many places as highlighted at [38]. Due to the previously mentioned integer overflow, these stores can be used to write outside the bounds of the allocated array which can trigger heap corruption leading to a heap-based overflow. This can grant an attacker a path to earn code execution with the privileges of the application.

```
$0x122,%edx
-0x140(%rbp),%rcx
                                                        ; length
; buffer on stack
0x62198h ·
0x621990:
                     lea
                              -0x1f0(%rbp),%rax
0x621997:
                    mov
                                                        : FILE*
                    mov
mov
                             %rcx,%rsi
%rax,%rdi
0x62199e
0x6219a1:
0x6219a4 ·
                    callq
                             0x62738a
                                                        · [38] fread
0x6219a9:
0x6219ab:
                    test
                             %eax,%eax
%al
                              -0x140(%rbp),%edx
-0x1b8(%rbp),%rax
0x6219b6:
                                                        ; pointer into heap buffer
0x6219bc:
                    mov
0x6219c3:
                    mov
                             %edx,(%rax)
                                                        ; [39] store to array element
0x6219c5:
                             -0x28(%rbp),%edx
                    mov
0x6219c8:
0x6219cf:
                             -0x1b8(%rbp),%rax
%edx,0x21c(%rax)
                                                        ; pointer into heap buffer ; [39] store to array element
                     mov
                    moν
0x6219d5:
0x6219d8:
                              -0x24(%rbp),%edx
-0x1b8(%rbp),%rax
                                                        ; pointer into heap buffer
                    moν
0x6219df:
                    mov
                             %edx,0x220(%rax)
                                                        ; [39] store to array element
0x6219e5:
                    movzwl -0x20(%rbp),%edx
                                                        : pointer into heap buffer
0x6219e9:
                    mov
                              -0x1b8(%rbp),%rax
0x6219f0:
                             %dx,0x224(%rax)
                                                        ; [39] store to array element
0x6219f7:
                    movzwl -0x13c(%rbp).%edx
                             -0x1b8(%rbp),%rax
%dx,0x4(%rax)
0x6219fe:
                                                        ; pointer into heap buffer
                                                        ; [39] store to array element
0x621a05:
                    mov
0x621a09:
                    movzwl -0x13a(%rbp),%eax
                    movzwl %ax,%edx
mov -0x1b8(%rbp),%rax
0x621a10:
0x621a13:
                                                        ; pointer into heap buffer
0x621a1a:
                             %edx,0x6(%rax)
                                                        ; [39] store to array element
                    mov
0x621a1d:
                    movzwl -0x138(%rbp),%edx
mov -0x1b8(%rbp),%rax
                                                        : [39] store to array element
0x621a2b:
                    mov
                             %dx.0xa(%rax)
0x621a2f:
                    movzwl -0x136(%rbp),%edx
0x621a36:
0x621a3d:
                             -0x1b8(%rbp),%rax
%dx,0xc(%rax)
                                                        ; pointer into heap buffer ; [39] store to array element
0x621a41:
                             -0x134(%rbp),%edx
-0x1b8(%rbp),%rax
%edx,0xe(%rax)
                    mov
0x621a47:
0x621a4e:
                    mov
mov
                                                        ; pointer into heap buffer
; [39] store to array element
                             -0x130(%rbp),%edx
-0x1b8(%rbp),%rax
0x621a51:
                    mov
                                                        ; pointer into heap buffer
0x621a57:
                    mov
0x621a5e:
                    mov
                             %edx,0x12(%rax)
                                                        ; [39] store to array element
0x621a61:
                              -0x12c(%rbp),%edx
                    mov
0x621a67:
0x621a6e:
                             -0x1b8(%rbp),%rax
%edx,0x16(%rax)
                                                        ; pointer into heap buffer ; [39] store to array element
```

If the document's version was later than 314, then the following code would be executed. This condition is different from the earlier version in that at [40], the application will read 0x228 bytes of data directly into the heap buffer. Similar to the implementation on earlier document versions, at [41] the application will write to a number of places that can also trigger heap corruption by writing outside the bounds of the array that was allocated. This is a heap overflow and with more work can enable an attacker to earn code execution.

```
0x621b22:
                 mov
                        $0x228.%edx
                                               : length
                         -0x1b8(%rbp),%rcx
-0x1f0(%rbp),%rax
0x621b27:
                 mov
                                               ; pointer into heap buffer ; FILE*
0x621b2e:
                 mov
0x621h35.
                 mov
                        %rcx.%rsi
0x621b38:
                        %rax,%rdi
                 mov
                                               : [40] fread
0x621b3b:
                 callq
                        0x62738a
0x621b40:
                 test
                        %eax,%eax
0x621b42:
                        %al
                 sete
0x621c2a:
                 mov
                        -0x1b8(%rbp),%rax
0x621c31:
                        %rdx,0x228(%rax)
                                               ; [41] store to array element
                 mov
0x621c87:
                 mov
                        -0x1b8(%rbp),%rax
                        %rdx,0x234(%rax)
                                               ; [41] store to array element
0x621c8e:
                mov
```

Crash Information

This output starts out by setting a breakpoint at the allocation. Emitting its parameter shows the length that was read from the file. After the integer overflow that occurs during the multiply, the result is 0x20c which providers an undersized allocation that will later be written to.

```
(gdb) bp 0x621912
Breakpoint 4 at 0x621912

(gdb) r
Starting program: /usr/share/office2021/textmaker poc.tmd
[Thread debugging using libthread_db enabled]
Using host libthread_db library "/lib/x86_64-linux-gnu/libthread_db.so.1".
...
Thread 1 "textmaker" hit Breakpoint 4, 0x000000000000000112 in ?? ()

(gdb) x/7i 0x6218fd
0x6218fd: mov $0x23c,%edx
0x621962: mov -0x1e0(%rbp),%eax
0x621908: imul %edx,%eax
0x621908: imul %edx,%eax
0x621910: mov %eax,%edi
>0x621910: mov %eax,%edi
>0x621911: callq 0xc483ec
0x621917: mov %rax,-0x174(%rbp)
(gdb) p/x *(int*)($rbp-0x1e0)
$2 = 0x7292cd
(gdb) i r $rdi
rdi 0x20c 0x20c
(gdb) p/x *(int*)($rbp-0x1e0) * 0x20c
(gdb) p/x *(int*)($rbp-0x1e0) * 0x20c
(gdb) p/x *(int*)($rbp-0x1e0) * 0x20c
(gdb) i r $rax
rax 0x2fe12c0 0x2fe12c0
```

The following output shows the index being used to calculate an index into the undersized allocation that was just recently mentioned.

```
(gdb) bp 0x62196f
Breakpoint 5 at 0x62196f
(gdb) c
Continuing.

Thread 1 "textmaker" hit Breakpoint 5, 0x000000000062196f in ?? ()
(gdb) x/6i 0x621956
0x621956: mov -0x174(%rbp),%rdx
0x621956: mov -0x164(%rbp),%eax
0x621956: i mov -0x168(%rbp),%eax
0x621963: cltq
0x621965: imul $0x23c,%rax,%rax
0x621965: imul $0x23c,%rax,%rax
0x621966: mov %rax,-0x1b8(%rbp)
(gdb) p/x *(int*)($rbp-0x1d8)
$5 = 0x0
(gdb) i r $rax
rax 0x2fe12c0 0x2fe12c0
```

The following output shows the call to fread(3) which is reading 0x228 bytes of data into the previously calculated pointer. This pointer results in 0x228 bytes of data being written outside the bounds of an allocation that is only 0x20c bytes in size.

After 0x228 bytes have been read into a 0x20c-byte heap chunk, if we continue execution we can see that the heap has been corrupted.

Timeline

2020-10-08 - Vendor Disclosure 2020-12-03 - Follow up with vendor 2021-01-05 - 2nd follow up; vendor acknowledged issues fixed 2021-01-05 - Public Release

CREDIT

Discovered by a member of Cisco Talos.

VULNERABILITY REPORTS PREVIOUS REPORT NEXT REPORT

TALOS-2020-1162 TALOS-2020-1185

© 2022 Cisco Systems, Inc. and/or its affiliates. All rights reserved. View our Privacy Policy.