



GBase 8s 安装手册



GBase 8s 安装手册，南大通用数据技术股份有限公司

GBase 版权所有©2004-2030，保留所有权利

版权声明

本文档所涉及的软件著作权及其他知识产权已依法进行了相关注册、登记，由南大通用数据技术股份有限公司合法拥有，受《中华人民共和国著作权法》、《计算机软件保护条例》、《知识产权保护条例》和相关国际版权条约、法律、法规以及其它知识产权法律和条约的保护。未经授权许可，不得非法使用。

免责声明

本文档包含的南大通用数据技术股份有限公司的版权信息由南大通用数据技术股份有限公司合法拥有，受法律的保护，南大通用数据技术股份有限公司对本文档可能涉及到的非南大通用数据技术股份有限公司的信息不承担任何责任。在法律允许的范围内，您可以查阅，并仅能够在《中华人民共和国著作权法》规定的合法范围内复制和打印本文档。任何单位和个人未经南大通用数据技术股份有限公司书面授权许可，不得使用、修改、再发布本文档的任何部分和内容，否则将视为侵权，南大通用数据技术股份有限公司具有依法追究其责任的权利。

本文档中包含的信息如有更新，恕不另行通知。您对本文档的任何问题，可直接向南大通用数据技术股份有限公司告知或查询。

通讯方式

南大通用数据技术股份有限公司

天津市高新区开华道22号普天创新产业园东塔20-23层

电话：400-013-9696

邮箱：info@gbase.cn

商标声明

GBASE[®] 是南大通用数据技术股份有限公司向中华人民共和国国家商标局申请注册的注册商标，注册商标专用权由南大通用数据技术股份有限公司合法拥有，受法律保护。未经南大通用数据技术股份有限公司书面许可，任何单位及个人不得以任何方式或理由对该商标的任何部分进行使用、复制、修改、传播、抄录或与其它产品捆绑使用销售。凡侵犯南大通用数据技术股份有限公司商标权的，南大通用数据技术股份有限公司将依法追究其法律责任。

目 录

1 安装环境检查.....	1
1.1 硬件要求.....	1
1.2 系统要求.....	1
2 安装说明.....	1
3 一键安装.....	1
3.1 上传并解压安装包.....	2
3.2 安装配置文件说明.....	2
3.3 执行一键安装脚本.....	2
4 手动安装.....	6
4.1 创建gbasedbt用户.....	6
4.2 创建安装目录.....	7
4.3 上传并解压安装包.....	7
4.4 执行安装.....	7
4.5 创建和初始化实例.....	15
4.5.1 脚本自动创建和初始化实例.....	15
4.5.2 手动创建和初始化实例.....	18
5 典型安装.....	20
6 静默安装.....	23
7 数据库的简单使用.....	23
7.1 启动/停止数据库服务.....	23
7.2 登录数据库.....	25
7.3 创建数据库.....	25
8 数据库的卸载.....	25

1 安装环境检查

1.1 硬件要求

硬件	最低配置	推荐配置
处理器	1×2 核 2.0GHz	4×4 核 3.0GHz
内存	4GB	64GB 或更多
硬盘	100GB	1TB
光驱	CD-ROM	CD-ROM

1.2 系统要求

GBase 8s 产品支持多种处理器平台，除国际主流的 x86_64 处理器（包括 Intel 和 AMD）外，全面支持飞腾、鲲鹏、龙芯、兆芯、海光、申威等国产处理器。

GBase 8s 产品可以运行于多款操作系统，包括：RHEL和CentOS等广泛应用的Linux操作系统，统信UOS、麒麟、欧拉等国产操作系统。

您的系统需要安装以下软件包，如果缺失请提前安装：

- tar
- jdk
- libaio
- libgcc
- libstdc
- ncurses
- pam
- unzip
- compat-libstdc
- libtinfo

2 安装说明

GBase 8s 安装方式分为一键安装、手动安装、典型安装和静默安装4种。一键安装适用于普通用户，操作简单，无需太多人工干预。手动安装适用于管理员，提供了更多的灵活性和可操作性。典型安装适用于小功能测试，不推荐应用使用。静默安装适用于嵌入式，在应用中嵌入安装命令即可完成安装。根据需求选择一种安装方式即可。

3 一键安装

一键安装是通过执行安装脚本，完成 GBase 8s 数据库软件的安装及实例的初始化配置。

3.1 上传并解压安装包

以GBase8sV8.8_TL_3.6.2_2_ddbbf5_RHEL6_x86_64.tar版本的安装包为例，将安装包文件复制到/opt/GBase目录下，并执行tar -vxf

GBase8sV8.8_TL_3.6.2_2_ddbbf5_RHEL6_x86_64.tar 命令完成解压。

```
[root@localhost ~]# cd /opt/GBase
[root@localhost GBase]# tar -vxf GBase8sV8.8_TL_3.6.2_2_RHEL6_x86_64.tar

drwxr-xr-x 2 root root      4096 Jan 17 13:13 doc
-rw----- 1 root root 350617600 Feb 12 17:51
GBase8sV8.8_TL_3.6.3_2_561324_RHEL6_x86_64.tar
-rwxr-xr-x 1 root root      1035 Jan 17 13:21 .gbase.properties
-rwxr-xr-x 1 root root 350417134 Jan 17 13:21 ids_install
-rw-r--r-- 1 root root      1864 Jan 17 13:21 ids.properties
-rwxr-xr-x 1 root root      82770 Jan 17 13:21 onsecurity
drwxr-xr-x 2 root root      4096 Mar  7 14:21 PluginPak
```

3.2 执行一键安装脚本

```
[root@localhost ~]# cd PluginPak
[root@localhost PluginPak]# sh install_init.sh
[2025-02-24 17:44:37] GBase8s software One-click automatic
installation start [info]
[2025-02-24 17:44:37] Check gbase8s installtion environment [info]
[2025-02-24 17:44:37] Check the system tools required to install
gbase8s database [info]
[2025-02-24 17:44:37] Check the system tools required to install
gbase8s database [ok]
[2025-02-24 17:44:37] Check the system libs required to install
gbase8s database [info]
[2025-02-24 17:44:37] Check the system libs required to install
gbase8s database [ok]
[2025-02-24 17:44:37] Check gbase8s installtion environment
[successful]
[2025-02-24 17:44:37] Install the gbase8s database software, this will
take a moment... [info]
[2025-02-24 17:45:56] Install the gbase8s database software...
[successful]
[2025-02-24 17:45:56] Execute database server oninit, this will take
a moment... [info]
```

```
[2025-02-24 17:46:32] Creating system database
[2025-02-24 17:47:43] Instance initialization... [successful]
[2025-02-24 17:47:43] Database statistics are being generated, this
will take a moment... [info]
[2025-02-24 17:47:43] Collecting instance information starts [info]
[2025-02-24 17:47:43] Information is retained about 10 days [info]
[2025-02-24 17:47:43] Current environment variables is
/home/gbasedbt/.bash_profile [info]
[2025-02-24 17:47:43] Delete files which 10 days ago [info]
[2025-02-24 17:47:43] Collecting stats...(should take about 2
minutes) [info]
[2025-02-24 17:48:00] Stats stored in stats.20250224-1747 [info]
[2025-02-24 17:48:00] Collecting instance information [successful]
[2025-02-24 17:48:00] Collect post-installation Instance information
[successful]
[2025-02-24 17:48:00] Collecting installation information starts
[info]
[2025-02-24 17:48:00] Information is retained about 10 days [info]
[2025-02-24 17:48:00] Current environment variables is
/home/gbasedbt/.bash_profile [info]
[2025-02-24 17:48:00] Delete files which 10 days ago [info]
[2025-02-24 17:48:00] Delete files which 10 days ago [ok]
[2025-02-24 17:48:00] Start collecting..... [info]
[2025-02-24 17:48:19] Start collecting..... [ok]
[2025-02-24 17:48:19] Collecting installation information
[successful]
[2025-02-24 17:48:19] Collect post-installation environment
information [successful]
[2025-02-24 17:48:22]
#####
#####
[2025-02-24 17:48:22] Installation
Information
[2025-02-24 17:48:22]
[2025-02-24 17:48:22] USER_OS_NAME: gbasedbt
[2025-02-24 17:48:22] USER_OS_PWD: GBase@123
[2025-02-24 17:48:22] HOMEDIR: /home/gbasedbt
[2025-02-24 17:48:22] GBASEDBTSERVER: gbase01
```

```
[2025-02-24 17:48:22] PROFILE_NAME: profile.gbase01
[2025-02-24 17:48:22] SQLHOSTS_NAME: sqlhosts.gbase01
[2025-02-24 17:48:22] ONCONFIG_NAME: onconfig.gbase01
[2025-02-24 17:48:22] GBASEDBTDIR: /opt/gbase8s
[2025-02-24 17:48:22] IPADDRESS: 0.0.0.0
[2025-02-24 17:48:22] PORT: 9088
[2025-02-24 17:48:22] DB_LOCALE: zh_CN.utf8
[2025-02-24 17:48:22] CLIENT_LOCALE: zh_CN.utf8
[2025-02-24 17:48:22] CHUNK_DIR: /opt/gbase8s/datafile
[2025-02-24 17:48:22] CHUNK_TOTAL_SIZE: 5120 (MB)
[2025-02-24 17:48:22] SHM_TOTAL_SIZE: 786 (MB)
[2025-02-24 17:48:22] INSTALL_LOG_DIR:
/opt/gbase8s/logs/install_gbase01.log
[2025-02-24 17:48:22] JDBC_URL:
jdbc:gbasedbt-sqli://0.0.0.0:9088/gbasedb:GBASEDBTSERVER=gbase01
[2025-02-24 17:48:22]
#####
#####
[2025-02-24 17:48:22]
[2025-02-24 17:48:22] Congratulations! GBase Software installation
is successfully in 2025-02-24 17:48:22
[2025-02-24 17:48:22]
[2025-02-24 17:48:22] Product install status:
[2025-02-24 17:48:22] 1)GBase8s V8.8: Successful
[2025-02-24 17:48:22] 2)GBase Connect: Successful
[2025-02-24 17:48:22]
[2025-02-24 17:48:22] For more information about using GBase products,
see the GBase Information Center at https://www.gbase.cn
/community/section/10
```

3.3 安装配置文件说明

init.ini 文件中定义了安装时的配置参数，用户可以根据自己的安装需求和硬件环境进行调整。

```
#####
#####
# 数据库服务器参数配置
# 当前的配置文件允许您自定义关于安装数据库服务器的参数，如果您不修改当前的参数
配置，那么我
```

```

# 们将用默认参数安装配置数据库服务器
#####

#####

# 数据库基本参数配置
#####
#####
# USER_OS_PWD          - 该参数表示系统级用户 gbasedbt 的密码，缺省为
“GBase@123”，如果您想自定义，请确保含有数字、大小写字母、符号
# HOMEDIR              - 该参数表示系统级用户 gbasedbt 的家目录，缺省为
“/home/gbasedbt”
# GBASEDBTSERVER       - 该参数表示数据库实例名，缺省为 “gbase01”，如果您
想自定义，请确保至少包含字母或包含字母和数字，并且字母必须置于首位
# IPADDRESS            - 该参数表示提供数据库相关服务的 IP 地址，缺省为
“0.0.0.0”
# PORT                - 该参数表示提供数据库相关服务的端口，缺省为 “9088”
# GBASEDBTDIR          - 该参数表示数据库安装路径，缺省为 “/opt/gbase8s”
# CLIENT_LOCALE        - 该参数表示数据库客户端字符集，缺省为 “zh_CN.utf8”
# DB_LOCALE            - 该参数表示数据库的字符集，缺省为 “zh_CN.utf8”，可以
设置范围如下：
#                      en_US.819 等，具体其他字符集是否支持，设置前可以咨询管
理员
# SERVERNUM           - 该参数表示 GBase 实例的唯一 ID。可接受的值是[0,255]，
缺省为 “0”
#####
#####
USER_OS_PWD=GBase@123
HOMEDIR=/home/gbasedbt
GBASEDBTSERVER=gbase01
IPADDRESS=0.0.0.0
PORT=9088
GBASEDBTDIR=/opt/gbase8s
CLIENT_LOCALE=zh_CN.utf8
DB_LOCALE=zh_CN.utf8
SERVERNUM=0
#####
#####
# 服务器效率参数配置
#####
#####
# SHM_SIZE             - 该参数表示安装数据库所占用的内存，缺省为 0，表示定义为
可用内存的 1/4。

```



```

# 如果您想自定义，请保持定义值大于等于 512，单位为“MB”
# CHUNK_SIZE - 该参数表示安装数据库所需要的可用的磁盘空间，缺省为
5120。如果您想自定义，请确保输入大于等于 5120 的整数，并且小于
CHUNK_MAX_SIZE，单位为“MB”
# CHUNK_DIR - 该参数表示存储 chunk 的路径，缺省为
“/opt/gbase8s/datafile”
# CPU_VPS - 该参数表示 GBase 占用的 CPU 核数，缺省为 0，表示逻辑
CPU-1，如果计算结尾为
# 0，则缺省值含义为 1，如果您想自定义确保该值为小于 CPU 核
数的正整数
# CHUNK_MAX_SIZE - 该参数表示数据库所有 chunk 的极值，包括自动扩展值，缺
省是 51200。0 表示
# 无限制，如果您想自定义，确保输入值为大于 CHUNK_SIZE 的
整数，单位为“MB”
#####
#####
SHM_SIZE=0
CHUNK_SIZE=5120
CHUNK_DIR=/opt/gbase8s/datafile
CPU_VPS=0
CHUNK_MAX_SIZE=51200
#####
#####
# 服务器特殊参数配置
#####
#####
# DB_SERVICE - 该参数表示是否需要安装数据库的系统级服务，缺省为 0
# 0 表示不需要安装
# 1 表示安装但是不设置开机自启功能
# 2 表示安装并且设置开机自启
# 执行命令 :service gbase8s
start|stop|status|restart
#####
#####
DB_SERVICE=0

```

4 手动安装

4.1 创建gbasedbt用户

GBase 8s数据库需要一个名为gbasedbt的操作系统用户，做为数据库的超级用户。我们在安装前，需要创建好这个用户。

检查gbasedbt用户是否存在：

```
[root@localhost ~]# cat /etc/passwd | grep gbasedbt
[root@localhost ~]#
```

检查gbasedbt用户组是否存在：

```
[root@localhost ~]# cat /etc/group | grep gbasedbt
[root@localhost ~]#
```

若系统不存在相关组及用户，则需要创建。以root用户登录系统，执行如下命令创建gbasedbt 组和 gbasedbt 用户：

```
[root@localhost ~]# groupadd gbasedbt
[root@localhost ~]# useradd -g gbasedbt gbasedbt
```

执行如下命令为 gbasedbt 用户设置密码，建议设置相对复杂的密码：

```
[root@localhost ~]# passwd gbasedbt1234
```

4.2 创建安装目录

GBase 8s 数据库缺省的安装目录为 /opt/GBASE/gbase，您也可以自定义安装目录，安装目录必须为空。以缺省的安装目录为例，创建目录并修改属主为gbasedbt。

```
[root@localhost ~]# mkdir -p /opt/GBASE/gbase
[root@localhost ~]# chown gbasedbt:gbasedbt /opt/GBASE/gbase
```

4.3 上传并解压安装包

以GBase8sV8.8_AEE_3.5.1_3_6a4e30_RHEL6_x86_64.tar版本的安装包为例，将安装包文件复制到/opt目录下，并执行tar -vxf

GBase8sV8.8_AEE_3.5.1_3_6a4e30_RHEL6_x86_64.tar 命令完成解压。

```
[root@localhost ~]# cd /opt
[root@localhost opt]# tar -vxf
GBase8sV8.8_AEE_3.5.1_3_6a4e30_RHEL6_x86_64.tar
ids_install
onsecurity
doc/
ids.properties
.gbase.properties
```

4.4 执行安装

以 root 身份登录，进入解压目录，执行要安装的产品的安装脚本 ids_install，即可进行安装，具体命令如下：

```
[root@localhost /]# cd /opt
[root@localhost opt]# sh ids_install
```

执行安装过程中，安装程序先检查系统环境，如果系统没有安装JDK，那么安装包会先解压JDK，自动安装到系统中。如果已经安装，那么将显示产品的授权条款，回车依次查看全部的版权条款，最后确认是否接受这些版权条款。输入”Y”接受授权条款，按回车

键即可继续。

具体安装过程示例如下：

```
[root@localhost opt]# sh ids_install
Preparing to install...
Extracting the JRE from the installer archive...
Unpacking the JRE...
Extracting the installation resources from the installer archive...
Configuring the installer for this system's environment...

Launching installer...

=====
GBase Software Bundle                                (created with InstallAnywhere)
=====

Preparing CONSOLE Mode Installation...

=====
Getting Started
=====

This application will guide you through the installation of GBase Software
Bundle.
Copyright General Data Corporation 2014, 2019. All rights reserved.

1. Release Notes
The Release Notes can be found in /opt/doc/ids_unix_relnotes_12.10.html.
2. Launch Information Center
Access the GBase Information Center at http://www.gbase.cn.
To Begin Installation, respond to each prompt to proceed to the next step in
the installation.
If you want to change something on a previous step, type 'back'.
You may cancel this installation at any time by typing 'quit'.
PRESS <ENTER> TO CONTINUE:

=====
License Agreement
=====

Installation and Use of GBase 8s Software Bundle Requires Acceptance of
the Following License Agreement:

Thank you for choosing GBase product!

Please read carefully the following licencing agreement before installing any
product: TIANJIN GENERAL DATA TECHNOLOGY CO. LTD. LICENSE AGREEMENT

READ THE TERMS OF THIS AGREEMENT AND ANY PROVIDED SUPPLEMENTAL LICENSETERMS
(COLLECTIVELY "AGREEMENT") CAREFULLY BEFORE OPENING THE SOFTWAREMEDIA PACKAGE.
BY OPENING THE SOFTWARE MEDIA PACKAGE, YOU AGREE TO THE TERMS OF THIS
AGREEMENT. IF YOU ARE ACCESSING THE SOFTWARE ELECTRONICALLY, INDICATE YOUR
ACCEPTANCE OF THESE TERMS. IF YOU DO NOT AGREE TO ALL THESE TERMS, PROMPTLY
RETURN THE UNUSED SOFTWARE TO YOUR PLACE OF PURCHASE FOR A REFUND.

1. LICENSE TO USE. GeneralData grants you a non-exclusive and non-transferable
license for the internal use only of the accompanying software and
documentation and any error corrections provided by GeneralData(collectively
"Software"), by the number of users and the class of computer hardware for
which the corresponding fee has been paid.
```

2. RESTRICTIONS. Software is confidential and copyrighted. Title to Software and all associated intellectual property rights is retained by GeneralData and/or its licensors. Except as specifically authorized in any Supplemental License Terms, you may not make copies of Software, other than a single copy of Software for archival purposes. Unless enforcement is prohibited by applicable law, you may not modify, decompile, or reverse engineer Software. You acknowledge that Software is not designed, licensed or intended for use in the design, construction, operation or maintenance of any nuclear facility. GeneralData disclaims any express or implied warranty of fitness for such uses. No right, title or interest in or to any trademark, service mark, logo or trade name of GeneralData or its licensors is granted under this Agreement.

3. DISCLAIMER OF WARRANTY. Unless specified in this agreement, all express or implied conditions, representations and warranties, including any implied warranty of merchantability, fitness for a particular purpose or non-infringement are disclaimed, except to the extent that these disclaimers are held to be legally invalid.

4. LIMITATION OF LIABILITY. To the extent not prohibited by law, in no event will GeneralData or its licensors be liable for any lost revenue, profit or data, or for special, indirect, consequential, incidental or punitive damages, however caused regardless of the theory of liability, arising out of or related to the use of or inability to use software, even if GeneralData has been advised of the possibility of such damages. In no event will GeneralData's liability to you, whether in contract, tort (including negligence), or otherwise, exceed the amount paid by you for Software under this Agreement. The foregoing limitations will apply even if the above stated warranty fails of its essential purpose.

5. TERMINATION. This Agreement is effective until terminated. You may terminate this Agreement at any time by destroying all copies of Software. This Agreement will terminate immediately without notice from GeneralData if you fail to comply with any provision of this Agreement. Upon Termination, you must destroy all copies of Software.

6. EXPORT REGULATIONS. All Software and technical data delivered under this Agreement are subject to US export control laws and may be subject to export or import regulations in other countries. You agree to comply strictly with all such laws and regulations and acknowledge that you have the responsibility to obtain such licenses to export, re-export, or import as may be required after delivery to you.

7. CHINESE GOVERNMENT RESTRICTED. If Software is being acquired by or on behalf of the Chinese Government, then the Government's rights in Software and accompanying documentation will be only as set forth in this Agreement.

8. GOVERNING LAW. Any action related to this Agreement will be governed by Chinese law: "COPYRIGHT LAW OF THE PEOPLE'S REPUBLIC OF CHINA", "PATENT LAW OF THE PEOPLE'S REPUBLIC OF CHINA", "TRADEMARK LAW OF THE PEOPLE'S REPUBLIC OF CHINA", "COMPUTER SOFTWARE PROTECTION REGULATIONS OF THE PEOPLE'S REPUBLIC OF CHINA". No choice of law rules of any jurisdiction will apply."

9. SEVERABILITY. If any provision of this Agreement is held to be unenforceable, this Agreement will remain in effect with the provision omitted, unless omission would frustrate the intent of the parties, in which case this Agreement will immediately terminate.

10. INTEGRATION. This Agreement is the entire agreement between you and GeneralData relating to its subject matter. It supersedes all prior or contemporaneous oral or written communications, proposals, representations and warranties and prevails over any conflicting or additional terms of any quote,

```
order, acknowledgment, or other communication between the parties relating
to
its subject matter during the term of this Agreement. No modification of this
Agreement will be binding, unless in writing and signed by an authorize
representative of each party. When the translation document has the different
meaning or has the conflicting views with Chinese original text conflict,
should take the laws and regulations promulgation unit as well as the
Generaldata issue Chinese original text as the standard.
```

```
All trademarks and registered trademarks mentioned herein are the property
of
their respective owners.
```

```
DO YOU ACCEPT THE TERMS OF THIS LICENSE AGREEMENT? (Y/N): Y
```

1. 指定安装路径。

根据界面提示输入安装路径，不输入直接回车则默认为/opt/GBASE/gbase。

```
=====
Installation Location
-----

Choose location for software installation

Default Install Folder: /opt/GBASE/gbase

ENTER AN ABSOLUTE PATH, OR PRESS <ENTER> TO ACCEPT THE DEFAULT:
```

2. 选择安装类型，自定义安装输入 2 选择 Custom installation。

```
=====
Installation or Distribution
-----

Select the installation type.

Typical: Install the database server with all features and a database server
that
is configured with default values. Includes:
** Client Software Development Kit (CSDK)
** Java Database Connectivity (JDBC)
Minimum disk space required: 700-800MB

Custom: Install the database server with specific features and software that
you need.
Optionally install a configured database server instance.
Minimum disk space required: 75 MB (without a server instance)

->1- Typical installation
   2- Custom installation
   3- Extract the product files (-DLEGACY option)
```

```
4- Create a RPM package for redistribution
```

```
ENTER THE NUMBER FOR YOUR CHOICE, OR PRESS <ENTER> TO ACCEPT THE DEFAULT:: 2
```

3. 选择自定义安装回车后，如下提示信息展示了选择或取消选择特定功能部件的操作方法，直接<回车>即可。

```
=====
"Choose Install Features" Help
-----
```

```
On the next screen, type the number of a feature to change whether it is
selected or deselected. You can provide a list of numbers, separated by commas,
with no leading or trailing spaces.
```

```
For example, assume that the screen contains this list:
```

```
1- [X] ABC
```

```
2- [ ] XYZ
```

```
Please choose the Features to be installed by this installer.: ____
```

```
If you want to install both ABC and XYZ, type: 2
```

```
If you want to install only XYZ, type: 1,2
```

```
PRESS <ENTER> TO CONTINUE:
```

```
=====
```

4. 如下展示了可供选择的功能部件列表。

输入 1 或者直接回车则默认安装所有的功能部件，输入 2 并回车则需按照步骤 3 中提示的操作方法选择自己所需的功能部件，选择完成后回车继续。

```
=====
Choose Install Set
-----
```

```
=====
Choose Product Features
-----
```

```
ENTER A COMMA_SEPARATED LIST OF NUMBERS REPRESENTING THE FEATURES YOU WOULD
LIKE TO SELECT, OR DESELECT. TO VIEW A FEATURE'S DESCRIPTION, ENTER
'<NUMBER>'. PRESS <RETURN> WHEN YOU ARE DONE:
```

```
1- [X] GBase database server
```

```
2-  |-[X] Base Server
3-  |-[X] Extensions and tools
4-    |-[X] J/Foundation
5-    |-[X] Database extensions
6-    |-[X] Conversion and reversion support
7-    |-[X] XML publishing
8-  |-[X] Demonstration database scripts
9-  |-[X] Enterprise Replication
10- |-[X] Data loading utilities
11-    |-[X] onunload and onload utilities
12-    |-[X] dbload utility
13- |-[X] Backup and Restore
14-    |-[X] archecker utility
15-    |-[X] ON-Bar utility
16-    |-[X] Interface to Tivoli Storage Manager
17- |-[X] Administrative utilities
18-    |-[X] Performance monitoring utilities
19-    |-[X] Miscellaneous monitoring utilities
20-    |-[X] Auditing utilities
21-    |-[X] Database import and export utilities
22- |-[X] JSON Client Support
23- [X] Global Language Support (GLS)
24- |-[X] Chinese
```

Please choose the Features to be installed by this installer.:

```
=====
Feature review
-----
```

Would you like to review the features that you have selected, or change which features you have selected?

```
->1- Continue
    2- Return to feature tree
```

ENTER THE NUMBER OF THE DESIRED CHOICE, OR PRESS <ENTER> TO ACCEPT THE
DEFAULT:

5. 选择是否支持角色分离，若需要支持角色分离，则输入1后回车，默认不支持。

```
=====
Get Role Separation choice
-----
```

```
Enable role separation for auditing procedures.
```

```
If you enable role separation, you can assign existing groups of users to
specific roles.
```

```
If you do not enable role separation, the database server administrator
performs all administration tasks.
```

- ```
1- Enable role separation
->2- Do not enable role separation
```

```
ENTER THE NUMBER FOR YOUR CHOICE, OR PRESS <ENTER> TO ACCEPT THE DEFAULT::
```

6. 选择是否在安装过程中自动创建实例。默认为2，不自动创建实例。

```
=====
Server Instance

```

```
Type 'back' to go to the previous step or 'quit' to cancel the installation.
```

```
Create a database server instance?
```

- ```
1- Yes - create a server instance
->2- No - do not create a server instance
```

```
ENTER THE NUMBER FOR YOUR CHOICE, OR PRESS <ENTER> TO ACCEPT THE DEFAULT::
```

7. 确认数据库安装信息正确无误后，回车开始安装。安装完成继续回车结束安装。

```
=====
Installation Summary
-----
```

```
Please review the following before continuing:
```

```
Product Name:
```

```
GBase Software Bundle
```

```
Install Folder:
```

```
/opt/GBASE/gbase
```

```
Product Features:
```

```
GBase database server,
Base Server,
Extensions and tools,
J/Foundation,
Database extensions,
```



```
Conversion and reversion support,
XML publishing,
Demonstration database scripts,
Enterprise Replication,
Data loading utilities,
onunload and onload utilities,
dbload utility,
Backup and Restore,
archecker utility,
ON-Bar utility,
Interface to Tivoli Storage Manager,
Administrative utilities,
Performance monitoring utilities,
Miscellaneous monitoring utilities,
Auditing utilities,
Database import and export utilities,
JSON Client Support,
Global Language Support (GLS),
Chinese
```

Disk Space Information (for Installation Target):

Required: 497,274,517 Bytes

Available: 9,861,873,664 Bytes

PRESS <ENTER> TO CONTINUE:

```
=====
Ready To Install
-----
```

InstallAnywhere is now ready to install GBase Software Bundle onto your system
at the following location:

/opt/GBASE/gbase

PRESS <ENTER> TO INSTALL:

```
=====
Installing...
-----
```

```
[=====|=====|=====|=====]
[-----|-----|-----|-----]
```

```
=====
Installation Complete
-----
Congratulations! GBase Software Bundle installation is complete.

Product install status:
GBase: Successful
GBase Connect: Successful

Main Version: GBase 8s V8.8

For more information about using GBase products, see the GBase Information
Center at http://www.gbase.cn.

PRESS <ENTER> TO EXIT THE INSTALLER:
```

4.5 创建和初始化实例

创建和初始化实例有两种方式，一种是使用脚本自动化创建及初始化实例，一种是手动创建及初始化实例。

4.5.1 脚本自动创建和初始化实例

安装完成后，在安装目录的etc目录下（例如以上安装示例中的/opt/GBASE/gbase/etc目录）包含初始化实例脚本 GBaseInit_gbasedbt.sh。使用 gbasedbt 用户执行 GBaseInit_gbasedbt.sh 脚本，自动创建并初始化实例。

```
[root@localhost gbase]# su gbasedbt
[gbasedbt@localhost gbase]$ sh GBaseInit_gbasedbt.sh
Initializing Program...OK
ENTER THE INSTANCE INFORMATION or PRESS <ENTER> TO ACCEPT THE DEFAULT.
// 创建实例名称，默认为 gbaseserver
ENTER GBASE INSTANCE NAME (GBASEDBTSERVER) [Default:gbaseserver]:
//选择安装目录。默认为 /opt/GBASE/gbase
SEARCHING FOR GBASE INSTALL FOLDER, PLEASE WAIT FOR SECONDS...
GBASE INSTALL FOLDER LIST:
  1) /opt/GBASE/gbase
CHOOSE GBASE INSTALL FOLDER(GBASEDBTDIR) [Default:/opt/GBASE/gbase]:
//选择本机 IP 地址
CHOOSE SERVICE IP ADDRESS FROM THE LIST:
  1) 192.168.127.101
```

```
2) 127.0.0.1
ENTER THE NUMBER FOR YOUR CHOICE [Default:192.168.127.101]:
//指定数据库的监听端口, 缺省为 9088, 可自定义端口
SPECIFY THE PORT NUMBER FOR GBASE [Default:9088]:
//选择初始化类型: 1 全部使用默认值 2 自定义安装
INITIALIZE TYPE:
1) TYPICAL -- Initialize the instance with all features configured with default
values.
2) CUSTOM -- Initialize the instance with specific features that you need.
ENTER THE NUMBER FOR YOUR CHOICE [Default:1]: 2
//选择数据库字符集
GBASE CHARACTER SET LIST:
1) en_US.8859-1
2) zh_CN.GB18030-2000
3) zh_CN.utf8
ENTER THE NUMBER FOR YOUR CHOICE [Default:1]: 2
//输入数据库空间存储路径
ENTER THE DATA SPACE PATH [Default:/opt/GBASE/gbase/gbaseserver_dbs]:
//设置逻辑日志空间大小
ENTER THE LOGICAL LOG DBSPACE SIZE(MB) [Default:540]:
//设置物理日志空间大小
ENTER THE PHYSICAL LOG DBSPACE SIZE(MB) [Default:540]:
//设置智能大对象空间大小
ENTER THE SMART LOB DBSPACE SIZE(MB) [Default:138]:
//设置临时数据空间大小
ENTER THE TEMPORARY DBSPACE SIZE(MB) [Default:138]:
// 输入 Y 启动以上设置, N 重新进行配置
ENTER "Y" TO START DATABASE ADVANCED SETTINGS, OR ENTER "N" TO ACCEPT DEFAULT
VALUES: [Default:Y]: Y
// 指示创建几个保存数据的数据库空间
ENTER THE NUMBER OF DATA DBSPACES [Default:1]:
// 指示创建几个保存临时数据的数据库空间
ENTER THE NUMBER OF TEMP DBSPACES [Default:1]:
// 是否启用GL_USEGLU, 默认不启用
Enter "Y" TO ENABLE ENVIRONMENT GL_USEGLU, OR ENTER "N" TO DISABLE: [Default:N]:
//实例配置如下所示:
INSTANCE SUMMARY:
Instance name:                gbaseserver
GBase install directory:      /opt/GBASE/gbase
IP address & port:             192.168.127.101:9088
Character set:                 zh_CN.GB18030-2000
Logical log space size:       430 MB
Physical log space size:      430 MB
```

```
Smart LOB space size:      116 MB
Temp DBSpace size:        116 MB
Data path:                 /opt/GBASE/gbase/gbaseserver_dbs
Data path free size:       4292 MB
The number of data DBSpace: 1
The number of temp DBSpace: 1
Environment GL_USEGLU:     1
Enter "Y" to Start database initializing, or Enter "N" to Edit Again: Y
Touching Chunks...OK
Create sqlhosts File:  /opt/GBASE/gbase/etc/sqlhosts.gbaseserver ...OK
Setting Parameters in /opt/GBASE/gbase/etc/onconfig.gbaseserver :
ROOTPATH.ROOTSIZE.DBSERVERNAME.FULL_DISK_INIT.SBSPACENAME.SYSSBSPACENAME.D
BSPACETEMP.LOGFILES.MULTIPROCESSOR.VPCLASS.NETTYPE.CLEANERS.DEF_TABLE_LOCK
MODE.DIRECT_IO.LOCKS.TAPEDEV.LTAPEDEV.CKPTINTVL.DS_MAX_QUERIES.DS_TOTAL_ME
MORY.DS_NONPDQ_QUERY_MEM.PHYSBUFF.LOGBUFF.AUTO_TUNE.MSGPATH.SERVERNUM.ALLO
W_NEWLINE.TEMPTAB_NOLOG.DUMPSHMEM.USEOSTIME.STACKSIZE.ON_RECVRY_THREADS.OF
F_RECVRY_THREADS.USELASTCOMMITTED.SHMVIRTSIZE.SHMADD.GBASEDBTCONTIME.BUFFE
RPOOL2K.BUFFERPOOL16K...AUTO_CKPTS.OK
Initializing Root DBSpace & Share Memory...OK
Creating system database.....OK
Creating logical log Dbspace...OK
Creating physical log Dbspace...OK
Creating smart LOB Dbspace...OK
Creating temp Dbspace.1...OK
Creating data Dbspace.1...OK
Setting dbscheduler...OK
Moving physical log...OK
Adding 40 logical logs:
1.2.3.4.5.6.7.8.9.10.11.12.13.14.15.16.17.18.19.20.21.22.23.24.25.26.27.28
.29.30.31.32.33.34.35.36.37.38.39.40...OK
Setting data chunks extendable...OK
Cleaning logical logs in rootdbs.....OK
Database restarting.....OK
Creating database: gbasedb...OK

Now you can use this URL to connect to gbasedb:
jdbc:gbasedbt-sqli://192.168.8.123:9088/gbasedb:GBASEDBTSERVER=gbaseserver
;

Version:
GBase Database Server -- On-Line -- Up 00:00:13 -- 1121592 Kbytes
Build Number:      3.5.1_3_6a4e30

GBase Initializing Finished!
```

```
Initialize log file : ./InitGBaseDB_202401081452.log

Press <ENTER> to Exit and Logout...
```

以上自动创建和初始化实例完毕，回车退出。

4.5.2 手动创建和初始化实例

您也可以按照如下步骤，手动创建实例并初始化。

(1) 创建一个实例，假设其实例名为“gbaseserver”。

(2) 创建一个实例需要配置以下三个文件，使用实例名作为文件的后缀，实例名为“gbaseserver”，则配置文件的名称如下：

- a) 环境变量文件名为 profile.gbaseserver
- b) 配置参数文件名称为 onconfig.gbaseserver
- c) sqlhosts 配置文件名称为 sqlhosts.gbaseserver

1. 创建数据库的数据文件存储目录

以 root 身份登录，进入安装目录，创建数据目录，以 /dbs为例：

```
[root@localhost ~]# cd /opt/GBASE/gbase
[root@localhost gbase]# mkdir dbs
[root@localhost gbase]# chown gbasedbt:gbasedbt dbs (目录属主要改成 gbasedbt)
[root@localhost gbase]# chmod 755 dbs (目录需要 755 权限)
[root@localhost gbase]# cd dbs
[root@localhost dbs]# touch rootdbs
[root@localhost dbs]# chown gbasedbt:gbasedbt rootdbs
[root@localhost dbs]# chmod 660 rootdbs
```

2. 配置 profile.gbaseserver 环境变量文件

切换到 gbasedbt 用户身份登录，将默认环境变量 .bash_profile 文件复制一份，命名为 profile.gbaseserver，修改文件信息并保存。

```
[root@localhost dbs]# su gbasedbt
[gbasedbt@localhost ~]$ cd /home/gbasedbt
[gbasedbt@localhost ~]$ cp .bash_profile profile.gbaseserver
[gbasedbt@localhost ~]$ vi profile.gbaseserver //修改环境变量文件
```

(进入文件后按“i”建，开启 insert 模式)

注意：根据实例的实际信息更改红色部分字段信息

```
export GBASEDBTSERVER=gbaseserver //实例名
export GBASEDBTDIR=/opt/GBASE/gbase //安装路径
export ONCONFIG=onconfig.gbaseserver //配置参数文件名称
export GBASEDBTSQLHOSTS=$GBASEDBTDIR/etc/sqlhosts.gbaseserver //sqlhosts 文件路径
export PATH=$GBASEDBTDIR/bin:$GBASEDBTDIR/sbin:/usr/bin:${PATH}:.
export GL_DATE="%iY-%m-%d"
```

```
export DATETIME="%iY-%m-%d %H:%M:%S"
export DB_LOCALE=zh_cn.GB18030-2000
export CLIENT_LOCALE=zh_cn.GB18030-2000
export
LD_LIBRARY_PATH=${GBASEBTDIR}/lib:${GBASEBTDIR}/lib/esql:${GBASEBTDIR}/lib/cli
export TERM=vt100
export TERMCAP=${GBASEBTDIR}/etc/termcap
export GBASEBTTERM=termcap
export DBTEMP=${GBASEBTDIR}/tmp
```

执行如下命令，使环境变量生效：

```
[gbasedbt@localhost ~]$ source profile.gbaseserver
```

为了 gbasedbt 用户在登录后自动应用这些环境变量，可执行vi .bash_profile命令修改该文件，将source /home/gbasedbt/profile.gbaseserver添加到文件末尾并保存，并执行source .bash_profile命令生效。

3. 配置 onconfig.gbaseserver 参数文件

将 /opt/GBASE/gbase/etc/ 目录中的 onconfig.std 文档复制一份，命名为 \$ONCONFIG 变量指定的名称 onconfig.gbaseserver。

```
[gbasedbt@localhost ~]$ cd /opt/GBASE/gbase/etc/
[gbasedbt@localhost etc]$ cp onconfig.std onconfig.gbaseserver
```

使用vi onconfig.gbaseserver 命令修改文件，修改以下参数配置并保存：

ROOTPATH	/opt/GBASE/gbase/dbs/rootdbs	//系统数据库文件存储空间路径, 参照步骤 1 中的设置
SERVERNUM	1	//实例编号，多实例中每个实例编号要唯一
DBSERVERNAME	gbaseserver	//数据库服务器实例名称
TAPEDEV	/dev/null	//用于存储空间备份的磁带设备
LTAPEDEV	/dev/null	//用于逻辑日志备份的磁带的设备路径

4. 配置 sqlhosts.gbaseserver 文件

将 /opt/GBASE/gbase/etc/ 目录中的 sqlhosts.std 文档复制一份，命名为 GBASEBTDQLHOSTS 变量指定的名称 sqlhost.gbaseserver。

```
[gbasedbt@localhost ~]$ cd /opt/GBASE/gbase/etc/
[gbasedbt@localhost etc]$ cp sqlhosts.std sqlhosts.gbaseserver
```

使用vi sqlhosts.gbaseserver命令修改文件，在文件末尾添加相关实例名、网络连接方式、IP 及端口号。示例如下，但请注意，相关实例名、网络连接方式、IP 及端口号需

替换为数据库的实际安装信息。

实例名	网络连接方式	IP	端口
gbaseserver	onsoc tcp	192.168.127.101	9088

5. 初始化数据库

使用 gbasedbt 用户执行初始化命令：

```
[gbasedbt@localhost ~]$ oninit -ivy
```

5 典型安装

缺省情况下，典型安装会创建一个适用于您主机环境的数据库服务器实例。但是，您也可以在安装过程中选择禁用创建服务器实例的选项。

进入解压目录，执行安装脚本 ids_install，即可进行安装。具体命令如下：

```
[root@localhost ~]# cd /opt
[root@localhost opt]# sh ids_install
```

典型安装过程如下所示：

- 1. 接受授权协议，内容详见 3 手动安装。
- 2. 选择安装类型，使用默认安装选项 1，直接回车，进行典型安装。

```
=====
Installation or Distribution
-----

Select the installation type.

Typical: Install the database server with all features and a database server
that
is configured with default values. Includes:
** Client Software Development Kit (CSDK)
** Java Database Connectivity (JDBC)
Minimum disk space required: 700-800MB

Custom: Install the database server with specific features and software that
you need.
Optionally install a configured database server instance.
Minimum disk space required: 75 MB (without a server instance)

->1- Typical installation
   2- Custom installation
   3- Extract the product files (-DLEGACY option)
   4- Create a RPM package for redistribution

ENTER THE NUMBER FOR YOUR CHOICE, OR PRESS <ENTER> TO ACCEPT THE DEFAULT:: 1
```

3. 创建实例

系统提示是否创建一个实例，默认选项 1 为创建，直接回车，创建一个实例。

```
=====
Server Instance Creation
-----

Create a server instance?

->1- Yes - create an instance
   2- No - do not create an instance

ENTER THE NUMBER FOR YOUR CHOICE, OR PRESS <ENTER> TO ACCEPT THE DEFAULT::
```

4. 选择数据库用户数

选择该实例预期要支持的数据库用户数，默认选项为 1，直接回车继续。

```
=====
Configuration - Number of Users
-----

Select the number of expected database users.

->1- 1 - 100
   2- 101 - 500
   3- 501 - 1000
   4- 1000+

ENTER THE NUMBER FOR YOUR CHOICE, OR PRESS <ENTER> TO ACCEPT THE DEFAULT::
```

5. 配置结束，点击回车进行安装。安装后会提示将进行数据库实例的初始化，按回车继续。

```
=====
Ready To Install
-----

InstallAnywhere is now ready to install GBase 8s Software Bundle onto your
system at the following location:
/opt/GBASE/gbase
PRESS <ENTER> TO INSTALL:

=====
Installing...
-----

[=====|=====|=====|=====]
[-----|-----|-----|-----]

=====
Server Initialization
-----

The server will now be initialized. Initialization might take quite a while,
depending on the performance of your computer.

PRESS <ENTER> TO CONTINUE:
```

6. 数据库实例创建成功并应用，点击回车后继续。

```
=====
Using the new instance
-----

A database server instance was created. If you chose to initialize the
```



```
instance, it is ready to use.

You can open a command prompt to an initialized instance by running one of the
following commands at /opt/GBASE/gbase, where ol_gbasedbt1210 is the path or
filename of the instance.

Windows:
ol_gbasedbt1210.cmd

UNIX csh:
source ol_gbasedbt1210.csh

UNIX ksh or bourne:
./ol_gbasedbt1210.ksh

If initialization fails, check the online.log file for messages. The instance's
root chunk must be owned by the correct user and group, and it must have
readable and writable (rw) permission bits set only for owner and group.

PRESS <ENTER> TO CONTINUE:
```

7. 安装完成，回车后退出安装程序。

```
=====
Installation Complete
-----

Congratulations! GBase Software Bundle installation is complete.

Product install status:
GBase: Successful
GBase Connect: Successful

Main Version: GBase 8s V8.8

For more information about using GBase products, see the GBase Information
Center at http://www.gbase.cn.

PRESS <ENTER> TO EXIT THE INSTALLER:
```

安装完成后，服务器当前环境变量即默认为您安装的数据库实例。您也可以选择把 GBase 8s 安装目录下的环境变量文件 `ol_gbasedbt1210.ksh` 的内容追加到 `gbasedbt` 用户主目录下的 `.bash_profile` 文件中，以便于 `gbasedbt` 用户再次登录时即可自动应用这些环境变量，命令参考如下：

```
[root@localhost ~]# cd /opt/GBASE/gbase
[root@localhost gbase]# cat ol_gbasedbt1210.ksh >>
/home/gbasedbt/.bash_profile
[root@localhost ~]# cd /home/gbasedbt/
[root@localhost ~]# source .bash_profile
```

典型安装完成，查看该实例实际端口的方式如下：

- (1) 查看安装目录下，形如 `ol_gbasedbt1210.ksh` 的环境变量文件，参数 `GBASEDBTSERVER` 的值即为数据库服务器对应的实例名。例如：`GBASEDBTSERVER=ol_gbasedbt1210`。
- (2) 执行如下命令，查看对应端口号。如下 `30490` 即为典型安装后数据库实例的端口号。

```
[gbasedbt@localhost server1]$ cat /etc/services|grep ol_gbasedbt1210
ol_gbasedbt1210      30490/tcp
```

```
ol_gbasedbt1210_json 27017/tcp
#JSON listener for ol_gbasedbt1210
```

6 静默安装

要完成静默安装，必须有响应文件，其带有想要如何安装该产品的定制设置。创建响应文件有两种方式：录制您安装的配置生成响应文件或定制 `bundle.properties` 模板文件。以下从生成响应文件开始，介绍静默安装的安装步骤。

1. 可选择如下任意一种方式生成响应文件。

(1) 录制您安装的配置生成响应文件：

使用如下命令执行 GBase 8s 安装脚本，录制模板生成响应文件。安装完成后，将在 `/opt` 路径下生成响应文件 `bundle.properties`。

```
[root@localhost opt] ./ids_install -r /opt/bundle.properties
```

(2) 定制 `bundle.properties` 模板文件：

该安装介质包含基于文本的 `bundle.properties` 文件，可创建该文件的副本，并为想要的安装配置编辑该文件。

重要：1) 请不要对安装介质中的 `bundle.properties` 文件进行重写、移动或删除。

2) 必须将定制的 `.properties` 文件中的产品许可证条款协议设置更改“true”（`LICENSE_ACCEPTED=TRUE`）。

2. 将响应文件复制到想要安装 GBase 8s 和任何客户机程序的计算机。

3. 运行静默安装命令，指示响应文件的相对或绝对路径：

```
[root@localhost opt] ./ids_install -i silent -f /opt/bundle.properties
-DLICENSE_ACCEPTED=TRUE
(-DLICENSE_ACCEPTED=TRUE 指示接受许可协议)
```

4. 配置数据库服务器。

安装完成后，需要设置环境变量、修改配置文件相关参数。

7 数据库的简单使用

7.1 启动/停止数据库服务

通常情况下，使用 `gbasedbt` 用户来启动和停止数据库服务。

成功安装数据库 GBase 8s 后，数据库会自动处于启动状态，可通过 `ps -ef|grep oninit`

命令检查服务进程是否存在:

```
[root@localhost opt]# ps -ef|grep oninit
gbasedbt 10830      1  0 19:52 ?        00:00:04 /opt/GBASE/gbase/bin/oninit -vy
root      10831 10830  0 19:52 ?        00:00:00 /opt/GBASE/gbase/bin/oninit -vy
root      10832 10831  0 19:52 ?        00:00:00 /opt/GBASE/gbase/bin/oninit -vy
root      10833 10831  0 19:52 ?        00:00:00 /opt/GBASE/gbase/bin/oninit -vy
root      10834 10831  0 19:52 ?        00:00:00 /opt/GBASE/gbase/bin/oninit -vy
root      10835 10831  0 19:52 ?        00:00:00 /opt/GBASE/gbase/bin/oninit -vy
root      10836 10831  0 19:52 ?        00:00:00 /opt/GBASE/gbase/bin/oninit -vy
root      10837 10831  0 19:52 ?        00:00:00 /opt/GBASE/gbase/bin/oninit -vy
root      10915 10831  0 19:52 ?        00:00:00 /opt/GBASE/gbase/bin/oninit -vy
root      11997  5051  0 20:02 pts/0    00:00:00 grep oninit
```

以 gbasedbt 用户身份登录后, 执行 onmode -ky, 可停止数据库服务, 示例如下:

```
[gbasedbt@localhost ~]$ onmode -ky
```

执行 oninit -vy, 启动数据库服务, 示例如下:

```
[gbasedbt@localhost ~]$ oninit -vy
Warning: Parameter's user-configured value was adjusted. (DS_MAX_SCANS)
Warning: Parameter's user-configured value was adjusted. (ONLIDX_MAXMEM)
Reading configuration file
'/opt/GBASE/gbase/etc/onconfig.ol_gbasedbt1210'...succeeded
Creating /GBASEDBTMP/.infoxdirs...succeeded
Allocating and attaching to shared memory...succeeded
Creating resident pool 8310 kbytes...succeeded
Creating infos file
"/opt/GBASE/gbase/etc/.infos.ol_gbasedbt1210"...succeeded
Linking conf file "/opt/GBASE/gbase/etc/.conf.ol_gbasedbt1210"...succeeded
Initializing rhead structure...rhlock_t 16384 (512K)... rlock_t (5312K)...
Writing to infos file...succeeded
Initialization of Encryption...succeeded
Initializing ASF...succeeded
Initializing Dictionary Cache and SPL Routine Cache...succeeded
Bringing up ADM VP...succeeded
Creating VP classes...succeeded
Forking main_loop thread...succeeded
Initializing DR structures...succeeded
Forking 1 'soctcp' listener threads...succeeded
Forking 1 'soctcp' listener threads...succeeded
Forking 1 'soctcp' listener threads...succeeded
Starting tracing...succeeded
Initializing 2 flushers...succeeded
Initializing SDS Server network connections...succeeded
Initializing log/checkpoint information...succeeded
Initializing dbspaces...succeeded
Opening primary chunks...succeeded
Validating chunks...succeeded
Initialize Async Log Flusher...succeeded
Starting B-tree Scanner...succeeded
Init ReadAhead Daemon...succeeded
Init DB Util Daemon...succeeded
Initializing DBSPACETEMP list...succeeded
Init Auto Tuning Daemon...succeeded
Checking database partition index...succeeded
```

```
Initializing dataskip structure...succeeded
Checking for temporary tables to drop...succeeded
Updating Global Row Counter...succeeded
Forking onmode_mon thread...succeeded
Creating periodic thread...succeeded
Creating periodic thread...succeeded
Starting scheduling system...succeeded
Verbose output complete: mode = 5
```

启动成功后，输入 `ps -ef|grep oninit` 检查数据库服务进程存在：

```
[gbasedbt@localhost ~]$ ps -ef|grep oninit
gbasedbt 12056      1  0 20:14 ?        00:00:00 oninit -vy
root      12057    12056  0 20:14 ?        00:00:00 oninit -vy
root      12058    12057  0 20:14 ?        00:00:00 oninit -vy
root      12059    12057  0 20:14 ?        00:00:00 oninit -vy
root      12060    12057  0 20:14 ?        00:00:00 oninit -vy
root      12061    12057  0 20:14 ?        00:00:00 oninit -vy
root      12062    12057  0 20:14 ?        00:00:00 oninit -vy
root      12063    12057  0 20:14 ?        00:00:00 oninit -vy
root      12064    12057  0 20:14 ?        00:00:00 oninit -vy
gbasedbt 12134    12116  0 20:25 pts/0    00:00:00 grep  oninit
```

7.2 登录数据库

以 gbasedbt 用户身份登录，输入 `dbaccess --` 命令进入数据库命令行模式，示例如下：

```
[gbasedbt@localhost ~]$ dbaccess - -
>
```

7.3 创建数据库

在 dbaccess 交互命令行中，执行如下SQL语句，创建数据库，示例如下：

```
[gbasedbt@localhost~]$ dbaccess - -
> create database gbase8s with log;

Database created.
```

8 数据库的卸载

当用户需要卸载 GBase 8s 数据库系统时，可使用卸载脚本自动卸载数据库。以下是卸载数据库的相关步骤。

1. 使用 gbasedbt 用户执行 `onmode -ky` 命令停止数据库服务。
2. 切换到 root 用户，进入安装目录下的 `uninstall/uninstall_ids`，执行该目录下的 `uninstallids` 命令进行卸载。直接回车确认卸载，示例如下：

\$GBASEDBTDIR指定的目录) 里的旧的license文件后, 重启数据库实例即可。

The logo for GBASE, featuring the word "GBASE" in a bold, red, sans-serif font, followed by a registered trademark symbol (®). To the left of the text is a red square.

南大通用数据技术股份有限公司
General Data Technology Co., Ltd.



微信二维码

