BTRFS

Search docs

OVERVIEW

Introduction Status

☐ Manual pages

btrfs(8)

btrfs(5)

btrfs-balance(8)

btrfs-check(8)

□ btrfs-convert(8)

SYNOPSIS

DESCRIPTION

OPTIONS EXIT STATUS

SEE ALSO

btrfs-device(8)

btrfs-filesystem(8)

btrfs-find-root(8)

btrfs-image(8)

btrfs-inspect-internal(8)

btrfs-ioctl(2)

btrfs-map-logical(8)

btrfs-property(8) btrfs-qgroup(8)

btrfs-quota(8)

btrfs-receive(8)

btrfs-replace(8) btrfs-rescue(8)

btrfs-restore(8)

btrfs-scrub(8)

btrfs-select-super(8)

btrfs-send(8)

btrfs-subvolume(8)

btrfstune(8) fsck.btrfs(8)

mkfs.btrfs(8)

Administration

Hardware considerations Changes (feature/version)

Changes (kernel/version)

Changes (btrfs-progs)

Contributors

Glossary Installation instructions

Source repositories

Interoperability

FEATURES

Common Linux features

Custom ioctls

Balance

Auto-repair on read

Compression

Checksumming Convert

Deduplication

Defragmentation

Inline files

Quota groups Reflink

Resize Scrub

Seeding device

Send/receive Subpage support

Subvolumes

Swapfile

Tree checker Trim/discard

Volume management

Zoned mode

DEVELOPER DOCUMENTATION

Development notes Developer's FAQ

Conventions and style for documentation

Experimental features

Btrees

On-disk Format

Send stream format JSON output

Internal APIs

Release checklist

Pull request review workflow Command line, formatting, UI guidelines

btrfs-ioctl(2)

TODO

Troubleshooting pages

btrfs-convert(8)

Manual pages / btrfs-convert(8)

SYNOPSIS

btrfs-convert [options] <device>

DESCRIPTION

The btrfs-convert tool can be used to convert existing source filesystem image to a btrfs filesystem in-place. The original filesystem image is accessible in subvolume named like ext2 saved as file image.

View page source

Supported filesystems:

- ext2, ext3, ext4 -- original feature, always built in
- reiserfs -- since version 4.13, optionally built, requires libreiserfscore 3.6.27
- NTFS -- external tool https://github.com/maharmstone/ntfs2btrfs

The list of supported source filesystem by a given binary is listed at the end of help (option --help).

• Warning

If you are going to perform rollback to the original filesystem, you should not execute btrfs balance command on the converted filesystem. This will change the extent layout and make btrfs-convert unable to rollback.

The conversion utilizes free space of the original filesystem. The exact estimate of the required space cannot be foretold. The final btrfs metadata might occupy several gigabytes on a hundreds-gigabyte filesystem.

If the ability to rollback is no longer important, the it is recommended to perform a few more steps to transition the btrfs filesystem to a more compact layout. This is because the conversion inherits the original data blocks' fragmentation, and also because the metadata blocks are bound to the original free space layout.

Due to different constraints, it is only possible to convert filesystems that have a supported data block size (i.e. the same that would be valid for mkfs.btrfs). This is typically the system page size (4KiB on x86_64 machines).

• Note

Always consider if a mkfs and file copy would not be a better option than the in-place conversion given what was said above. The conversion depends on 3rd party libraries and the other filesystems could still evolve and add new features. Not all combinations are covered or tested.

BEFORE YOU START

The source filesystem must be clean, e.g. no journal to replay or no repairs needed. The respective fsck utility must be run on the source filesystem prior to conversion. Please refer to the manual pages in case you encounter problems.

For ext2/3/4:

e2fsck -fvy /dev/sdx

For reiserfs:

reiserfsck -fy /dev/sdx

Skipping that step could lead to incorrect results on the target filesystem, but it may work.

REMOVE THE ORIGINAL FILESYSTEM METADATA

By removing the subvolume named like ext2_saved or reiserfs_saved, all metadata of the original filesystem will be removed:

btrfs subvolume delete /mnt/ext2_saved

At this point it is not possible to do a rollback. The filesystem is usable but may be impacted by the fragmentation inherited from the original filesystem.

MAKE FILE DATA MORE CONTIGUOUS

An optional but recommended step is to run defragmentation on the entire filesystem. This will attempt to make file extents more contiguous.

btrfs filesystem defrag -v -r -f -t 32M /mnt/btrfs

Verbose recursive defragmentation (-v, -r), flush data per-file (-f) with target extent size 32MiB (-t).

ATTEMPT TO MAKE BTRFS METADATA MORE COMPACT

Optional but recommended step.

The metadata block groups after conversion may be smaller than the default size (256MiB or 1GiB). Running a balance will attempt to merge the block groups. This depends on the free space layout (and fragmentation) and may fail due to lack of enough work space. This is a soft error leaving the filesystem usable but the block group layout may remain unchanged.

Note that balance operation takes a lot of time, please see also btrfs-balance(8).

btrfs balance start -m /mnt/btrfs

OPTIONS

--csum <type>, --checksum <type>

Specify the checksum algorithm. Default is crc32c. Valid values are crc32c, xxhash, sha256 or blake2. To mount such filesystem kernel must support the checksums as well.

-d|--no-datasum

disable data checksum calculations and set the NODATASUM file flag, this can speed up the conversion

-i|--no-xattr

ignore xattrs and ACLs of files

-n|--no-inline

disable inlining of small files to metadata blocks, this will decrease the metadata consumption and may help to convert a filesystem with low free space

-N|--nodesize <SIZE>

set filesystem nodesize, the tree block size in which btrfs stores its metadata. The default value is 16KiB (16384) or the page size, whichever is bigger. Must be a multiple of the sectorsize, but not larger than 65536. See mkfs.btrfs(8) for more details.

-r|--rollback

rollback to the original ext2/3/4 filesystem if possible

-I|--label <LABEL>

set filesystem label during conversion

-L|--copy-label

★ BTRFS Search docs **OVERVIEW** Introduction ☐ Manual pages btrfs(8) btrfs(5) btrfs-balance(8) btrfs-check(8) ☐ btrfs-convert(8) SYNOPSIS DESCRIPTION OPTIONS **EXIT STATUS** SEE ALSO btrfs-device(8) btrfs-filesystem(8) btrfs-find-root(8) btrfs-image(8) btrfs-inspect-internal(8) btrfs-ioctl(2) btrfs-map-logical(8) btrfs-property(8) btrfs-qgroup(8) btrfs-quota(8) btrfs-receive(8) btrfs-replace(8) btrfs-rescue(8) btrfs-restore(8) btrfs-scrub(8) btrfs-select-super(8) btrfs-send(8) btrfs-subvolume(8) btrfstune(8) fsck.btrfs(8) mkfs.btrfs(8) Administration Hardware considerations Changes (feature/version) Changes (kernel/version)

Status

Changes (btrfs-progs) Contributors Glossary Installation instructions Source repositories Interoperability **FEATURES** Common Linux features Custom ioctls Auto-repair on read Balance Compression Checksumming Convert Deduplication Defragmentation Inline files Quota groups Reflink Resize Scrub Seeding device

Send/receive

Subvolumes

Tree checker

Trim/discard

Zoned mode

Volume management

Development notes

Conventions and style for

Experimental features

Developer's FAQ

documentation

Btrfs design

On-disk Format

JSON output

Internal APIs

btrfs-ioctl(2)

TODO

Release checklist

Pull request review workflow

Command line, formatting, UI guidelines

Send stream format

Btrees

DEVELOPER DOCUMENTATION

Swapfile

Subpage support

use label from the converted filesystem -O|--features <feature1>[,<feature2>...] A list of filesystem features enabled the at time of conversion. Not all features are supported by old kernels. To disable a feature, prefix it with ^. Description of the features is in section FILESYSTEM FEATURES of mkfs.btrfs(8). To see all available features that btrfs-convert supports run: btrfs-convert -0 list-all -p|--progress show progress of conversion (a heartbeat indicator and number of inodes processed), on by default --no-progress disable progress and show only the main phases of conversion --uuid <SPEC> set the FSID of the new filesystem based on 'SPEC': • new - (default) generate UUID for the FSID of btrfs • copy - copy UUID from the source filesystem • UUID - a conforming UUID value, the 36 byte string representation --version Print the **btrfs-convert** version, builtin features and exit. **EXIT STATUS** btrfs-convert will return 0 if no error happened. If any problems happened, 1 will be returned. **SEE ALSO** mkfs.btrfs(8) Next 😜 Previous © Copyright. Built with Sphinx using a theme provided by Read the Docs.