btrfs-receive(8)

Manual pages / btrfs-receive(8)

SYNOPSIS

btrfs receive [options] <path>

or

btrfs receive --dump [options]

DESCRIPTION

Receive a stream of changes and replicate one or more subvolumes that were previously generated by **btrfs send**. The received subvolumes are stored to *path*, unless --*dump* option is given.

View page source

If --dump option is specified, btrfs receive will only do the validation of the stream, and print the stream metadata, one operation per line.

btrfs receive will fail in the following cases:

- 1. receiving subvolume already exists
- 2. previously received subvolume has been changed after it was received
- 3. default subvolume has changed or you didn't mount the filesystem at the toplevel subvolume

A subvolume is made read-only after the receiving process finishes successfully (see BUGS below).

Options

-f <FILE>

read the stream from FILE instead of stdin,

-C|--chroot

confine the process to *path* using chroot(1)

-e

terminate after receiving an end cmd marker in the stream.

Without this option the receiver side terminates only in case of an error on end of file.

-E|--max-errors <NERR>

terminate as soon as NERR errors occur while stream processing commands from the stream

Default value is 1. A value of 0 means no limit.

-m <ROOTMOUNT>

the root mount point of the destination filesystem

By default the mount point is searched in :file:/proc/self/mounts`. If /proc is not accessible, e.g. in a chroot environment, use this option to tell us where this filesystem is mounted.

--force-decompress

if the stream contains compressed data (see --compressed-data in btrfs-send(8)), always decompress it instead of writing it with encoded I/O

--dump

dump the stream metadata, one line per operation

Does not require the *path* parameter. The filesystem remains unchanged. Each stream command is on one line in the form of *key=value* and separated by one or more spaces. Values that contain special characters (like paths or extended attributes) are encoded in C-like way, e.g. '\n' or octal escape sequence like '\NNN' where N is the char value. Same encoding as is used in /proc files.

-q|--quiet

(deprecated) alias for global -q option

-v

(deprecated) alias for global -v option

Global options

-v|--verbose

increase verbosity about performed actions, print details about each operation

-q|--quiet

suppress all messages except errors

BUGS

btrfs receive sets the subvolume read-only after it completes successfully. However, while the receive is in progress, users who have write access to files or directories in the receiving *path* can add, remove, or modify files, in which case the resulting read-only subvolume will not be an exact copy of the sent subvolume.

If the intention is to create an exact copy, the receiving *path* should be protected from access by users until the receive operation has completed and the subvolume is set to read-only.

Additionally, receive does not currently do a very good job of validating that an incremental send stream actually makes sense, and it is thus possible for a specially crafted send stream to create a subvolume with reflinks to arbitrary files in the same filesystem. Because of this, users are advised to not use btrfs receive on send streams from untrusted sources, and to protect trusted streams when sending them across untrusted networks.

EXIT STATUS

btrfs receive returns a zero exit status if it succeeds. Non zero is returned in case of failure.

AVAILABILITY

btrfs is part of btrfs-progs. Please refer to the documentation at https://btrfs.readthedocs.io.

SEE ALSO

btrfs-send(8), mkfs.btrfs(8)

 ♦ Previous

© Copyright.

Built with Sphinx using a theme provided by Read the Docs.

btrfs(8)

☐ Manual pages

Status

btrfs(5) btrfs-balance(8)

btrfs-check(8)

btrfs-convert(8)

btrfs-device(8)

btrfs-filesystem(8)

btrfs-find-root(8)

btrfs-image(8)
btrfs-inspect-internal(8)

btris-irispect-ii

btrfs-ioctl(2)

btrfs-map-logical(8)

btrfs-property(8) btrfs-qgroup(8)

btrfs-quota(8)

□ btrfs-receive(8)

SYNOPSIS

DESCRIPTION

BUGS

EXIT STATUS

AVAILABILITY

SEE ALSO

btrfs-replace(8)

btrfs-rescue(8)

btrfs-rescue

btrfs-restore(8)

btrfs-scrub(8)

btrfs-select-super(8) btrfs-send(8)

btrfs-subvolume(8)

btrfstune(8) fsck.btrfs(8)

mkfs.btrfs(8)

Administration

Hardware considerations

Changes (feature/version)

Changes (kernel/version)
Changes (btrfs-progs)

Contributors

Glossary

Installation instructions

Source repositories
Interoperability

FEATURES

Common Linux features
Custom ioctls

Auto-repair on read

Balance Compression

Checksumming
Convert

Defragmentation

Deduplication

Inline files

Quota groups

Reflink Resize

Scrub
Seeding device

Send/receive
Subpage support

Subvolumes

Swapfile

Tree checker

Trim/discard

Volume management

Zoned mode

Developer's FAQ

documentation

Development notes

DEVELOPER DOCUMENTATION

Experimental features

Conventions and style for

Btrfs design
Btrees

On-disk Format

JSON output

Send stream format

Internal APIs
Release checklist

Pull request review workflow

Command line, formatting, UI guidelines

btrfs-ioctl(2)

TODO

- P stable