MEASURE · #1303

A measure counts characters, not slide width

Sixteen em, about thirty-three characters — the default heading measure.

SECTION 01 · THE DEFECT

The old cap bound on every divider slide it was measured on

DIAGNOSIS · UNITS

A fraction of the slide is not a count of characters.

The two agree only while the type size holds still — and it doesn't. Lattice curates `--fs-*` per orientation, so one `cqi` cap allowed about 22 characters per line on landscape and 12 on portrait.

- `--measure-bookend-heading` — `16em`, about 33 characters
- `--measure-bookend-lede` — `26em`, about 56 characters
- Both overridable from front-matter `style:`

SECTION 02 · THE LEDE

A subtitle takes the reading measure, not the frame

The frame alone would allow roughly ninety characters on one line, well past the point where the eye loses the line return.

Lede measure · divider light

REFERENCE

Where the measure is written down.

`typography` — section 8 defines measure alongside size

`base.docs` — the two tokens, under the headline register

`decision` — the measurement, and why landscape moved

CLOSING

Balance decides the breaks; the measure decides the width

Widening a cap to cure an orphaned last word only moves the orphan, and buys a longer line for nothing.