参考

pike版本Nova使用Cinder 新attach/detach 的API Cinder新attach/detach API

Nova如何使用新的API

attach流程:

- 1. (api):调用attachment_create创建一个attachment记录。请求中不会携带connector参数,因此Cinder只创建一个空的attachment记录,并将卷状态改为reserved,不会返回target的连接信息。返回的attachment_id会被更新到BDM的记录中。
- 2. (compute):调用attachment_update接口,该接口返回target的连接信息,并且在Cinder完成所有attach相关操作,卷状态被设定为in-use(也就是说Cinder这时候认为挂载已经挂完了,没我的事了)。这时候Nova Compute会等待Volume的状态更新完成,如果状态更新发生了错误,那么会将虚机的状态设为ERROR。
- 3. (compute):使用os-brick连接磁盘到Host。
- 4. (compute):将设备提供给VM使用。

dettach:

- 1. (api):检查请求是否合法;
- 2. (compute):从VM分离Volume,如果失败request停止;
- 3. (compute): 调用os-brick断开host和backend的连接;
- 4. (compute):如果BDM记录中设定attachment_id,那么使用新的接口detach,否则使用旧接口,如果此时发生错误VM状态会被设为ERROR

对数据模型的影响

nova在blockdevicemapping表中可能不在保存connection_info信息,只保存attachment_id。

需要连接信息时,通过cinder接口获取。

Data model impact

When using the new API flow, we no longer need to store the connection_info, as we don't need to pass that back to Cinder. Instead we just store the attachment_id for each host the volume is attached to, and any time we need the connection_info we fetch that from Cinder.

When an attachment_id is populated, we use the new flow to do all attach or detach operations. When not present, we use the old flow.