



LME KNITTING PATTERN

LME MINI & ME PONCHO FOR ADULTS

SIZE XS-4XL

An easy-knit poncho with a low ribbed neckline and a round increase section. The whole garment is knitted in the round from the top down as one continuous piece. No splits and no seaming. The poncho finishes with a continuous i-cord edge and one fastening on each side.



By Renate Dahl

Little Montessori Explorers

lmexplorers.com



TIPS: Read the whole pattern once before you cast on. Always knit a gauge swatch first, see page 3.

BEFORE YOU START

The poncho is knitted in the round from the neckline to the hem. Eight even increase lines shape the round silhouette. After the last increase, all stitches are knitted plain in the round with no further shaping. The buttonholes are made on the back part of the same round piece, right above the hem. The buttons are sewn on the front part.

WHAT YOU LEARN

- to knit a low, soft ribbed neckline in 1 knit, 1 purl
- to knit in the round on a circular needle
- to increase evenly in eight sections
- to make a simple buttonhole on each side
- to bind off with i-cord all round the hem

HOW HARD IS IT?

Easy to a little practised. You should be able to cast on, knit and purl, and knit in the round. Increases, buttonholes and i-cord bind-off are explained step by step.

One step at a time, and in the end you have a poncho.

WHAT YOU NEED

YARN

DROPS Air (65% alpaca, 28% polyamide, 7% wool, 50 g = approx. 150 m). The poncho is knitted with one strand.

Size	Amount	Skeins
XS	450 g	9
S	450 g	9
M	500 g	10
L	500 g	10
XL	550 g	11
2XL	550 g	11
3XL	600 g	12
4XL	600 g	12

NEEDLES AND KIT

- 4.5 mm circular needle, 40–60 cm, for the neckline
- 5 mm circular needle, 80–120 cm, for the rest of the poncho
- 8 stitch markers and 4 removable markers
- 2 flat buttons, approx. 18–25 mm
- tapestry needle and tape measure

GAUGE

17 stitches and 22 rows in stockinette = 10 × 10 cm on 5 mm needles after washing and drying. Knit a swatch. Change needle size if your gauge does not match.

SIZES AND MEASUREMENTS

WHICH SIZE?

Choose first by age or usual size. The poncho has plenty of ease. Full length is measured from the top of the neckline to the hem.

Size	Stitches	Width	Length	Arm opening
XS	336	ca. 99 cm	ca. 62 cm	ca. 28 cm
S	352	ca. 104 cm	ca. 66 cm	ca. 28 cm
M	360	ca. 106 cm	ca. 68 cm	ca. 31 cm
L	376	ca. 111 cm	ca. 72 cm	ca. 31 cm
XL	392	ca. 115 cm	ca. 75 cm	ca. 33 cm
2XL	408	ca. 120 cm	ca. 78 cm	ca. 33 cm
3XL	432	ca. 127 cm	ca. 82 cm	ca. 35 cm
4XL	448	ca. 132 cm	ca. 84 cm	ca. 35 cm

IMPORTANT ABOUT THE CONSTRUCTION

All sizes are knitted as one round piece. There is no side opening that is cut or knitted separately. The arm opening is only formed once a point on the front part is buttoned to a point on the back part on each side.

Try the poncho on as you go. The length can easily be adjusted before the buttonholes are knitted.

TECHNIQUES AND NECKLINE

GLOSSARY

Term	Means
st	stitch
rnd	round
k / p	knit / purl
inc 1, leaning left	insert the left needle from the front under the strand between two stitches and knit it twisted, through the back loop
inc 1, leaning right	insert the left needle from the back under the strand between two stitches and knit it through the front loop, not twisted
stockinette in the round	all stitches knitted plain
i-cord	narrow knitted cord edge
knitted cast-on	knit into the last stitch on the needle without slipping it off, place the new stitch back onto the left needle

1 - NECKLINE

Cast on with the 4.5 mm circular needle:

Size	Cast on	Rib height
XS	80 m	3 cm
S	80 m	3 cm
M	88 m	3 cm
L	88 m	3 cm
XL	88 m	3 cm
2XL	88 m	3 cm
3XL	96 m	3 cm
4XL	96 m	3 cm

Join in the round without twisting the work. Place a clear round marker at centre back. Knit *1 knit, 1 purl* in the round until the neckline has the given height. Switch to the 5 mm needle and knit 1 plain round.

ROUND INCREASE SECTION

2 - PLACE THE MARKERS

Divide the stitches into 8 equal sections with markers. The round marker is also the first increase marker.

Size	Stitches per section
XS	10
S	10
M	11
L	11
XL	11
2XL	11
3XL	12
4XL	12

INCREASE ROUND

3 - INCREASE ROUND

Knit to 1 stitch before the marker. Increase 1 stitch leaning left. Move the marker over. Increase 1 stitch leaning right. Repeat at all 8 markers. This increases 16 stitches.

Then knit 1 whole round plain with no increases. Repeat these two rounds until the right stitch count is reached:

Size	Increase rounds	Stitches after increases	Approx. length
XS	16	336	ca. 22 cm
S	17	352	ca. 24 cm
M	17	360	ca. 24 cm
L	18	376	ca. 25 cm
XL	19	392	ca. 26 cm
2XL	20	408	ca. 28 cm
3XL	21	432	ca. 29 cm
4XL	22	448	ca. 30 cm



TIPS: How to increase: For a stitch leaning left, insert the left needle from the front under the strand between two stitches and knit it twisted, through the back loop. For a stitch leaning right, insert the left needle from the back under the strand between two stitches and knit it through the front loop, not twisted. The two new stitches then lean away from each other, giving a neat, symmetrical line out from each marker.

Checkpoint: The right stitch count matters most. If the height is off, keep knitting with no increases until the work has the given length.

KNIT ON IN THE ROUND

4 - THE WHOLE PONCHO

Remove the 7 ordinary increase markers, but keep the round marker at centre back. Knit all stitches plain in the round with no more increases. Continue until the work measures approx. 1.5 cm less than the given full length.

Size	Stop at
XS	60.5 cm
S	64.5 cm
M	66.5 cm
L	70.5 cm
XL	73.5 cm
2XL	76.5 cm
3XL	80.5 cm
4XL	82.5 cm

SIDE FASTENING

5 - SIDE FASTENING

Lay the work flat with the round marker at centre back. Find the middle of each side.

Count the given number of stitches from the side middle towards the front and place a marker for the button. Count the same number of stitches towards the back and place a marker for the buttonhole.

Size	Stitches
XS	24
S	24
M	26
L	26
XL	28
2XL	28
3XL	30
4XL	30

The work is still one whole, unbroken circle. Nothing is split.

BUTTONHOLE AND I-CORD EDGE

PLACEMENT FROM CENTRE BACK

Point	Knapphull 1	Knapp 1	Knapp 2	Knapphull 2
XS	60	108	228	276
S	64	112	240	288
M	64	116	244	296
L	68	120	256	308
XL	70	126	266	322
2XL	74	130	278	334
3XL	78	138	294	354
4XL	82	142	306	366

6 - BUTTONHOLE

Knit to the first buttonhole marker: yarn over, k2tog. Knit to the next buttonhole marker and repeat. Finish the round. Then knit 1 whole plain round, also across the yarn overs.

7 - I-CORD EDGE

Cast on 3 new stitches on the left needle using the knitted cast-on method. Knit 2. Knit the next i-cord stitch together with the next poncho stitch through the back loop. Slide the 3 stitches back without turning. Repeat all round the hem. Sew the beginning and end neatly together.



TIPS: Knitted cast-on: knit into the last stitch on the left needle as usual, but do not slip the old stitch off. Place the new stitch you just knitted back onto the left needle. Repeat until you have cast on 3 new stitches.

The i-cord edge runs continuously all round the poncho.

FINISHING

8 - THE BUTTONS

Sew one button on securely at each marker on the front part, right above the i-cord edge. Button each one through the buttonhole on the back part on the same side. The back part lies over the front part. Weave in ends, wash gently and dry flat.

FINISHING TOUCHES

- ☐ Weave in all ends on the wrong side.
- ☐ Soak the garment in lukewarm water with wool wash. Do not rub or wring.
- ☐ Press the water out in a towel. Dry flat to the given measurements.
- ☐ Check the buttons after drying. Sew them extra securely.

Before this pattern is sold: every size must be test-knitted, measured after washing and technically checked.

Happy knitting!



Renate Dahl

Little Montessori Explorers

lmexplorers.com

© 2026 Little Montessori Explorers. This pattern is for personal use only. The pattern may not be copied, shared, resold or published. Finished items may be sold on a small scale with credit to Little Montessori Explorers.