


>_SH





1. INSTALL DEBIAN 11

- *Enable SSH on installion *Enable XFCE on installation
- \$ su root \$ nano /etc/sudoers *add sudoer
- \$ sudo apt update && sudo apt upgrade \$ sudo apt install net-tools
- *To disable the Laptop Close Lid:
- \$ sudo nano /etc/systemd/logind.conf *Insert these

HandleLidSwitch=ignore Han dleLidSwitchExternalPower=ignore HandleLidSwitchDocked=ignore

- *To disable the GUI:
- \$ sudo systemctl set-default multi-user.target \$ sudo reboot
- To re-enable the GUI:
- \$ sudo systemctl set-default graphical.target \$ sudo reboot
- *Firewall
- \$ sudo apt install ufw
- \$ sudo ufw allow ssh
- \$ sudo ufw allow http
- \$ sudo ufw allow 3389
- \$ sudo nano /etc/network/interfaces
- \$ sudo systemctl restart networking

2. OpenSSH permissions

\$ sudo nano /etc/ssh/sshd_config

*Insert these

PasswordAuthentication yes ChallengeResponseAuthentication no PermitRootLogin yes PubkeyAuthentication yes

*ChallengeResponseAuthentication no GSSAPIAuthentication yes GSSAPICleanupCredentials no

- *UsePAM yes
- *X11Forwarding yes
- *PrintMotd no

3. INSTALL DOCKER {ENGINE}

*UPDATE

\$ sudo apt-get update

\$ sudo apt-get install \
ca-certificates \
curl \
gnupg \
lsb-release

***ADD DOCKER GPG KEY**

\$ sudo mkdir -p /etc/apt/keyrings
\$ curl -fsSL https://download.docker.com/linux/debian/gpg |
sudo gpg --dearmor -o /etc/apt/keyrings/docker.gpg

*ADD DOCKER REPO

\$ echo \

"deb [arch= $(dpkg - print-architecture) signed-by=/etc/apt/keyrings/docker.gpg] https://download.docker.com/linux/debian \$

\$(lsb_release -cs) stable" | sudo tee /etc/apt/sources.list.d/docker.list > /dev/null

***UPDATE {AGAIN}**

\$ sudo apt-get update

3. INSTALL DOCKER {ENGINE}

***UPDATE {AGAIN}**

\$ sudo apt-get install docker-ce docker-ce-cli containerd.io docker-compose-plugin

*DOCKER PULL

- \$ sudo docker pull hello-world
- \$ sudo docker run hello-world

4. INSTALL PORTAINER CE {P:9000}

*PORTAINER DATABASE

\$ docker volume create portainer_data

*DOCKER PULL

\$ docker run -d -p 8000:8000 -p 9443:9443 -p 9000:9000 --name portainer --restart=al-ways -v /var/run/docker.sock:/var/run/docker.sock -v portainer_data:/data portainer/portainer-ce:latest

