

White Rabbit X — 完全ユーザーマニュアル

現在の EA ソースと set マニフェストから生成した正式リファレンス — EA 1.11 — 127 inputs — 3738 sets

範囲と正本

EA ソースが inputs、既定値、機能を定義し、マニフェストが各 set の状態、パス、SHA-256 を定義します。旧 Quantum 資料は履歴専用です。

EA SHA-256: D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973.

Manifest SHA-256:

E96B9E4050F8EA8B764E187BD6CC1E907AE2AE8C4A6489C9EF2D3317C6003F75.

自動生成資料。パラメータ識別子は EA と完全に一致します。

インストールと初回実行

一致する EX5 を導入し、Tester Inputs で set を読み、正確な銘柄を選び Journal を確認します。

シグナルとエントリー

6 エンジン reversal、signal/reference cross、baseline/reference cross を共有します。And は同じ確定足、All はいずれかを意味します。

- 12 のネイティブエンジン: MACD、EMA Cross、Momentum、Stochastic、TRIX、RSI、CCI、Williams %R、DeMarker、MFI、OsMA、Ichimoku。
- 確定足における AND/OR を明示した 7 エントリー方式。
- 独立した MTF、MA、ADX、ATR、news フィルター。
- 4 PositionSizeMode と equity/margin 保護。
- Stop、take、breakeven、trailing、reversal の決済。
- Dashboard、時間、言語、WFO を統合。
- EntryIndicator: MACD, EMA_Cross, Momentum, Stochastic, TRIX, RSI, CCI, WPR, DeMarker, MFI, OsMA, Ichimoku.
- EntryMethod: Reversal, SignalCross, ReferenceCross, ReversalAndSignalCross, ReversalAndReferenceCross, SignalAndReferenceCross, All.
- PositionSizeMode: Percentage, Monetary, FixedLot, FixedR.
- RecoveryMode: None, Martingale, DAlembert.
- GridMode: Disabled, SeparateProfit, UnifiedProfit.

フィルター

MTF は上位足 MACD 整合、MA、ADX、ATR volatility、news は独立です。追加すると標本が減少します。

News filter and CSV workflow

Live mode reads the MT5 Economic Calendar in broker-server time and blocks new entries if the calendar query fails. Backtests cannot read that live calendar: run MQL5 \ Scripts \ White Rabbit News Exporter on a live/demo chart, cover the entire test interval, and write NewsCSVFile to the terminal Common \ Files folder. The semicolon-delimited header is datetime;currency;importance;event_name, where importance 2 is moderate and 3 is high. Use the same broker/server timezone; for suffixed or

non-FX symbols set ExportMoedas and NewsMoedasManual explicitly. Manual currencies take precedence over automatic symbol parsing.

執行とポジション管理

spread、margin、volume step、tick size、stops/freeze 制約を確認し、Journal で結果を確認します。

Grid cycle and ATR spacing

Every additional grid leg is measured from the newest already-confirmed position on that side and must satisfy $ATR \times DistanciaMinima$. The initial order cannot recursively trigger another leg in the same calculation event; it becomes the anchor on the following cycle. Individual grid take-profits are disabled: Separate mode evaluates independent BUY/SELL cycles against frozen monetary targets and ends a side when it becomes flat; Unified evaluates the aggregate BUY+SELL basket and ends when both sides are flat. Realized commissions, swap, fees and stopped legs remain in the result while the corresponding cycle is open. The target triggers a close request, so actual exit costs and slippage can leave the final result slightly below it. Live cycle state is persisted across an EA restart. Grid is hedging-only and must be reoptimized after any EA, broker-contract or cost change.

決済スタック

Stop、ATR take、breakeven、ATR trailing、reversal exit は独立です。ReversalExitUseEntryFilters が決済フィルターを制御します。

リスクとリカバリー

PositionSizeMode は一つだけ選択します。Percentage/Fixed-R は stop 必須。Grid/Martingale/D'Alembert は研究用です。

時間、表示、WFO

ブローカーサーバー時刻を使い、日跨ぎと Saturday/Sunday に対応します。WFO は IS/OOS を定義します。

Diagnostics and supplied utilities

The Experts/ Journal tab is authoritative for rejected inputs, OrderCheck failures, news-calendar errors and close retries. Compile and run `SQL5 \ Scripts \ WhiteRabbit Filters SelfTest`; its final line must report zero failures. Use White Rabbit News Exporter to build the test CSV, then verify its date range, currencies, delimiter and Common \ Files location before a news-enabled backtest.

サイクル・ダッシュボードのテレメトリ

パネルはロット計算とバスケット決済と同じ状態スナップショットを使用します。

- tick の定期更新は毎秒 1 回までです。初期化と取引イベントは即時更新できます。
- Balance/Equity は口座全体です。Closed P&L は OnInit 以降の差分、Open P&L と positions は Symbol + Magic で絞った現在値です。
- Martingale は BUY/SELL 別に連続損失、サイクル損失回数・総額、recovered、deficit、deficit $\times$ Multiplicador の target を表示します。
- MaxMartingaleSteps 超過で hard reset し、旧 deficit を破棄して次注文を base lot にします。各側の保有は最大 1 です。
- D'Alembert は BUY/SELL の現在レベルと正規化した次ロットを表示します。

- Grid は legs/volume、コスト込み realized、open P&L、cycle P&L、開始時に固定した target、remaining を表示します。
- Anchor は直近の確定ポジションです。BUY は $\text{anchor} - \text{ATR} \times \text{DistanciaMinima}$ 未満、SELL は $\text{anchor} + \text{ATR} \times \text{DistanciaMinima}$ 超を厳密に要求し、進捗は ATR で示します。
- Separate は flat になった側だけ終了し、Unified は BUY/SELL 両方が flat で終了します。処理中注文は reset を遅らせます。
- Target は決済要求のトリガーです。実際の exit commission、fee、slippage により最終値が少し下回る場合があります。
- InterfaceLanguage は 11 言語を維持します。Auto は Tester で English、live で端末言語を使い、未翻訳 label は English にフォールバックします。

互換性と制約

これは保守的な規則で、ブローカー制限が優先されます。

- Percentage と Fixed-R は AtivarStop=true が必須です。
- Grid は Monetary/Fixed Lot、Recovery_None、hedging account のみです。
- Grid は take、正の DistanciaMinima、2 以上の上限が必要です。
- バasketが開いている間、そのサイクルの確定損失、swap、commission、fees は目標到達に必要な結果へ残り、単独レッグの利益では消えません。
- Grid_SeparateProfit では BUY/SELL のサイクルは独立します。一方の全ポジションがなくなるとその側のサイクルは終了し、次のエントリーは終了済み損失を持ち越さない新サイクルです。
- D'Alembert は Fixed Lot、Grid_Disabled、DAlembertStep>0 のみです。
- Martingale は MaxMartingaleSteps/MaxMartingaleLot に従います。
- OnOppositeOrder は hedging、両方向、grid 無効が必要です。
- News backtest は Common \ Files の CSV が必要です。
- 時間はブローカーサーバー基準です。
- suffix と銘柄仕様をブローカーごとに確認します。

検出された set ライブラリ

件数はファイルとマニフェストから取得します。set は研究仮説です。Counts and fingerprints were read at generation time.

Folder	Sets	Purpose
01_Forex	168	Per-asset baselines — Forex.
02_Metals	18	Per-asset baselines — Metals.
03_Cryptocurrencies	36	Per-asset baselines — Cryptocurrencies.
04_Indices_Energies	42	Per-asset baselines — Indices Energies.
05_US_Stocks_CFD	300	Per-asset baselines — US Stocks CFD.
06_Research_Matrix	935	Controlled one-axis research.
07_Entry_System_Matrix	3360	Indicator × entry method × management matrix.
08_Filter_Stack_Matrix	320	Signal-filter stack combinations.
09_Risk_Engine_Matrix	130	Compatible sizing, risk and recovery models.
10_Exit_Stack_Matrix	720	Exit-control stack combinations.

リスク警告

EA、set、過去結果は将来を保証しません。OOS と demo で検証してください。

全 inputs リファレンス

表はソース順です。区切り文字列も .set schema の一部です。

No.	Section	Subsection	Parameter	Type	Default	Source description	Enum options	Operational notes	
1	General	—	NomedaEs trategia	string	"White Rabbit X"	Strategy Name	—	Use within its declared section and validate the complete combinati on.	
2	Entries, Signal and Position M anagemen t	—	TimeFram e	ENUM_AL LOWED_TI MEFRAME S	M1	Entry timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Signal evaluation is gated to one decision per closed bar of this timeframe .	
3	Entries, Signal and Position M anagemen t	Entry Indicator	myBlankS paceEntryI ndicator	string	""	\	\	===== ===== ==== Entry Indicator ===== ===== ==== \	\
4	Entries, Signal and Position M anagemen t	Entry Indicator	EntryIndic ator	ENUM_EN TRY_INDIC ATOR	EntryIndic ator_MAC D	Selects the indicator used by Entry Method	EntryIndic ator_MAC D, EntryIn dicator_E MA_Cross , EntryIndi cator_Mo mentum, EntryIndic ator_Stoc hastic, Ent ryIndicato r_TRIX, En tryIndicat or_RSI, En tryIndicat or_CCI, En tryIndicat or_WPR, E ntryIndica tor_DeMar ker, EntryI ndicator_ MFI, EntryI ndicator_ OsMA, Ent ryIndicato r_Ichimok u	Selects the engine; Fast_EMA, Slow_EMA and MACD _SMA are reused by that engine.	

5	Entries, Signal and Position M anagemen t	Entry Indicator	InpApplied Price	ENUM_AP PLIED_PRI CE	PRICE_CL OSE	Applied price used by the selected indicator	—	Use within its declared section and validate the complete combinati on.	
6	Entries, Signal and Position M anagemen t	Entry Indicator	Fast_EMA	int	12	First period: MA CD/EMA fast; oscillator period; Stochastic %K; Ichimoku Tenkan	—	First sequential period; for Ichimoku this is Tenkan.	
7	Entries, Signal and Position M anagemen t	Entry Indicator	Slow_EMA	int	26	Second period: MA CD/EMA slow; Ichimoku Kijun	—	Second sequential period; for Ichimoku this is Kijun.	
8	Entries, Signal and Position M anagemen t	Entry Indicator	MACD_SM A	int	9	Third period: MACD signal; oscillator signal; Stochastic %D; Ichimoku Senkou B	—	Third sequential period; for Ichimoku this is Senkou Span B.	
9	Entries, Signal and Position M anagemen t	Entry Method	myBlanks pace1	string	""	\	\	===== ===== ===== Entry Method = ===== ===== ===== = \	\

10	Entries, Signal and Position Management	Entry Method	EntryMethod	ENUM_ENTRY_TRIGGER_MODE	EntryTrigger_All	Reversal, signal cross, reference cross or their combinations	EntryTrigger_Reversal, EntryTrigger_SignalCross, EntryTrigger_ReferenceCross, EntryTrigger_ReversalAndSignalCross, EntryTrigger_ReversalAndReferenceCross, EntryTrigger_SignalAndReferenceCross, EntryTrigger_All	And modes require both events on the same closed bar; All is OR.	
11	Entries, Signal and Position Management	ATR Settings	myBlankSpace42	string	""	\	\	===== ===== ===== ATR Settings = ===== ===== ===== \	\
12	Entries, Signal and Position Management	ATR Settings	ATR_Time Frame	ENUM_ALLOWED_TIMEFRAMES	M1	Time Frame ATR	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
13	Entries, Signal and Position Management	ATR Settings	PeriodoATR	int	14	ATR Period	—	Use within its declared section and validate the complete combination.	
14	Entries, Signal and Position Management	Stop Loss	myBlankSpace4s2	string	""	\	\	===== ===== ===== = Stop Loss === ===== ===== ===== \	\

15	Entries, Signal and Position Management	Stop Loss	AtivarStop	bool	true	Enable Stop Loss	—	Required by Percentage and Fixed-R sizing; recommended for every non-grid baseline.	
16	Entries, Signal and Position Management	Stop Loss	VelaStop	int	0	Stop Loss Candle	—	Use within its declared section and validate the complete combination.	
17	Entries, Signal and Position Management	Stop Loss	Stop	double	3	Stop Loss ATR Multiplier	—	Use within its declared section and validate the complete combination.	
18	Entries, Signal and Position Management	Take Profit	myBlankSpace101	string	""	\	\	===== ===== ===== Take Profit === ===== ===== ==== \	\
19	Entries, Signal and Position Management	Take Profit	TakeOrganico	bool	false	Enable Organic ATR Take Profit	—	Use within its declared section and validate the complete combination.	
20	Entries, Signal and Position Management	Take Profit	AtivarTake	bool	true	Enable Take Profit	—	Required by supported grid operation.	

21	Entries, Signal and Position Management	Take Profit	VelaTake	int	0	Take Profit Candle	—	Use within its declared section and validate the complete combination.	
22	Entries, Signal and Position Management	Take Profit	Take	double	3	Take Profit ATR Multiplier	—	Use within its declared section and validate the complete combination.	
23	Signal Filters	MTF Alignment	myBlankSpaceMTF	string	""	\	\	===== ===== ===== MTF Alignment ===== ===== ===== \	\
24	Signal Filters	MTF Alignment	AtivarFilterMTF	bool	false	Enable MTF Filter	—	Higher-timeframe alignment uses the EA's MACD trend layer.	
25	Signal Filters	MTF Alignment	MTF_RequiresAmbo	bool	false	Require Both Higher Timeframes Aligned	—	Use within its declared section and validate the complete combination.	
26	Signal Filters	Moving Average Filter	myBlankSpaceMA	string	""	\	\	===== ===== == Moving Average Filter == ===== ===== \	\

27	Signal Filters	Moving Average Filter	AtivarFiltroMA	bool	false	Enable Moving Average Filter	—	Use within its declared section and validate the complete combination.	
28	Signal Filters	Moving Average Filter	MA_TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	MA Timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
29	Signal Filters	Moving Average Filter	MA_Period	int	200	MA Period	—	Use within its declared section and validate the complete combination.	
30	Signal Filters	Moving Average Filter	MA_Method	ENUM_MA_METHOD	MODE_EMA	MA Method	—	Use within its declared section and validate the complete combination.	
31	Signal Filters	Moving Average Filter	MA_AppliedPrice	ENUM_APPLIED_PRICE	PRICE_CLOSE	Applied Price	—	Use within its declared section and validate the complete combination.	
32	Signal Filters	Moving Average Filter	MetodoMA	MetodoFiltroMA	MA_PrecoEmclinacao	Price and Slope Rule	MA_ApenasPreco, MA_ApenasInclinacao, MA_PrecoEmclinacao, MA_PrecoOuInclinacao	Use within its declared section and validate the complete combination.	

33	Signal Filters	Moving Average Filter	SentidoMA	SentidoFilterMA	MA_Tendencia	Trend or Reversal Direction	MA_Tendencia, MA_Reversao	Use within its declared section and validate the complete combination.	
34	Signal Filters	Moving Average Filter	MA_Slope Lookback	int	3	Slope Lookback Bars	—	Use within its declared section and validate the complete combination.	
35	Signal Filters	ADX Filter	myBlankSpaceMA1	string	""	\	\	===== ===== ===== ADX Filter ===== ===== = \	\
36	Signal Filters	ADX Filter	AtivarFilterADX	bool	false	Enable ADX Trend Strength Filter	—	Use within its declared section and validate the complete combination.	
37	Signal Filters	ADX Filter	ADX_Time Frame	ENUM_ALLOWED_TIMEFRAMES	M1	ADX Timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
38	Signal Filters	ADX Filter	ADX_Period	int	14	ADX Period	—	Use within its declared section and validate the complete combination.	

39	Signal Filters	ADX Filter	ADX_Limit	double	25	Minimum ADX Value	—	Use within its declared section and validate the complete combination.	
40	Signal Filters	ADX Filter	MetodoADX	MetodoFiltroADX	ADX_ApenasForca	Strength or Strength Plus Direction	ADX_ApenasForca, ADX_ForceMaisDirecaoDI	Use within its declared section and validate the complete combination.	
41	Signal Filters	Volatility Filter	myBlankSpaceVolatility	string	""	\	\	===== ===== ===== Volatility Filter === ===== ===== = \	\
42	Signal Filters	Volatility Filter	EntradaATR	bool	false	Enable ATR Volatility Filter	—	Use within its declared section and validate the complete combination.	
43	Signal Filters	Volatility Filter	VolatilityFilter	ENUM_VOLATILITY_MODE	VOL_HIGH	Trade Volatility Condition	VOL_LOW, VOL_HIGH	Use within its declared section and validate the complete combination.	
44	Signal Filters	News Filter	myBlankSpaceNews	string	""	\	\	===== ===== ===== News Filter === ===== ===== ==== \	\

45	Signal Filters	News Filter	AtivarFiltroNoticias	bool	false	Enable News Filter	—	Live calendar errors block new entries; backtests require the exported CSV under Common \ \ Files.	
46	Signal Filters	News Filter	NewsSomenteAltoImpacto	bool	false	High Impact Only	—	Use within its declared section and validate the complete combination.	
47	Signal Filters	News Filter	NewsMinutosAntes	int	15	Minutes Blocked Before Event	—	Use within its declared section and validate the complete combination.	
48	Signal Filters	News Filter	NewsMinutosDepois	int	15	Minutes Blocked After Event	—	Use within its declared section and validate the complete combination.	
49	Signal Filters	News Filter	NewsMoedasManual	string	""	Manual Currencies (e.g. "USD ,EUR"); empty = auto by symbol	—	When non-empty, overrides automatic currency extraction; required for most suffixes/non-FX symbols.	

50	Signal Filters	News Filter	NewsCSVFile	string	"WhiteRabbit_News.csv"	Common \ \ Files CSV for Backtests	—	Semicolon CSV in Common \ \ Files: date time;currency;importance;event_name, using broker-server time.	
51	Exit Management	—	AtivarBreakeven	bool	true	Enable Breakeven	—	Use within its declared section and validate the complete combination.	
52	Exit Management	—	Breakeven Distancia	double	1.0	Breakeven Distance (SL or ATR Stop Multiplier)	—	Use within its declared section and validate the complete combination.	
53	Exit Management	ATR Trailing	myBlankSpace46	string	""	\	\	===== ===== ===== ATR Trailing == ===== ===== ===== \	\
54	Exit Management	ATR Trailing	AtivarTrail ATR	bool	false	Enable ATR Trailing Stop	—	Use within its declared section and validate the complete combination.	
55	Exit Management	ATR Trailing	MetodoDe Calculo	Candlestick type	CandleClose	Trailing Price Source	CandleOpen, CandleClose, CandleHigh, CandleLow, Preco	Use within its declared section and validate the complete combination.	

56	Exit Management	ATR Trailing	TrailVela	int	0	Trailing Candle	—	Use within its declared section and validate the complete combination.	
57	Exit Management	ATR Trailing	Trail	double	3	Trail	—	Use within its declared section and validate the complete combination.	
58	Exit Management	Reversal Exit	myBlankSpace10	string	""	\	\	===== ===== ===== Reversal Exit ===== ===== ===== == \	\
59	Exit Management	Reversal Exit	ReversalExitMode	ENUM_REVERSAL_EXIT_MODE	ReversalExit_OnIndicatorSignal	Declared at source line 319.	ReversalExit_Disabled, ReversalExit_OnOppositeOrder, ReversalExit_OnIndicatorSignal	OnOppositeOrder requires a hedging account, both sides and grid disabled.	
60	Exit Management	Reversal Exit	ReversalExitUseEntryFilters	bool	false	Apply entry filters to indicator exits	—	False uses the raw opposite indicator signal; true also requires entry filters.	
61	Risk and Position Size	—	TradeCapitalPercentage	double	100	Percentage of Total Capital Allocated to EA	—	Allocation must be positive and no greater than the whole EA capital base.	

62	Risk and Position Size	—	PositionSizeMode	ENUM_POSITION_SIZE_MODE	PositionSize_FixedLot	Declared at source line 351.	PositionSize_Percentage, PositionSize_Monetary, PositionSize_FixedLot, PositionSize_FixedR	Exactly one model is active; compatibility depends on stop and grid selections.	
63	Risk and Position Size	—	PositionSizeValue	double	0.01	Percentage=% risk; Monetary=currency per 1.00 lot; Fixed Lot=lots; Fixed R=% of base capital per 1R	—	Meaning changes with PositionSizeMode; never compare raw values across modes.	
64	Risk and Position Size	Fixed-R Controls	myBlankSpaceRF	string	""	\	\	===== ===== ==== Fixed-R Controls = ===== ===== ==== \	\
65	Risk and Position Size	Fixed-R Controls	CapitalBaseR	double	0	Base Capital for 1R (0 = balance at OnInit)	—	Zero captures balance at initialization; Fixed-R only.	
66	Risk and Position Size	Fixed-R Controls	MaxRiskTradeR	double	0	Maximum Risk per Trade in R (0 = no cap)	—	Zero disables this additional Fixed-R cap.	
67	Risk and Position Size	Daily Loss Limit	myBlankSpaceDL	string	""	\	\	===== ===== ==== Daily Loss Limit === ===== ===== == \	\
68	Risk and Position Size	Daily Loss Limit	DailyLossLimitPercent	double	0	Maximum Daily Loss Percentage (0 = disabled)	—	Zero disables the daily limit; use a value below a total account loss.	

69	Risk and Position Size	Equity/Margin Protection	myBlankSpaceRiskProtection	string	""	\	\	===== ===== Equity/Margin Protection ===== ===== = \	\
70	Risk and Position Size	Equity/Margin Protection	MaxEquity Drawdown Percent	double	30.0	Maximum EA drawdown before closing positions (0 = disabled)	—	Zero disables the EA equity stop.	
71	Risk and Position Size	Equity/Margin Protection	MinFreeMarginPercent	double	50.0	Minimum free margin to preserve after a new entry (0 = disabled)	—	Zero disables the post-entry free-margin reserve.	
72	Grid and Recovery	—	Recovery Mode	ENUM_RECOVERY_MODE	Recovery_None	Declared at source line 368.	Recovery_None, Recovery_Martingale, Recovery_D'Alembert	None, Martingale or D'Alembert are mutually exclusive.	
73	Grid and Recovery	Recovery Target	myBlankSpace457	string	""	\	\	===== ===== ===== Recovery Target == ===== ===== == \	\
74	Grid and Recovery	Recovery Target	Multiplicador	double	1	Martingale or Grid Target Profit Multiplier	—	Recovery/grid target multiplier; validate a value greater than one where escalation is intended.	
75	Grid and Recovery	Martingale Limits	myBlankSpace16	string	""	\	\	===== ===== ===== Martingale Limits == ===== ===== == \	\

76	Grid and Recovery	Martingale Limits	MaxMartingaleSteps	int	0	Consecutive Losses Before Reset (0 = no limit)	—	Zero means no step limit; exceeding a positive limit hard-resets the old deficit and forces the next order to the base lot.	
77	Grid and Recovery	Martingale Limits	MaxMartingaleLot	double	0.0	Maximum Martingale or D'Alembert Lot (0 = broker limit only)	—	Zero means broker maximum only.	
78	Grid and Recovery	D'Alembert Settings	myBlankSpace_dal	string	""	\	\	===== ===== === D'Alembert Settings = ===== ===== === \	\
79	Grid and Recovery	D'Alembert Settings	D'AlembertStep	double	0.01	Lot Increment per Loss for D'Alembert	—	Must be positive; supported with Fixed Lot and grid disabled.	
80	Grid and Recovery	Grid Settings	myBlankSpace17	string	""	\	\	===== ===== ===== Grid Settings = ===== ===== ===== \	\
81	Grid and Recovery	Grid Settings	GridMode	ENUM_GRID_MODE	Grid_Disabled	Declared at source line 385.	Grid_Disabled, Grid_SeparateProfit, Grid_UnifiedProfit	Supported with Monetary or Fixed Lot sizing, Recovery_None and a hedging account; targets are frozen per cycle.	

82	Grid and Recovery	Grid Settings	Use ATR Grid	bool	false	Use ATR Only as Grid Signal	—	Research switch; require an existing basket anchor before adding a grid leg.	
83	Grid and Recovery	Grid Settings	ATR Distance Minima	double	2	ATR Distance Multiplier for Next Grid Order	—	Positive ATR-distance multiplier between grid entries.	
84	Trading Schedule	Trading Hours	Trading Hours	string	""	\	\	===== ===== ===== Trading Hours === ===== ===== === \	\
85	Trading Schedule	Trading Hours	Trading Hours	bool	false	Close Positions Outside Trading Hours	—	When enabled, positions are closed whenever server time is outside the interval.	
86	Trading Schedule	Trading Hours	TOD_From_Hour	int	00	Trading Start Hour	—	Use within its declared section and validate the complete combination.	
87	Trading Schedule	Trading Hours	TOD_From_Min	int	00	Trading Start Minute	—	Use within its declared section and validate the complete combination.	

88	Trading Schedule	Trading Hours	TOD_To_Hour	int	23	Trading End Hour	—	Use within its declared section and validate the complete combination.	
89	Trading Schedule	Trading Hours	TOD_To_Min	int	55	Trading End Minute	—	Use within its declared section and validate the complete combination.	
90	Trading Schedule	Trading Days	myBlankSpaceTradingDays	string	""	\	\	===== ===== ===== Trading Days === ===== ===== ==== \	\
91	Trading Schedule	Trading Days	TradeMonday	bool	true	Allow Trading on Monday	—	Use within its declared section and validate the complete combination.	
92	Trading Schedule	Trading Days	TradeTuesday	bool	true	Allow Trading on Tuesday	—	Use within its declared section and validate the complete combination.	
93	Trading Schedule	Trading Days	TradeWednesday	bool	true	Allow Trading on Wednesday	—	Use within its declared section and validate the complete combination.	

94	Trading Schedule	Trading Days	TradeThursday	bool	true	Allow Trading on Thursday	—	Use within its declared section and validate the complete combination.	
95	Trading Schedule	Trading Days	TradeFriday	bool	true	Allow Trading on Friday	—	Use within its declared section and validate the complete combination.	
96	Trading Schedule	Trading Days	TradeSaturday	bool	false	Allow Trading on Saturday	—	Explicit weekend permission; useful only when the broker symbol trades Saturday.	
97	Trading Schedule	Trading Days	TradeSunday	bool	false	Allow Trading on Sunday	—	Explicit weekend permission; useful only when the broker symbol trades Sunday.	
98	General Settings	Market Execution	myBlankSpaceExecution	string	""	\	\	===== ===== ==== Market Execution ===== ===== ===== \	\
99	General Settings	Market Execution	MaxSpread	double	0	Maximum Allowed Spread for New Trades	—	Zero disables the entry spread ceiling.	
100	General Settings	Market Execution	MaxSlippage	int	10	Slippage, ajustado no OnInit	—	Use within its declared section and validate the complete combination.	

101	General Settings	Position Exposure	myBlankSpaceExposure	string	""	\	\	===== ===== ===== Position Exposure ===== ===== ==== \	\
102	General Settings	Position Exposure	MaxLongTrades	int	1	Maximum Simultaneous BUY Positions	—	Zero disables BUY entries; grid sides require zero or at least two, while Martingale permits at most one.	
103	General Settings	Position Exposure	MaxShort Trades	int	1	Maximum Simultaneous SELL Positions	—	Zero disables SELL entries; grid sides require zero or at least two, while Martingale permits at most one.	
104	General Settings	Position Exposure	Hedging	bool	false	Allow Hedging	—	Does not change the account type; the real MT5 account must also support hedging.	
105	General Settings	Identity and Interface	myBlankSpaceInterface	string	""	\	\	===== ===== = Identity and Interface ===== ===== == \	\
106	General Settings	Identity and Interface	MagicNumber	int	384457	Magic Number	—	Must be unique for each independent strategy/symbol scope.	

107	General Settings	Identity and Interface	ModificationSafetyPoints	int	0	Optional extra distance beyond broker limits and current spread	—	Additional points beyond broker distance/spread constraints.	
108	General Settings	Identity and Interface	InterfaceLanguage	ENUM_INTERFACE_LANGUAGE	Language_Auto	Live chart interface language	Language_Auto, Language_English, Language_Portuguese, Language_Russian, Language_Chinese, Language_Spanish, Language_Japanese, Language_German, Language_Korean, Language_French, Language_Italian, Language_Turkish	Eleven live/visual UI languages; Auto uses English in Tester and untranslated labels fall back to English.	
109	General Settings	Chart Dashboard	myBlankSpaceDashboard	string	""	\	\	===== ===== ==== Chart Dashboard ===== ===== ==== \	\
110	General Settings	Chart Dashboard	EnableChartDashboard	bool	true	Show visual P&L panel on live and visual tester charts	—	Live/visual panel; periodic tick refresh is capped at once per second.	
111	General Settings	Chart Dashboard	Dashboard Corner	ENUM_BASSE_CORNER	CORNER_LEFT_UPPER	Dashboard chart corner	—	Use within its declared section and validate the complete combination.	

112	General Settings	Chart Dashboard	Dashboard OffsetX	int	12	Horizontal offset in pixels	—	Use within its declared section and validate the complete combination.	
113	General Settings	Chart Dashboard	Dashboard OffsetY	int	24	Vertical offset in pixels	—	Use within its declared section and validate the complete combination.	
114	General Settings	Chart Dashboard	ShowClosedDealLabels	bool	true	Show monetary and percentage result at each closed trade	—	Use within its declared section and validate the complete combination.	
115	General Settings	Chart Dashboard	MaxVisibleDealLabels	int	120	Maximum closed-trade labels kept on chart	—	Use within its declared section and validate the complete combination.	
116	General Settings	Chart Dashboard	ClosedDealLabelFontSize	int	10	Closed-trade label font size	—	Use within its declared section and validate the complete combination.	
117	General Settings	Chart Dashboard	ApplyEmbeddedChartTheme	bool	true	Apply the White Rabbit X clean chart style on every machine	—	Use within its declared section and validate the complete combination.	

118	Optimization (WFO)	—	AtivarWFO	bool	false	Enable WFO	—	Enables the internal WFO boundary logic; still requires an external chronological process.	
119	Optimization (WFO)	—	MetodoDeEntradaWFO	WFO_TIPO	Insample	Optimization Mode	Insample, InSampleAndOutSample	Use within its declared section and validate the complete combination.	
120	Optimization (WFO)	—	input_end_date	string	"2025.02.28"	Backtest End Date (manual)	—	Manual tester end date; keep synchronized with the selected test range.	
121	Optimization (WFO)	WFO Periods	myBlankSpaceWFOPeriods	string	""	\	\	===== ===== ===== WFO Periods == ===== ===== ===== \	\
122	Optimization (WFO)	WFO Periods	wfo_windowSize	WFO_TIME_PERIOD	Ano	In-Sample Window Size	Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom	Use within its declared section and validate the complete combination.	
123	Optimization (WFO)	WFO Periods	wfo_customWindowSizeDays	int	0	Custom Window Size in Days (0 = unused)	—	Use within its declared section and validate the complete combination.	

124	Optimizati on (WFO)	WFO Periods	wfo_step Size	WFO_TIM E_PERIOD	Semestre	Out-of-Sa mple Step Size	Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom	Use within its declared section and validate the complete combinati on.	
125	Optimizati on (WFO)	WFO Periods	wfo_cust omStepSiz ePercent	int	0	Custom Step Size in Days or Percentag e	—	Custom step: posit ive=perce ntage of IS; negativ e=fixed number of OOS days (for example -61).	
126	Optimizati on (WFO)	Optimizati on Criterion	myBlankS pace4447	string	""	\	\	===== ===== = Optimiz ation Criterion = ===== ===== = \	\

127	Optimization (WFO)	Optimization Criterion	selectedFormula	CustomFormulaType	Formula_ProfitPerTradeAdjustedByDD	Custom Optimization Formula	Formula_None, Formula_GridSurvivalScore, Formula_Profit, Formula_ProfitWinTradeDD, Formula_EfficiencyRelativeToDeposit, Formula_AdjustedEfficiencyForGrid, Formula_ProfitRelativeToDDAndDeposit, Formula_ProfitPerTradeAdjustedByDD, Formula_SharpeAdjustedByDD, Formula_PessimisticProfit, Formula_ResilienceToDrawdown, Formula_ReturnUniformity, Formula_SystemRobustness, Formula_LevainCompositeScore, Formula_SomaR	Optimization on criterion only; inspect stability and OOS results before selection.	
-----	--------------------	------------------------	-----------------	-------------------	------------------------------------	-----------------------------	---	---	--

EA SHA-256: D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973 **EA**
version: 1.12