

White Rabbit X — Complete User Manual

Authoritative reference generated from the current EA source and set manifest — EA 1.11 — 127 inputs — 3738 sets

Scope and source of truth

The EA source defines the input schema, defaults, enumerations and current feature surface. The set manifest defines every preset, family, status, path and integrity hash. Older Quantum material is historical only and must not be used to operate the current release.

EA SHA-256: D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973.

Manifest SHA-256: E96B9E4050F8EA8B764E187BD6CC1E907AE2AE8C4A6489C9EF2D3317C6003F75.

Generated material. Parameter identifiers remain exactly as declared by the EA.

Installation and first run

Compile or install the matching EX5, copy presets into the terminal Tester profile, select the correct broker symbol, load one set in Strategy Tester Inputs and verify every validation message.

Signal engines and entry methods

The selected entry indicator supplies three universal events: reversal, signal/reference cross and baseline/reference cross. Combination methods whose names contain “And” require their events on the same closed bar; “All” accepts any of the three events. A position is dispatched at most once per side for the selected signal bar.

- Twelve native engines: MACD, EMA Cross, Momentum, Stochastic, TRIX, RSI, CCI, Williams %R, DeMarker, MFI, OsMA and Ichimoku.
- Seven trigger methods with explicit reversal, cross, AND and OR semantics.
- Independent MTF/MACD, moving-average, ADX, ATR-volatility and news filters.
- Percentage, Monetary, Fixed Lot or Fixed-R sizing plus account-level risk protection.
- Stop, ATR take, breakeven, trailing and reversal controls form the exit stack.
- Dashboard, deal labels, languages, weekly schedule and WFO complete the operating layer.
- EntryIndicator: MACD, EMA_Cross, Momentum, Stochastic, TRIX, RSI, CCI, WPR, DeMarker, MFI, OsMA, Ichimoku.
- EntryMethod: Reversal, SignalCross, ReferenceCross, ReversalAndSignalCross, ReversalAndReferenceCross, SignalAndReferenceCross, All.
- PositionSizeMode: Percentage, Monetary, FixedLot, FixedR.
- RecoveryMode: None, Martingale, DAlembert.
- GridMode: Disabled, SeparateProfit, UnifiedProfit.

Filters

MTF alignment is a MACD higher-timeframe alignment layer. MA, ADX, ATR-volatility and news are independent filters. Enabling more filters narrows the sample; optimize stacks as hypotheses, not as a promise of higher quality.

News filter and CSV workflow

Live mode reads the MT5 Economic Calendar in broker-server time and blocks new entries if the calendar query fails. Backtests cannot read that live calendar: run MQL5\Scripts\White Rabbit News Exporter on a live/demo chart, cover the entire test interval, and write NewsCSVFile to the terminal Common\Files folder. The semicolon-delimited header is datetime;currency;importance;event_name, where importance 2 is moderate and 3 is high. Use the same broker/server timezone; for suffixed or non-FX symbols set ExportMoedas and NewsMoedasManual explicitly. Manual currencies take precedence over automatic symbol parsing.

Execution and position management

Spread, margin, broker volume steps, tick size, stops level and freeze level affect execution. Protective prices are part of the entry request when enabled. Closing requests can require a later retry, so inspect the Journal and never infer execution only from a visual signal.

Grid cycle and ATR spacing

Every additional grid leg is measured from the newest already-confirmed position on that side and must satisfy $ATR \times DistanciaMinima$. The initial order cannot recursively trigger another leg in the same calculation event; it becomes the anchor on the following cycle. Individual grid take-profits are disabled: Separate mode evaluates independent BUY/SELL cycles against frozen monetary targets and ends a side when it becomes flat; Unified evaluates the aggregate BUY+SELL basket and ends when both sides are flat. Realized commissions, swap, fees and stopped legs remain in the result while the corresponding cycle is open. The target triggers a close request, so actual exit costs and slippage can leave the final result slightly below it. Live cycle state is persisted across an EA restart. Grid is hedging-only and must be reoptimized after any EA, broker-contract or cost change.

Exit stack

Stop loss, organic ATR take profit, breakeven, ATR trailing and reversal exit are separate controls. Indicator reversal exits use the opposite raw signal by default; enable ReversalExitUseEntryFilters only when the entry filters must also confirm the exit.

Risk and recovery

Choose one PositionSizeMode. Percentage and Fixed-R require a valid stop. Grid, Martingale and D'Alembert are recovery research modes, not independent position-size modes. Exposure limits, daily loss, equity drawdown and minimum free margin are hard safety constraints.

Schedule, interface and WFO

Trading hours use broker server time and may cross midnight. Trading days include explicit Saturday and Sunday controls. The live/visual dashboard is optional. WFO inputs delimit the in-sample window, out-of-sample step and optimization criterion.

Diagnostics and supplied utilities

The Experts/Journal tab is authoritative for rejected inputs, OrderCheck failures, news-calendar errors and close retries. Compile and run MQL5\Scripts\WhiteRabbit Filters SelfTest; its final line must report zero failures. Use White Rabbit News Exporter to build the test CSV, then verify its date range, currencies, delimiter and Common\Files location before a news-enabled backtest.

Cycle-dashboard telemetry

The panel uses the same state snapshots used by position sizing and basket closure.

- Periodic tick refresh is capped at once per second; initialization and trade events can request an immediate refresh.

- Balance and Equity cover the whole account. Closed P&L is the delta since OnInit, while open P&L and positions are current snapshots; these strategy metrics are filtered by Symbol + Magic.
- Martingale reports, independently for BUY and SELL, consecutive losses, cycle loss count and gross amount, recovered value, outstanding deficit and target equal to deficit × Multiplicador.
- Exceeding MaxMartingaleSteps performs a hard Martingale reset: the old deficit is discarded and the next order uses the base lot. Martingale permits at most one open position per side.
- D'Alembert reports the current level and normalized next lot for BUY and SELL.
- Grid reports legs and volume, realized result including costs, open P&L, total cycle P&L, the monetary target frozen at cycle start and the remaining amount.
- The Grid anchor is the most recent confirmed position. BUY triggers strictly below anchor – ATR × DistanciaMinima; SELL strictly above anchor + ATR × DistanciaMinima. Progress is adverse distance in ATR versus the threshold.
- In Separate mode, becoming flat ends only that side's cycle; in Unified mode, the cycle ends when both BUY and SELL are flat. In-flight managed orders delay the reset.
- The target triggers a close request. Actual exit commission, fees and slippage can leave the final result slightly below that target.
- InterfaceLanguage preserves 11 UI languages. Auto uses English in the Tester and the terminal language live; a label without a specific translation falls back to English.

Supported combinations and restrictions

These are conservative operating rules for the current architecture. A broker can impose stricter limits, and a successful backtest does not override an incompatible account mode.

- PositionSize_Percentage and PositionSize_FixedR require AtivarStop=true and a calculable stop.
- Grid supports only PositionSize_Monetary or PositionSize_FixedLot, Recovery_None and a real hedging account.
- Grid requires AtivarTake=true, DistanciaMinima>0 and an active side limit of zero or at least two positions.
- Grid_SeparateProfit manages each side; Grid_UnifiedProfit manages the aggregate cycle result.
- While a basket remains open, its realized losses, swap, commission and fees remain included in the result still required to reach the target; profit from one isolated leg does not erase those costs.
- In Grid_SeparateProfit, BUY and SELL have independent cycles. If every position on one side disappears, that side's cycle ends; a later entry starts a new cycle without carrying the closed deficit forward.
- Recovery_DAlembert is restricted to Fixed Lot, Grid_Disabled and DAlembertStep>0.
- Recovery_Martingale observes MaxMartingaleSteps and MaxMartingaleLot; zero means no additional cap.
- ReversalExit_OnOppositeOrder requires a hedging account, Hedging=true, both sides enabled and grid disabled.
- News backtests require NewsCSVFile under Common\Files; NewsMoedasManual takes precedence over auto-detection.
- Schedules use broker server time; overnight intervals and weekend controls require explicit tests.
- Revalidate symbol suffix, contract size, tick value, minimum volume and costs for every broker.

Discovered set library

Every .set file is a research or optimization hypothesis. Counts below come from the current filesystem and manifest; they are not embedded in this document template. Counts and fingerprints were read at generation time.

Folder	Sets	Purpose
01_Forex	168	Per-asset baselines — Forex.
02_Metals	18	Per-asset baselines — Metals.
03_Cryptocurrencies	36	Per-asset baselines — Cryptocurrencies.
04_Indices_Energies	42	Per-asset baselines — Indices Energies.
05_US_Stocks_CFD	300	Per-asset baselines — US Stocks CFD.
06_Research_Matrix	935	Controlled one-axis research.
07_Entry_System_Matrix	3360	Indicator × entry method × management matrix.
08_Filter_Stack_Matrix	320	Signal-filter stack combinations.
09_Risk_Engine_Matrix	130	Compatible sizing, risk and recovery models.
10_Exit_Stack_Matrix	720	Exit-control stack combinations.

Risk warning

No EA, preset, indicator, optimization or historical result guarantees future performance. Validate symbol mapping, costs, execution, out-of-sample data and forward demo behavior before assuming financial risk.

Complete input reference

The table below is generated in declaration order. Layout separator strings are part of the .set schema and must remain present even though they do not change trading logic. The Source description column is copied verbatim from the .mq5 file in English for direct auditability.

No.	Section	Subsection	Parameter	Type	Default	Source description	Enum options	Operational notes	
1	General	—	NomedaEs trategia	string	"White Rabbit X"	Strategy Name	—	Use within its declared section and validate the complete c ombination .	
2	Entries, Signal and Position M anagement	—	TimeFrame	ENUM_AL LOWED_TI MEFRAME S	M1	Entry timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Signal evaluation is gated to one decision per closed bar of this timeframe.	
3	Entries, Signal and Position M anagement	Entry Indicator	myBlankSp aceEntryIn dicator	string	""	\	\	===== ===== == Entry Indicator = ===== ===== =\\	\
4	Entries, Signal and Position M anagement	Entry Indicator	EntryIndica tor	ENUM_EN TRY_INDI CATOR	EntryIndica tor_MACD	Selects the indicator used by Entry Method	EntryIndica tor_MACD, EntryIndica tor_EMA Cross, Entr yIndicator_ Momentum , EntryIndic ator_Stoch astic, Entry Indicator_T RIX, EntryI ndicator_R SI, EntryIn dicator_CC I, EntryIndi cator_WPR , EntryIndic ator_DeMa rker, EntryI ndicator_M FI, EntryIn dicator_Os MA, EntryI ndicator_Ic himoku	Selects the engine; Fast_EMA, Slow_EMA and MACD _SMA are reused by that engine.	
5	Entries, Signal and Position M anagement	Entry Indicator	InpApplied Price	ENUM_AP PLIED_PRI CE	PRICE_CL OSE	Applied price used by the selected indicator	—	Use within its declared section and validate the complete c ombination .	

6	Entries, Signal and Position Management	Entry Indicator	Fast_EMA	int	12	First period: MA CD/EMA fast; oscillator period; Stochastic %K; Ichimoku Tenkan	—	First sequential period; for Ichimoku this is Tenkan.	
7	Entries, Signal and Position Management	Entry Indicator	Slow_EMA	int	26	Second period: MA CD/EMA slow; Ichimoku Kijun	—	Second sequential period; for Ichimoku this is Kijun.	
8	Entries, Signal and Position Management	Entry Indicator	MACD_SMA	int	9	Third period: MACD signal; oscillator signal; Stochastic %D; Ichimoku Senkou B	—	Third sequential period; for Ichimoku this is Senkou Span B.	
9	Entries, Signal and Position Management	Entry Method	myBlankSpace1	string	""	\	\	===== ===== ===== Entry Method == ===== ===== =====\	\
10	Entries, Signal and Position Management	Entry Method	EntryMethod	ENUM_ENTRY_TRIGGER_MODE	EntryTrigger_All	Reversal, signal cross, reference cross or their combinations	EntryTrigger_Reversal, EntryTrigger_SignalCross, EntryTrigger_ReferenceCross, EntryTrigger_ReversalAndSignalCross, EntryTrigger_ReversalAndReferenceCross, EntryTrigger_SignalAndReferenceCross, EntryTrigger_All	And modes require both events on the same closed bar; All is OR.	

11	Entries, Signal and Position Management	ATR Settings	myBlankSpace42	string	""	\	\	===== ===== ==== ATR Settings == ===== ===== =====\	\
12	Entries, Signal and Position Management	ATR Settings	ATR_Time Frame	ENUM_ALLOWED_TIMEFRAME S	M1	Time Frame ATR	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
13	Entries, Signal and Position Management	ATR Settings	PeriodoATR	int	14	ATR Period	—	Use within its declared section and validate the complete combination.	
14	Entries, Signal and Position Management	Stop Loss	myBlankSpace4s2	string	""	\	\	===== ===== ===== Stop Loss ===== ===== =====\	\
15	Entries, Signal and Position Management	Stop Loss	AtivarStop	bool	true	Enable Stop Loss	—	Required by Percentage and Fixed-R sizing; recommended for every non-grid baseline.	
16	Entries, Signal and Position Management	Stop Loss	VelaStop	int	0	Stop Loss Candle	—	Use within its declared section and validate the complete combination.	
17	Entries, Signal and Position Management	Stop Loss	Stop	double	3	Stop Loss ATR Multiplier	—	Use within its declared section and validate the complete combination.	

18	Entries, Signal and Position Management	Take Profit	myBlankSpace101	string	""	\	\	===== ===== ===== Take Profit ===== ===== =====\ 	\
19	Entries, Signal and Position Management	Take Profit	TakeOrganico	bool	false	Enable Organic ATR Take Profit	—	Use within its declared section and validate the complete combination .	
20	Entries, Signal and Position Management	Take Profit	AtivarTake	bool	true	Enable Take Profit	—	Required by supported grid operation.	
21	Entries, Signal and Position Management	Take Profit	VelaTake	int	0	Take Profit Candle	—	Use within its declared section and validate the complete combination .	
22	Entries, Signal and Position Management	Take Profit	Take	double	3	Take Profit ATR Multiplier	—	Use within its declared section and validate the complete combination .	
23	Signal Filters	MTF Alignment	myBlankSpaceMTF	string	""	\	\	===== ===== ==== MTF Alignment ===== ===== =====\ 	\
24	Signal Filters	MTF Alignment	AtivarFiltro MTF	bool	false	Enable MTF Filter	—	Higher-time eframe alignment uses the EA's MACD trend layer.	
25	Signal Filters	MTF Alignment	MTF_RequireAmbos	bool	false	Require Both Higher Timeframes Aligned	—	Use within its declared section and validate the complete combination .	

26	Signal Filters	Moving Average Filter	myBlankSpaceMA	string	""	\	\	===== ===== Moving Average Filter ===== ===== =====\	\
27	Signal Filters	Moving Average Filter	AtivarFiltroMA	bool	false	Enable Moving Average Filter	—	Use within its declared section and validate the complete combination.	
28	Signal Filters	Moving Average Filter	MA_TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	MA Timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
29	Signal Filters	Moving Average Filter	MA_Period	int	200	MA Period	—	Use within its declared section and validate the complete combination.	
30	Signal Filters	Moving Average Filter	MA_Method	ENUM_MA_METHOD	MODE_EMA	MA Method	—	Use within its declared section and validate the complete combination.	
31	Signal Filters	Moving Average Filter	MA_AppliedPrice	ENUM_APPLIED_PRICE	PRICE_CLOSE	Applied Price	—	Use within its declared section and validate the complete combination.	
32	Signal Filters	Moving Average Filter	MetodoMA	MetodoFiltroMA	MA_PrecoEInclinacao	Price and Slope Rule	MA_ApenasPreco, MA_ApenasInclinacao, MA_PrecoEInclinacao, MA_PrecoOuInclinacao	Use within its declared section and validate the complete combination.	
33	Signal Filters	Moving Average Filter	SentidoMA	SentidoFiltroMA	MA_Tendencia	Trend or Reversal Direction	MA_Tendencia, MA_Reversao	Use within its declared section and validate the complete combination.	

34	Signal Filters	Moving Average Filter	MA_Slope Lookback	int	3	Slope Lookback Bars	—	Use within its declared section and validate the complete combination.	
35	Signal Filters	ADX Filter	myBlankSpaceMA1	string	""	\	\	===== ===== ===== ADX Filter ===== ===== =====\ 	\
36	Signal Filters	ADX Filter	AtivarFiltro ADX	bool	false	Enable ADX Trend Strength Filter	—	Use within its declared section and validate the complete combination.	
37	Signal Filters	ADX Filter	ADX_Time Frame	ENUM_ALLOWED_TIMEFRAMES	M1	ADX Timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
38	Signal Filters	ADX Filter	ADX_Period	int	14	ADX Period	—	Use within its declared section and validate the complete combination.	
39	Signal Filters	ADX Filter	ADX_Limit	double	25	Minimum ADX Value	—	Use within its declared section and validate the complete combination.	
40	Signal Filters	ADX Filter	MetodoADX	MetodoFiltroADX	ADX_ApenasForca	Strength or Strength Plus Direction	ADX_ApenasForca, ADX_Forca MaisDirecaoDI	Use within its declared section and validate the complete combination.	
41	Signal Filters	Volatility Filter	myBlankSpaceVolatility	string	""	\	\	===== ===== == Volatility Filter ===== ===== =====\ 	\

42	Signal Filters	Volatility Filter	EntradaATR	bool	false	Enable ATR Volatility Filter	—	Use within its declared section and validate the complete combination.	
43	Signal Filters	Volatility Filter	VolatilityFilter	ENUM_VOLATILITY_MODE	VOL_HIGH	Trade Volatility Condition	VOL_LOW, VOL_HIGH	Use within its declared section and validate the complete combination.	
44	Signal Filters	News Filter	myBlankSpaceNews	string	""	\	\	===== ===== ===== News Filter ===== ===== =====\\	\
45	Signal Filters	News Filter	AtivarFiltroNoticias	bool	false	Enable News Filter	—	Live calendar errors block new entries; backtests require the exported CSV under Common\\Files.	
46	Signal Filters	News Filter	NewsSomeAtoImpacto	bool	false	High Impact Only	—	Use within its declared section and validate the complete combination.	
47	Signal Filters	News Filter	NewsMinutesAntes	int	15	Minutes Blocked Before Event	—	Use within its declared section and validate the complete combination.	
48	Signal Filters	News Filter	NewsMinutesDepois	int	15	Minutes Blocked After Event	—	Use within its declared section and validate the complete combination.	

49	Signal Filters	News Filter	NewsMoedasManual	string	""	Manual Currencies (e.g. "USD, EUR"); empty = auto by symbol	—	When non-empty, overrides automatic currency extraction; required for most suffixed/non-FX symbols.	
50	Signal Filters	News Filter	NewsCSV File	string	"WhiteRabbit_News.csv"	Common\\Files CSV for Backtests	—	Semicolon CSV in Common\\Files: datetime;currency;importance;event_name, using broker-server time.	
51	Exit Management	—	AtivarBreakeven	bool	true	Enable Breakeven	—	Use within its declared section and validate the complete combination.	
52	Exit Management	—	Breakeven Distancia	double	1.0	Breakeven Distance (SL or ATR Stop Multiplier)	—	Use within its declared section and validate the complete combination.	
53	Exit Management	ATR Trailing	myBlankSpace46	string	""	\\	\\	===== ===== ==== ATR Trailing == ===== ===== ===\\	\\
54	Exit Management	ATR Trailing	AtivarTrail ATR	bool	false	Enable ATR Trailing Stop	—	Use within its declared section and validate the complete combination.	
55	Exit Management	ATR Trailing	MetodoDe Calculo	Candlestick type	CandleClose	Trailing Price Source	CandleOpen, CandleClose, CandleHigh, CandleLow, Preco	Use within its declared section and validate the complete combination.	

56	Exit Management	ATR Trailing	TrailVela	int	0	Trailing Candle	—	Use within its declared section and validate the complete combination.	
57	Exit Management	ATR Trailing	Trail	double	3	Trail	—	Use within its declared section and validate the complete combination.	
58	Exit Management	Reversal Exit	myBlankSpace10	string	""	\	\	===== ===== ===== Reversal Exit ===== ===== =====\ =====	\
59	Exit Management	Reversal Exit	ReversalExitMode	ENUM_REVERSAL_EXIT_MODE	ReversalExit_OnIndicatorSignal	Declared at source line 319.	ReversalExit_Disabled, ReversalExit_OnOppositeOrder, ReversalExit_OnIndicatorSignal	OnOppositeOrder requires a hedging account, both sides and grid disabled.	
60	Exit Management	Reversal Exit	ReversalExitUseEntryFilters	bool	false	Apply entry filters to indicator exits	—	False uses the raw opposite indicator signal; true also requires entry filters.	
61	Risk and Position Size	—	TradeCapitalPercentage	double	100	Percentage of Total Capital Allocated to EA	—	Allocation must be positive and no greater than the whole EA capital base.	
62	Risk and Position Size	—	PositionSizeMode	ENUM_POSITION_SIZE_MODE	PositionSize_FixedLot	Declared at source line 351.	PositionSize_Percentage, PositionSize_Monetary, PositionSize_FixedLot, PositionSize_FixedR	Exactly one model is active; compatibility depends on stop and grid selections.	

63	Risk and Position Size	—	PositionSizeValue	double	0.01	Percentage =% risk; Monetary=currency per 1.00 lot; Fixed Lot=lots; Fixed R=% of base capital per 1R	—	Meaning changes with PositionSizeMode ; never compare raw values across modes.	
64	Risk and Position Size	Fixed-R Controls	myBlankSpaceRF	string	""	\	\	===== =====	\
65	Risk and Position Size	Fixed-R Controls	CapitalBaseR	double	0	Base Capital for 1R (0 = balance at OnInit)	—	Zero captures balance at initialization ; Fixed-R only.	
66	Risk and Position Size	Fixed-R Controls	MaxRiskTradeR	double	0	Maximum Risk per Trade in R (0 = no cap)	—	Zero disables this additional Fixed-R cap.	
67	Risk and Position Size	Daily Loss Limit	myBlankSpaceDL	string	""	\	\	===== =====	\
68	Risk and Position Size	Daily Loss Limit	DailyLossLimitPercent	double	0	Maximum Daily Loss Percentage (0 = disabled)	—	Zero disables the daily limit; use a value below a total account loss.	
69	Risk and Position Size	Equity/Margin Protection	myBlankSpaceRiskProtection	string	""	\	\	===== =====	\

70	Risk and Position Size	Equity/Margin Protection	MaxEquity Drawdown Percent	double	30.0	Maximum EA drawdown before closing positions (0 = disabled)	—	Zero disables the EA equity stop.	
71	Risk and Position Size	Equity/Margin Protection	MinFreeMarginPercent	double	50.0	Minimum free margin to preserve after a new entry (0 = disabled)	—	Zero disables the post-entry free-margin reserve.	
72	Grid and Recovery	—	RecoveryMode	ENUM_RECOVERY_MODE	Recovery_None	Declared at source line 368.	Recovery_None, Recovery_Martingale, Recovery_D'Alembert	None, Martingale or D'Alembert are mutually exclusive.	
73	Grid and Recovery	Recovery Target	myBlankSpace457	string	""	\	\	===== ===== === Recovery Target === ===== =====\ 	\
74	Grid and Recovery	Recovery Target	Multiplicador	double	1	Martingale or Grid Target Profit Multiplier	—	Recovery/grid target multiplier; validate a value greater than one where escalation is intended.	
75	Grid and Recovery	Martingale Limits	myBlankSpace16	string	""	\	\	===== ===== == Martingale Limits === ===== =====\ 	\
76	Grid and Recovery	Martingale Limits	MaxMartingaleSteps	int	0	Consecutive Losses Before Reset (0 = no limit)	—	Zero means no step limit; exceeding a positive limit hard-resets the old deficit and forces the next order to the base lot.	

77	Grid and Recovery	Martingale Limits	MaxMartingaleLot	double	0.0	Maximum Martingale or D'Alembert Lot (0 = broker limit only)	—	Zero means broker maximum only.	
78	Grid and Recovery	DAlembert Settings	myBlankSpace_dal	string	""	\	\	===== ===== = DAlembert Settings == ===== =====\ 	\
79	Grid and Recovery	DAlembert Settings	DAlembert Step	double	0.01	Lot Increment per Loss for D'Alembert	—	Must be positive; supported with Fixed Lot and grid disabled.	
80	Grid and Recovery	Grid Settings	myBlankSpace17	string	""	\	\	===== ===== ==== Grid Settings == ===== ===== ==\ 	\
81	Grid and Recovery	Grid Settings	GridMode	ENUM_GRID_MODE	Grid_Disabled	Declared at source line 385.	Grid_Disabled, Grid_SeparateProfit, Grid_UnifiedProfit	Supported with Monetary or Fixed Lot sizing, Recovery_None and a hedging account; targets are frozen per cycle.	
82	Grid and Recovery	Grid Settings	UseATRGrid	bool	false	Use ATR Only as Grid Signal	—	Research switch; require an existing basket anchor before adding a grid leg.	
83	Grid and Recovery	Grid Settings	DistanceMinima	double	2	ATR Distance Multiplier for Next Grid Order	—	Positive ATR-distance multiplier between grid entries.	

84	Trading Schedule	Trading Hours	myBlankSpaceTradingHours	string	""	\	\	===== ===== ==== Trading Hours === ===== ===== =\	\
85	Trading Schedule	Trading Hours	Fecharordenforadohorario	bool	false	Close Positions Outside Trading Hours	—	When enabled, positions are closed whenever server time is outside the interval.	
86	Trading Schedule	Trading Hours	TOD_From_Hour	int	00	Trading Start Hour	—	Use within its declared section and validate the complete combination.	
87	Trading Schedule	Trading Hours	TOD_From_Min	int	00	Trading Start Minute	—	Use within its declared section and validate the complete combination.	
88	Trading Schedule	Trading Hours	TOD_To_Hour	int	23	Trading End Hour	—	Use within its declared section and validate the complete combination.	
89	Trading Schedule	Trading Hours	TOD_To_Min	int	55	Trading End Minute	—	Use within its declared section and validate the complete combination.	
90	Trading Schedule	Trading Days	myBlankSpaceTradingDays	string	""	\	\	===== ===== ==== Trading Days ===== ===== ===== =\	\
91	Trading Schedule	Trading Days	TradeMonday	bool	true	Allow Trading on Monday	—	Use within its declared section and validate the complete combination.	

92	Trading Schedule	Trading Days	TradeTuesday	bool	true	Allow Trading on Tuesday	—	Use within its declared section and validate the complete combination.	
93	Trading Schedule	Trading Days	TradeWednesday	bool	true	Allow Trading on Wednesday	—	Use within its declared section and validate the complete combination.	
94	Trading Schedule	Trading Days	TradeThursday	bool	true	Allow Trading on Thursday	—	Use within its declared section and validate the complete combination.	
95	Trading Schedule	Trading Days	TradeFriday	bool	true	Allow Trading on Friday	—	Use within its declared section and validate the complete combination.	
96	Trading Schedule	Trading Days	TradeSaturday	bool	false	Allow Trading on Saturday	—	Explicit weekend permission; useful only when the broker symbol trades Saturday.	
97	Trading Schedule	Trading Days	TradeSunday	bool	false	Allow Trading on Sunday	—	Explicit weekend permission; useful only when the broker symbol trades Sunday.	
98	General Settings	Market Execution	myBlankSpaceExecution	string	""	\	\	===== ===== == Market Execution ===== ===== ===\	\
99	General Settings	Market Execution	MaxSpread	double	0	Maximum Allowed Spread for New Trades	—	Zero disables the entry spread ceiling.	

100	General Settings	Market Execution	MaxSlippage	int	10	Slippage, ajustado no OnInit	—	Use within its declared section and validate the complete combination.	
101	General Settings	Position Exposure	myBlankSpaceExposure	string	""	\	\	===== ===== == Position Exposure = ===== ===== ==\	\
102	General Settings	Position Exposure	MaxLongTrades	int	1	Maximum Simultaneous BUY Positions	—	Zero disables BUY entries; grid sides require zero or at least two, while Martingale permits at most one.	
103	General Settings	Position Exposure	MaxShortTrades	int	1	Maximum Simultaneous SELL Positions	—	Zero disables SELL entries; grid sides require zero or at least two, while Martingale permits at most one.	
104	General Settings	Position Exposure	Hedging	bool	false	Allow Hedging	—	Does not change the account type; the real MT5 account must also support hedging.	
105	General Settings	Identity and Interface	myBlankSpaceInterface	string	""	\	\	===== ===== Identity and Interface = ===== =====\	\

106	General Settings	Identity and Interface	MagicNumber	int	384457	Magic Number	—	Must be unique for each independent strategy/symbol scope.	
107	General Settings	Identity and Interface	ModificationSafetyPoints	int	0	Optional extra distance beyond broker limits and current spread	—	Additional points beyond broker distance/spread constraints.	
108	General Settings	Identity and Interface	InterfaceLanguage	ENUM_INTERFACE_LANGUAGE	Language_Auto	Live chart interface language	Language_Auto, Language_English, Language_Portuguese, Language_Russian, Language_Chinese, Language_Spanish, Language_Japanese, Language_German, Language_Korean, Language_French, Language_Italian, Language_Turkish	Eleven live/visual UI languages; Auto uses English in Tester and untranslated labels fall back to English.	
109	General Settings	Chart Dashboard	myBlankSpaceDashboard	string	""	\	\	===== ===== == Chart Dashboard ===== ===== ==\	\
110	General Settings	Chart Dashboard	EnableChartDashboard	bool	true	Show visual P&L panel on live and visual tester charts	—	Live/visual panel; periodic tick refresh is capped at once per second.	
111	General Settings	Chart Dashboard	Dashboard Corner	ENUM_BASE_CORNER	CORNER_LEFT_UPPER	Dashboard chart corner	—	Use within its declared section and validate the complete combination.	

112	General Settings	Chart Dashboard	Dashboard OffsetX	int	12	Horizontal offset in pixels	—	Use within its declared section and validate the complete combination.	
113	General Settings	Chart Dashboard	Dashboard OffsetY	int	24	Vertical offset in pixels	—	Use within its declared section and validate the complete combination.	
114	General Settings	Chart Dashboard	ShowClosedDealLabels	bool	true	Show monetary and percentage result at each closed trade	—	Use within its declared section and validate the complete combination.	
115	General Settings	Chart Dashboard	MaxVisible DealLabels	int	120	Maximum closed-trade labels kept on chart	—	Use within its declared section and validate the complete combination.	
116	General Settings	Chart Dashboard	ClosedDealLabelFontSize	int	10	Closed-trade label font size	—	Use within its declared section and validate the complete combination.	
117	General Settings	Chart Dashboard	ApplyEmbeddedChartTheme	bool	true	Apply the White Rabbit X clean chart style on every machine	—	Use within its declared section and validate the complete combination.	
118	Optimization (WFO)	—	AtivarWFO	bool	false	Enable WFO	—	Enables the internal WFO boundary logic; still requires an external chronological process.	
119	Optimization (WFO)	—	MetodoDeEntradaWfo	WFO TIPO	Insample	Optimization Mode	Insample, InSampleAndOutSample	Use within its declared section and validate the complete combination.	

120	Optimization (WFO)	—	input_end_date	string	"2025.02.28"	Backtest End Date (manual)	—	Manual tester end date; keep synchronized with the selected test range.	
121	Optimization (WFO)	WFO Periods	myBlankSpaceWFOPeriods	string	""	\	\	===== ===== ===== WFO Periods == ===== ===== =====\	\
122	Optimization (WFO)	WFO Periods	wfo_windowSize	WFO_TIME_PERIOD	Ano	In-Sample Window Size	Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom	Use within its declared section and validate the complete combination.	
123	Optimization (WFO)	WFO Periods	wfo_customWindowSizeDays	int	0	Custom Window Size in Days (0 = unused)	—	Use within its declared section and validate the complete combination.	
124	Optimization (WFO)	WFO Periods	wfo_stepSize	WFO_TIME_PERIOD	Semestre	Out-of-Sample Step Size	Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom	Use within its declared section and validate the complete combination.	
125	Optimization (WFO)	WFO Periods	wfo_customStepSizePercent	int	0	Custom Step Size in Days or Percentage	—	Custom step: positive=percentage of IS; negative=fixed number of OOS days (for example -61).	
126	Optimization (WFO)	Optimization Criterion	myBlankSpace4447	string	""	\	\	===== ===== Optimization Criterion ===== =====\	\

127	Optimization (WFO)	Optimization Criterion	selectedFormula	CustomFormulaType	Formula_ProfitPerTradeAdjustedByDD	Custom Optimization Formula	Formula_One, Formula_GridSurvivalScore, Formula_Profit, Formula_ProfitWinTradeDD, Formula_EfficiencyRelativeToDeposit, Formula_AdjustedEfficiencyForGrid, Formula_ProfitRelativeToDDAndDeposit, Formula_ProfitPerTradeAdjustedByDD, Formula_SharpeAdjustedByDD, Formula_PessimisticProfit, Formula_ResilienceToDrawdown, Formula_ReturnUniformity, Formula_SystemRobustness, Formula_LevainCompositeScore, Formula_SomaR	Optimization criterion only; inspect stability and OOS results before selection.	
-----	--------------------	------------------------	-----------------	-------------------	------------------------------------	-----------------------------	--	--	--

EA SHA-256: D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973 EA
version: 1.12