

White Rabbit X — 完整用户手册

依据当前 EA 源码与 set 清单生成的权威参考 — EA 1.11 — 127 inputs — 3738 sets

范围与事实来源

EA 源码定义 inputs、默认值、枚举与功能；清单定义每个 set 的状态、路径和 SHA-256。旧 Quantum 资料仅供追溯。

EA SHA-256: D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973. Manifest SHA-256: E96B9E4050F8EA8B764E187BD6CC1E907AE2AE8C4A6489C9EF2D3317C6003F75.

自动生成资料；参数标识符与 EA 完全一致。

安装与首次运行

安装匹配的 EX5，在 Tester Inputs 加载一个 set，选择精确的经纪商品种并检查 Journal。

信号引擎与入场方法

六种引擎共享反转、signal/reference 交叉和 baseline/reference 交叉。And 要求同一根已收盘 K 线，All 接受任一事件。

- 十二种原生引擎：MACD、EMA Cross、Momentum、Stochastic、TRIX、RSI、CCI、Williams %R、DeMarker、MFI、OsMA、Ichimoku。
- 七种入场方法明确区分同一收盘 K 线的 AND 与 OR。
- MTF、MA、ADX、ATR 波动率与新闻过滤器独立。
- 四种 PositionSizeMode 以及 equity/margin 保护。
- Stop、take、breakeven、trailing、reversal 构成出场组合。
- Dashboard、交易日程、语言与 WFO 属于操作层。
- EntryIndicator: MACD, EMA_Cross, Momentum, Stochastic, TRIX, RSI, CCI, WPR, DeMarker, MFI, OsMA, Ichimoku.
- EntryMethod: Reversal, SignalCross, ReferenceCross, ReversalAndSignalCross, ReversalAndReferenceCross, SignalAndReferenceCross, All.
- PositionSizeMode: Percentage, Monetary, FixedLot, FixedR.
- RecoveryMode: None, Martingale, DAlembert.
- GridMode: Disabled, SeparateProfit, UnifiedProfit.

过滤器

MTF 是高周期 MACD 对齐；MA、ADX、ATR 波动率与新闻相互独立。叠加过滤器会缩小样本。

News filter and CSV workflow

Live mode reads the MT5 Economic Calendar in broker-server time and blocks new entries if the calendar query fails. Backtests cannot read that live calendar: run MQL5\Scripts\White Rabbit News Exporter on a live/demo chart, cover the entire test interval, and write NewsCSVFile to the terminal Common\Files folder. The semicolon-delimited header is datetime;currency;importance;event_name, where importance 2 is moderate and 3 is high. Use the same broker/server timezone; for suffixed or non-FX symbols set ExportMoedas and NewsMoedasManual explicitly. Manual currencies take precedence over automatic symbol parsing.

执行与持仓管理

执行受点差、保证金、手数步长、tick size、stops/freeze 限制影响。必须在 Journal 中确认结果。

Grid cycle and ATR spacing

Every additional grid leg is measured from the newest already-confirmed position on that side and must satisfy $ATR \times DistanciaMinima$. The initial order cannot recursively trigger another leg in the same calculation event; it becomes the anchor on the following cycle. Individual grid take-profits are disabled: Separate mode evaluates independent BUY/SELL cycles against frozen monetary targets and ends a side when it becomes flat; Unified evaluates the aggregate BUY+SELL basket and ends when both sides are flat. Realized commissions, swap, fees and stopped legs remain in the result while the corresponding cycle is open. The target triggers a close request, so actual exit costs and slippage can leave the final result slightly below it. Live cycle state is persisted across an EA restart. Grid is hedging-only and must be reoptimized after any EA, broker-contract or cost change.

出场组合

Stop、ATR take、breakeven、ATR trailing 与 reversal exit 相互独立；ReversalExitUseEntryFilters 控制出场是否使用入场过滤器。

风险与恢复

只能选择一个 PositionSizeMode。Percentage 与 Fixed-R 需要 stop；Grid、Martingale、D'Alembert 属于研究型恢复模式。

时段、界面与 WFO

时段使用经纪商服务器时间，可跨午夜，并有 Saturday/Sunday 控制。WFO 定义 IS/OOS 与标准。

Diagnostics and supplied utilities

The Experts/Journal tab is authoritative for rejected inputs, OrderCheck failures, news-calendar errors and close retries. Compile and run MQL5\Scripts\WhiteRabbit Filters SelfTest; its final line must report zero failures. Use White Rabbit News Exporter to build the test CSV, then verify its date range, currencies, delimiter and Common\Files location before a news-enabled backtest.

周期仪表板遥测

面板使用与仓位计算和篮子平仓相同的状态快照。

- 按 tick 的周期刷新最多每秒一次；初始化和交易事件可立即刷新。
- Balance/Equity 属于整个账户。Closed P&L 是 OnInit 之后的变化；Open P&L 与 positions 是当前状态，并按 Symbol + Magic 过滤。
- Martingale 分别显示 BUY/SELL 连续亏损、周期亏损次数与总额、已恢复金额、剩余 deficit，以及 deficit $\times$ Multiplicador 的 target。
- 超过 MaxMartingaleSteps 会 hard reset：旧 deficit 被丢弃，下一单使用基础手数；每个方向最多允许一笔持仓。
- D'Alembert 显示 BUY/SELL 当前级别与下一笔规范化手数。
- Grid 显示 legs/volume、包含成本的 realized、open P&L、cycle P&L、周期开始时冻结的 target 与 remaining。
- Anchor 是最近确认的持仓。BUY 必须严格低于 $anchor - ATR \times DistanciaMinima$ ；SELL 必须严格高于 $anchor + ATR \times DistanciaMinima$ ；进度以 ATR 表示。
- Separate 在某一方向 flat 时仅结束该方向周期；Unified 在 BUY/SELL 都 flat 时结束。未完成订单会延后 reset。
- Target 只触发平仓请求；实际退出 commission、fee 与 slippage 可能使最终结果略低于目标。
- InterfaceLanguage 保留 11 种界面语言。Auto 在 Tester 使用 English、实盘使用终端语言；缺少翻译的标签回退为 English。

兼容组合与限制

这些是保守规则；经纪商可能实施更严格限制。

- Percentage 与 Fixed-R 需要 AtivarStop=true。
- Grid 仅支持 Monetary/Fixed Lot、Recovery_None 与 hedging account。
- Grid 需要 take、正 DistanciaMinima 以及活动方向至少两笔上限。
- 只要篮子仍有持仓，本周期已实现亏损、swap、commission 与 fees 就继续计入达到目标所需的结果；单独一腿盈利不会清除这些成本。
- 在 Grid_SeparateProfit 中 BUY 与 SELL 周期独立。某一方向全部持仓消失时，该方向周期结束；之后的入场开启新周期，不继承已结束的亏损。
- D'Alembert 仅限 Fixed Lot、Grid_Disabled、DAlembertStep>0。
- Martingale 受 MaxMartingaleSteps 与 MaxMartingaleLot 限制。
- OnOppositeOrder 需要 hedging、双向交易且关闭 grid。
- 新闻回测需要 Common\Files 中的 CSV。
- 时段使用经纪商服务器时间。
- 每个经纪商都要重新核对 suffix 与品种规格。

检测到的 set 库

数量从文件系统与清单读取。每个 set 是研究假设，不是收益承诺。 Counts and fingerprints were read at generation time.

Folder	Sets	Purpose
01_Forex	168	Per-asset baselines — Forex.
02_Metals	18	Per-asset baselines — Metals.
03_Cryptocurrencies	36	Per-asset baselines — Cryptocurrencies.
04_Indices_Energies	42	Per-asset baselines — Indices Energies.
05_US_Stocks_CFD	300	Per-asset baselines — US Stocks CFD.
06_Research_Matrix	935	Controlled one-axis research.
07_Entry_System_Matrix	3360	Indicator × entry method × management matrix.
08_Filter_Stack_Matrix	320	Signal-filter stack combinations.
09_Risk_Engine_Matrix	130	Compatible sizing, risk and recovery models.
10_Exit_Stack_Matrix	720	Exit-control stack combinations.

风险警告

任何 EA、set 或历史结果都不能保证未来表现。必须进行 OOS 与模拟盘验证。

完整 inputs 参考

表格按源码声明顺序生成；分隔字符串为 .set schema 的一部分。

No.	Section	Subsection	Parameter	Type	Default	Source description	Enum options	Operational notes	
1	General	—	NomedaEstrategia	string	"White Rabbit X"	Strategy Name	—	Use within its declared section and validate the complete combination.	
2	Entries, Signal and Position Management	—	TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	Entry timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Signal evaluation is gated to one decision per closed bar of this timeframe.	
3	Entries, Signal and Position Management	Entry Indicator	myBlankSpaceEntryIndicator	string	""	\	\	===== ===== == Entry Indicator == ===== =====	\
4	Entries, Signal and Position Management	Entry Indicator	EntryIndicator	ENUM_ENTRY_INDICATOR	EntryIndicator_MACD	Selects the indicator used by Entry Method	EntryIndicator_MACD, EntryIndicator_EMA_Cross, EntryIndicator_Momentum, EntryIndicator_Stochastic, EntryIndicator_TRIX, EntryIndicator_RSI, EntryIndicator_CCI, EntryIndicator_WPR, EntryIndicator_DeMarker, EntryIndicator_MFI, EntryIndicator_OsMA, EntryIndicator_Ichimoku	Selects the engine; Fast_EMA, Slow_EMA and MACD_SMA are reused by that engine.	
5	Entries, Signal and Position Management	Entry Indicator	InpAppliedPrice	ENUM_APPLIED_PRICE	PRICE_CLOSE	Applied price used by the selected indicator	—	Use within its declared section and validate the complete combination.	
6	Entries, Signal and Position Management	Entry Indicator	Fast_EMA	int	12	First period: MACD/EMA fast; oscillator period; Stochastic %K; Ichimoku Tenkan	—	First sequential period; for Ichimoku this is Tenkan.	

7	Entries, Signal and Position Management	Entry Indicator	Slow_EMA	int	26	Second period: MACD/EMA slow; Ichimoku Kijun	—	Second sequential period; for Ichimoku this is Kijun.	
8	Entries, Signal and Position Management	Entry Indicator	MACD_SMA	int	9	Third period: MACD signal; oscillator signal; Stochastic %D; Ichimoku Senkou B	—	Third sequential period; for Ichimoku this is Senkou Span B.	
9	Entries, Signal and Position Management	Entry Method	myBlankSpace1	string	""	\	\	===== ===== ===== Entry Method == ===== ===== =====\	\
10	Entries, Signal and Position Management	Entry Method	EntryMethod	ENUM_ENTRY_TRIGGER_MODE	EntryTrigger_All	Reversal, signal cross, reference cross or their combinations	EntryTrigger_Reversal, EntryTrigger_SignalCross, EntryTrigger_ReferenceCross, EntryTrigger_ReversalAndSignalCross, EntryTrigger_ReversalAndReferenceCross, EntryTrigger_SignalAndReferenceCross, EntryTrigger_All	And modes require both events on the same closed bar; All is OR.	
11	Entries, Signal and Position Management	ATR Settings	myBlankSpace42	string	""	\	\	===== ===== ===== ATR Settings == ===== ===== =====\	\
12	Entries, Signal and Position Management	ATR Settings	ATR_TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	Time Frame ATR	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
13	Entries, Signal and Position Management	ATR Settings	PeriodoATR	int	14	ATR Period	—	Use within its declared section and validate the complete combination.	

14	Entries, Signal and Position Management	Stop Loss	myBlankSpace4s2	string	""	\	\	===== ===== ===== Stop Loss = ===== ===== =====\ 	\
15	Entries, Signal and Position Management	Stop Loss	AtivarStop	bool	true	Enable Stop Loss	—	Required by Percentage and Fixed-R sizing; recommended for every non-grid baseline.	
16	Entries, Signal and Position Management	Stop Loss	VelaStop	int	0	Stop Loss Candle	—	Use within its declared section and validate the complete combination.	
17	Entries, Signal and Position Management	Stop Loss	Stop	double	3	Stop Loss ATR Multiplier	—	Use within its declared section and validate the complete combination.	
18	Entries, Signal and Position Management	Take Profit	myBlankSpace101	string	""	\	\	===== ===== ===== Take Profit ===== ===== =====\ 	\
19	Entries, Signal and Position Management	Take Profit	TakeOrganico	bool	false	Enable Organic ATR Take Profit	—	Use within its declared section and validate the complete combination.	
20	Entries, Signal and Position Management	Take Profit	AtivarTake	bool	true	Enable Take Profit	—	Required by supported grid operation.	
21	Entries, Signal and Position Management	Take Profit	VelaTake	int	0	Take Profit Candle	—	Use within its declared section and validate the complete combination.	
22	Entries, Signal and Position Management	Take Profit	Take	double	3	Take Profit ATR Multiplier	—	Use within its declared section and validate the complete combination.	

23	Signal Filters	MTF Alignment	myBlankSpaceMTF	string	""	\	\	=====	\
								=====	
								===== MTF Alignment =	
								=====	
								=====	
								====\	
24	Signal Filters	MTF Alignment	AtivarFiltro MTF	bool	false	Enable MTF Filter	—	Higher-timeframe alignment uses the EA's MACD trend layer.	
25	Signal Filters	MTF Alignment	MTF_RequireAmbos	bool	false	Require Both Higher Timeframes Aligned	—	Use within its declared section and validate the complete combination.	
26	Signal Filters	Moving Average Filter	myBlankSpaceMA	string	""	\	\	=====	\
								=====	
								Moving Average Filter =====	
								=====	
								====\	
27	Signal Filters	Moving Average Filter	AtivarFiltro MA	bool	false	Enable Moving Average Filter	—	Use within its declared section and validate the complete combination.	
28	Signal Filters	Moving Average Filter	MA_TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	MA Timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
29	Signal Filters	Moving Average Filter	MA_Period	int	200	MA Period	—	Use within its declared section and validate the complete combination.	
30	Signal Filters	Moving Average Filter	MA_Method	ENUM_MA_METHOD	MODE_EMA	MA Method	—	Use within its declared section and validate the complete combination.	
31	Signal Filters	Moving Average Filter	MA_AppliedPrice	ENUM_APPLIED_PRICE	PRICE_CLOSE	Applied Price	—	Use within its declared section and validate the complete combination.	

32	Signal Filters	Moving Average Filter	MetodoMA	MetodoFiltroMA	MA_PrecoEInclinacao	Price and Slope Rule	MA_ApenasPreco, MA_ApenasInclinacao, MA_PrecoEInclinacao, MA_PrecoOuInclinacao	Use within its declared section and validate the complete combination.	
33	Signal Filters	Moving Average Filter	SentidoMA	SentidoFiltroMA	MA_Tendencia	Trend or Reversal Direction	MA_Tendencia, MA_Reversao	Use within its declared section and validate the complete combination.	
34	Signal Filters	Moving Average Filter	MA_SlopeLookback	int	3	Slope Lookback Bars	—	Use within its declared section and validate the complete combination.	
35	Signal Filters	ADX Filter	myBlankSpaceMA1	string	""	\	\	===== ===== ===== ADX Filter = ===== ===== =====\ 	\
36	Signal Filters	ADX Filter	AtivarFiltroADX	bool	false	Enable ADX Trend Strength Filter	—	Use within its declared section and validate the complete combination.	
37	Signal Filters	ADX Filter	ADX_TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	ADX Timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
38	Signal Filters	ADX Filter	ADX_Period	int	14	ADX Period	—	Use within its declared section and validate the complete combination.	
39	Signal Filters	ADX Filter	ADX_Limit	double	25	Minimum ADX Value	—	Use within its declared section and validate the complete combination.	
40	Signal Filters	ADX Filter	MetodoADX	MetodoFiltroADX	ADX_ApenasForca	Strength or Strength Plus Direction	ADX_ApenasForca, ADX_ForcaMaisDirecaoDI	Use within its declared section and validate the complete combination.	

41	Signal Filters	Volatility Filter	myBlankSpaceVolatility	string	""	\	\	===== ===== == Volatility Filter == ===== =====\\	\
42	Signal Filters	Volatility Filter	EntradaATR	bool	false	Enable ATR Volatility Filter	—	Use within its declared section and validate the complete combination.	
43	Signal Filters	Volatility Filter	VolatilityFilter	ENUM_VOLATILITY_MODE	VOL_HIGH	Trade Volatility Condition	VOL_LOW, VOL_HIGH	Use within its declared section and validate the complete combination.	
44	Signal Filters	News Filter	myBlankSpaceNews	string	""	\	\	===== ===== ===== News Filter ===== ===== =====\\	\
45	Signal Filters	News Filter	AtivarFiltroNoticias	bool	false	Enable News Filter	—	Live calendar errors block new entries; backtests require the exported CSV under Common\\Files.	
46	Signal Filters	News Filter	NewsSomenteAltoImpacto	bool	false	High Impact Only	—	Use within its declared section and validate the complete combination.	
47	Signal Filters	News Filter	NewsMinutosAntes	int	15	Minutes Blocked Before Event	—	Use within its declared section and validate the complete combination.	
48	Signal Filters	News Filter	NewsMinutosDepois	int	15	Minutes Blocked After Event	—	Use within its declared section and validate the complete combination.	

49	Signal Filters	News Filter	NewsMoeda sManual	string	""	Manual Currencies (e.g. "USD,E UR"); empty = auto by symbol	—	When non-empty, overrides automatic currency extraction; required for most suffixe d/non-FX symbols.	
50	Signal Filters	News Filter	NewsCSVFil e	string	"WhiteRabbi t_News.csv"	Common\\F iles CSV for Backtests	—	Semicolon CSV in Com mon\\Files: datetime;cur rency;import ance;event_ name, using broker-serve r time.	
51	Exit Manage ment	—	AtivarBreake ven	bool	true	Enable Breakeven	—	Use within its declared section and validate the complete co mbination.	
52	Exit Manage ment	—	BreakevenDi stancia	double	1.0	Breakeven Distance (SL or ATR Stop Multiplier)	—	Use within its declared section and validate the complete co mbination.	
53	Exit Manage ment	ATR Trailing	myBlankSpa ce46	string	""	\	\	===== ===== ==== ATR Trailing === ===== ===== ==\	\
54	Exit Manage ment	ATR Trailing	AtivarTrailA TR	bool	false	Enable ATR Trailing Stop	—	Use within its declared section and validate the complete co mbination.	
55	Exit Manage ment	ATR Trailing	MetodoDeC alculo	Candlestickt ype	CandleClose	Trailing Price Source	CandleOpen , CandleClos e, CandleHigh, CandleLow, Preco	Use within its declared section and validate the complete co mbination.	
56	Exit Manage ment	ATR Trailing	TrailVela	int	0	Trailing Candle	—	Use within its declared section and validate the complete co mbination.	

57	Exit Management	ATR Trailing	Trail	double	3	Trail	—	Use within its declared section and validate the complete combination.	
58	Exit Management	Reversal Exit	myBlankSpace10	string	""	\	\	===== ===== ===== Reversal Exit ===== ===== =====\	\
59	Exit Management	Reversal Exit	ReversalExitMode	ENUM_REVERSAL_EXIT_MODE	ReversalExit_OnIndicatorSignal	Declared at source line 319.	ReversalExit_Disabled, ReversalExit_OnOppositeOrder, ReversalExit_OnIndicatorSignal	OnOppositeOrder requires a hedging account, both sides and grid disabled.	
60	Exit Management	Reversal Exit	ReversalExitUseEntryFilters	bool	false	Apply entry filters to indicator exits	—	False uses the raw opposite indicator signal; true also requires entry filters.	
61	Risk and Position Size	—	TradeCapitalPercentage	double	100	Percentage of Total Capital Allocated to EA	—	Allocation must be positive and no greater than the whole EA capital base.	
62	Risk and Position Size	—	PositionSizeMode	ENUM_POSITION_SIZE_MODE	PositionSize_FixedLot	Declared at source line 351.	PositionSize_Percentage, PositionSize_Monetary, PositionSize_FixedLot, PositionSize_FixedR	Exactly one model is active; compatibility depends on stop and grid selections.	
63	Risk and Position Size	—	PositionSizeValue	double	0.01	Percentage=% risk; Monetary=currentcy per 1.00 lot; Fixed Lot=lots; Fixed R=% of base capital per 1R	—	Meaning changes with PositionSizeMode; never compare raw values across modes.	
64	Risk and Position Size	Fixed-R Controls	myBlankSpaceRF	string	""	\	\	===== ===== == Fixed-R Controls == ===== ===== ==\	\

65	Risk and Position Size	Fixed-R Controls	CapitalBaseR	double	0	Base Capital for 1R (0 = balance at OnInit)	—	Zero captures balance at initialization; Fixed-R only.	
66	Risk and Position Size	Fixed-R Controls	MaxRiscoTradeR	double	0	Maximum Risk per Trade in R (0 = no cap)	—	Zero disables this additional Fixed-R cap.	
67	Risk and Position Size	Daily Loss Limit	myBlankSpaceDL	string	""	\	\	===== ===== == Daily Loss Limit = ===== ===== ==\	\
68	Risk and Position Size	Daily Loss Limit	DailyLossLimitPercent	double	0	Maximum Daily Loss Percentage (0 = disabled)	—	Zero disables the daily limit; use a value below a total account loss.	
69	Risk and Position Size	Equity/Margin Protection	myBlankSpaceRiskProtection	string	""	\	\	===== ===== Eq uity/Margin Protection = ===== =====	\
70	Risk and Position Size	Equity/Margin Protection	MaxEquityDrawdownPercent	double	30.0	Maximum EA drawdown before closing positions (0 = disabled)	—	Zero disables the EA equity stop.	
71	Risk and Position Size	Equity/Margin Protection	MinFreeMarginPercent	double	50.0	Minimum free margin to preserve after a new entry (0 = disabled)	—	Zero disables the post-entry free-margin reserve.	
72	Grid and Recovery	—	RecoveryMode	ENUM_RECOVERY_MODE	Recovery_One	Declared at source line 368.	Recovery_One, Recovery_Martingale, Recovery_D'Alembert	None, Martingale or D'Alembert are mutually exclusive.	
73	Grid and Recovery	Recovery Target	myBlankSpace457	string	""	\	\	===== ===== ==== Recovery Target === ===== ===== \\	\

74	Grid and Recovery	Recovery Target	Multiplicador	double	1	Martingale or Grid Target Profit Multiplier	—	Recovery/grid target multiplier; validate a value greater than one where escalation is intended.	
75	Grid and Recovery	Martingale Limits	myBlankSpace16	string	""	\	\	===== ===== == Martingale Limits ==== ===== =====\ =====	\
76	Grid and Recovery	Martingale Limits	MaxMartingaleSteps	int	0	Consecutive Losses Before Reset (0 = no limit)	—	Zero means no step limit; exceeding a positive limit hard-resets the old deficit and forces the next order to the base lot.	
77	Grid and Recovery	Martingale Limits	MaxMartingaleLot	double	0.0	Maximum Martingale or D'Alembert Lot (0 = broker limit only)	—	Zero means broker maximum only.	
78	Grid and Recovery	D'Alembert Settings	myBlankSpace_dal	string	""	\	\	===== ===== = D'Alembert Settings ==== ===== =====\ =====	\
79	Grid and Recovery	D'Alembert Settings	D'AlembertStep	double	0.01	Lot Increment per Loss for D'Alembert	—	Must be positive; supported with Fixed Lot and grid disabled.	
80	Grid and Recovery	Grid Settings	myBlankSpace17	string	""	\	\	===== ===== ==== Grid Settings ==== ===== =====\ =====	\

81	Grid and Recovery	Grid Settings	GridMode	ENUM_GRID_MODE	Grid_Disabled	Declared at source line 385.	Grid_Disabled, Grid_SeparateProfit, Grid_UnifiedProfit	Supported with Monetary or Fixed Lot sizing, Recovery_None and a hedging account; targets are frozen per cycle.	
82	Grid and Recovery	Grid Settings	UseATRGrid	bool	false	Use ATR Only as Grid Signal	—	Research switch; require an existing basket anchor before adding a grid leg.	
83	Grid and Recovery	Grid Settings	DistanceMinima	double	2	ATR Distance Multiplier for Next Grid Order	—	Positive ATR-distance multiplier between grid entries.	
84	Trading Schedule	Trading Hours	myBlankSpaceTradingHours	string	""	\	\	===== ===== ===== Trading Hours ==== ===== ===== =\\	\
85	Trading Schedule	Trading Hours	Fecharordenforadohorario	bool	false	Close Positions Outside Trading Hours	—	When enabled, positions are closed whenever server time is outside the interval.	
86	Trading Schedule	Trading Hours	TOD_From_Hour	int	00	Trading Start Hour	—	Use within its declared section and validate the complete combination.	
87	Trading Schedule	Trading Hours	TOD_From_Min	int	00	Trading Start Minute	—	Use within its declared section and validate the complete combination.	
88	Trading Schedule	Trading Hours	TOD_To_Hour	int	23	Trading End Hour	—	Use within its declared section and validate the complete combination.	

89	Trading Schedule	Trading Hours	TOD_To_Min	int	55	Trading End Minute	—	Use within its declared section and validate the complete combination.	
90	Trading Schedule	Trading Days	myBlankSpaceTradingDays	string	""	\	\	===== ===== ===== Trading Days==== ===== ===== =\	\
91	Trading Schedule	Trading Days	TradeMonday	bool	true	Allow Trading on Monday	—	Use within its declared section and validate the complete combination.	
92	Trading Schedule	Trading Days	TradeTuesday	bool	true	Allow Trading on Tuesday	—	Use within its declared section and validate the complete combination.	
93	Trading Schedule	Trading Days	TradeWednesday	bool	true	Allow Trading on Wednesday	—	Use within its declared section and validate the complete combination.	
94	Trading Schedule	Trading Days	TradeThursday	bool	true	Allow Trading on Thursday	—	Use within its declared section and validate the complete combination.	
95	Trading Schedule	Trading Days	TradeFriday	bool	true	Allow Trading on Friday	—	Use within its declared section and validate the complete combination.	
96	Trading Schedule	Trading Days	TradeSaturday	bool	false	Allow Trading on Saturday	—	Explicit weekend permission; useful only when the broker symbol trades Saturday.	

97	Trading Schedule	Trading Days	TradeSunday	bool	false	Allow Trading on Sunday	—	Explicit weekend permission; useful only when the broker symbol trades Sunday.	
98	General Settings	Market Execution	myBlankSpaceExecution	string	""	\	\	===== ===== == Market Execution = ===== ===== ==\	\
99	General Settings	Market Execution	MaxSpread	double	0	Maximum Allowed Spread for New Trades	—	Zero disables the entry spread ceiling.	
100	General Settings	Market Execution	MaxSlippage	int	10	Slippage, ajustado no OnInit	—	Use within its declared section and validate the complete combination.	
101	General Settings	Position Exposure	myBlankSpaceExposure	string	""	\	\	===== ===== == Position Exposure == ===== ===== \	\
102	General Settings	Position Exposure	MaxLongTrades	int	1	Maximum Simultaneous BUY Positions	—	Zero disables BUY entries; grid sides require zero or at least two, while Martingale permits at most one.	
103	General Settings	Position Exposure	MaxShortTrades	int	1	Maximum Simultaneous SELL Positions	—	Zero disables SELL entries; grid sides require zero or at least two, while Martingale permits at most one.	
104	General Settings	Position Exposure	Hedging	bool	false	Allow Hedging	—	Does not change the account type; the real MT5 account must also support hedging.	

105	General Settings	Identity and Interface	myBlankSpaceInterface	string	""	\	\	===== ===== Identity and Interface == ===== =====\\	\
106	General Settings	Identity and Interface	MagicNumber	int	384457	Magic Number	—	Must be unique for each independent strategy/symbol scope.	
107	General Settings	Identity and Interface	ModificationSafetyPoints	int	0	Optional extra distance beyond broker limits and current spread	—	Additional points beyond broker distance/spread constraints.	
108	General Settings	Identity and Interface	InterfaceLanguage	ENUM_INTERFACE_LANGUAGE	Language_Auto	Live chart interface language	Language_Auto, Language_English, Language_Portuguese, Language_Russian, Language_Chinese, Language_Spanish, Language_Japanese, Language_German, Language_Korean, Language_French, Language_Italian, Language_Turkish	Eleven live/visual UI languages; Auto uses English in Tester and untranslated labels fall back to English.	
109	General Settings	Chart Dashboard	myBlankSpaceDashboard	string	""	\	\	===== ===== == Chart Dashboard ===== ===== ==\\	\
110	General Settings	Chart Dashboard	EnableChartDashboard	bool	true	Show visual P&L panel on live and visual tester charts	—	Live/visual panel; periodic tick refresh is capped at once per second.	
111	General Settings	Chart Dashboard	DashboardCorner	ENUM_BASE_CORNER	CORNER_LEFT_UPPER	Dashboard chart corner	—	Use within its declared section and validate the complete combination.	

112	General Settings	Chart Dashboard	DashboardOffsetX	int	12	Horizontal offset in pixels	—	Use within its declared section and validate the complete combination.	
113	General Settings	Chart Dashboard	DashboardOffsetY	int	24	Vertical offset in pixels	—	Use within its declared section and validate the complete combination.	
114	General Settings	Chart Dashboard	ShowClosedDealLabels	bool	true	Show monetary and percentage result at each closed trade	—	Use within its declared section and validate the complete combination.	
115	General Settings	Chart Dashboard	MaxVisibleDealLabels	int	120	Maximum closed-trade labels kept on chart	—	Use within its declared section and validate the complete combination.	
116	General Settings	Chart Dashboard	ClosedDealLabelFontSize	int	10	Closed-trade label font size	—	Use within its declared section and validate the complete combination.	
117	General Settings	Chart Dashboard	ApplyEmbeddedChartTheme	bool	true	Apply the White Rabbit X clean chart style on every machine	—	Use within its declared section and validate the complete combination.	
118	Optimization (WFO)	—	AtivarWFO	bool	false	Enable WFO	—	Enables the internal WFO boundary logic; still requires an external chronological process.	
119	Optimization (WFO)	—	MetodoDeEntradaWFO	WFOType	Insample	Optimization Mode	Insample, InSampleAndOutSample	Use within its declared section and validate the complete combination.	
120	Optimization (WFO)	—	input_end_date	string	"2025.02.28"	Backtest End Date (manual)	—	Manual tester end date; keep synchronized with the selected test range.	

121	Optimization (WFO)	WFO Periods	myBlankSpaceWFOPeriods	string	""	\	\	===== ===== ===== WFO Periods === ===== =====	\
122	Optimization (WFO)	WFO Periods	wfo_windowSize	WFO_TIME_PERIOD	Ano	In-Sample Window Size	Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom	Use within its declared section and validate the complete combination.	
123	Optimization (WFO)	WFO Periods	wfo_customWindowSizeDays	int	0	Custom Window Size in Days (0 = unused)	—	Use within its declared section and validate the complete combination.	
124	Optimization (WFO)	WFO Periods	wfo_stepSize	WFO_TIME_PERIOD	Semestre	Out-of-Sample Step Size	Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom	Use within its declared section and validate the complete combination.	
125	Optimization (WFO)	WFO Periods	wfo_customStepSizePercent	int	0	Custom Step Size in Days or Percentage	—	Custom step: positive =percentage of IS; negative=fixed number of OOS days (for example -61).	
126	Optimization (WFO)	Optimization Criterion	myBlankSpace4447	string	""	\	\	===== ===== ===== Optimization Criterion ===== =====	\

127	Optimization (WFO)	Optimization Criterion	selectedFormula	CustomFormulaType	Formula_ProfitPerTradeAdjustedByDD	Custom Optimization Formula	Formula_None, Formula_GridSurvivalScore, Formula_Profit, Formula_ProfitWinTradeDD, Formula_EfficiencyRelativeToDeposit, Formula_AdjustedEfficiencyForGrid, Formula_ProfitRelativeToDDAndDeposit, Formula_ProfitPerTradeAdjustedByDD, Formula_SharpeAdjustedByDD, Formula_PessimisticProfit, Formula_ResilienceToDrawdown, Formula_ReturnUniformity, Formula_SystemRobustness, Formula_LevainCompositeScore, Formula_SomaR	Optimization criterion only; inspect stability and OOS results before selection.	
-----	--------------------	------------------------	-----------------	-------------------	------------------------------------	-----------------------------	---	--	--

EA SHA-256: D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973 EA version:
1.12