

White Rabbit X — 전체 사용자 설명서

현재 EA 소스와 set 매니페스트에서 생성한 공식 참조 — EA 1.11 — 127 inputs — 3738 sets

범위와 기준 데이터

EA 소스가 inputs, 기본값, 기능을 정의하고 매니페스트가 각 set의 상태, 경로, SHA - 256을 정의합니다. 구 Quantum 자료는 기록용입니다.

EA SHA - 256:

D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973. Manifest
SHA - 256: E96B9E4050F8EA8B764E187BD6CC1E907AE2AE8C4A6489C9EF2D3317C6003F75.

자동 생성 문서이며 파라미터 식별자는 EA와 정확히 같습니다.

설치와 첫 실행

일치하는 EX5를 설치하고 Tester Inputs에서 set을 로드한 뒤 정확한 심볼과 Journal을 확인합니다.

신호와 진입 방식

6개 엔진은 reversal, signal/reference cross, baseline/reference cross를 공유합니다. And는 같은 종가 확정 봉, All은 어느 하나입니다.

- 12개 네이티브 엔진: MACD, EMA Cross, Momentum, Stochastic, TRIX, RSI, CCI, Williams %R, DeMarker, MFI, OsMA, Ichimoku.
- 확정 봉의 AND/OR 의미가 명확한 7개 진입 방식.
- 독립적인 MTF, MA, ADX, ATR, news 필터.
- 4개 PositionSizeMode와 equity/margin 보호.
- Stop, take, breakeven, trailing, reversal 청산.
- Dashboard, 일정, 언어, WFO 통합.
- EntryIndicator: MACD, EMA_Cross, Momentum, Stochastic, TRIX, RSI, CCI, WPR, DeMarker, MFI, OsMA, Ichimoku.
- EntryMethod: Reversal, SignalCross, ReferenceCross, ReversalAndSignalCross, ReversalAndReferenceCross, SignalAndReferenceCross, All.
- PositionSizeMode: Percentage, Monetary, FixedLot, FixedR.
- RecoveryMode: None, Martingale, DAlembert.
- GridMode: Disabled, SeparateProfit, UnifiedProfit.

필터

MTF는 상위 시간대 MACD 정렬이고 MA, ADX, ATR volatility, news는 독립적입니다.

News filter and CSV workflow

Live mode reads the MT5 Economic Calendar in broker - server time and blocks new entries if the calendar query fails. Backtests cannot read that live calendar: run MQL5\Scripts\White Rabbit News Exporter on a live/demo chart, cover the entire test interval, and write NewsCSVFile to the terminal Common\Files folder. The semicolon - delimited header is datetime;currency;importance;event_name, where importance 2 is moderate and 3 is high. Use the same broker/server timezone; for suffixed or non - FX symbols set ExportMoedas and NewsMoedasManual explicitly. Manual currencies take

precedence over automatic symbol parsing.

실행과 포지션 관리

spread, margin, volume step, tick size, stops/freeze 제한이 실행에 영향을 줍니다. Journal에서 확인하십시오.

Grid cycle and ATR spacing

Every additional grid leg is measured from the newest already - confirmed position on that side and must satisfy $ATR \times DistanciaMinima$. The initial order cannot recursively trigger another leg in the same calculation event; it becomes the anchor on the following cycle. Individual grid take - profits are disabled: Separate mode evaluates independent BUY/SELL cycles against frozen monetary targets and ends a side when it becomes flat; Unified evaluates the aggregate BUY+SELL basket and ends when both sides are flat. Realized commissions, swap, fees and stopped legs remain in the result while the corresponding cycle is open. The target triggers a close request, so actual exit costs and slippage can leave the final result slightly below it. Live cycle state is persisted across an EA restart. Grid is hedging - only and must be reoptimized after any EA, broker - contract or cost change.

청산 스택

Stop, ATR take, breakeven, ATR trailing, reversal exit는 독립적입니다.
ReversalExitUseEntryFilters가 청산 필터를 제어합니다.

위험과 복구

PositionSizeMode 하나만 선택합니다. Percentage/Fixed - R은 stop이 필요하며
Grid/Martingale/D'Alembert는 연구용입니다.

시간, 인터페이스, WFO

브로커 서버 시간, 자정 통과, Saturday/Sunday 설정을 지원합니다. WFO는 IS/OOS를 정의합니다.

Diagnostics and supplied utilities

The Experts/Journal tab is authoritative for rejected inputs, OrderCheck failures, news - calendar errors and close retries. Compile and run MQL5\Scripts\WhiteRabbit Filters SelfTest; its final line must report zero failures. Use White Rabbit News Exporter to build the test CSV, then verify its date range, currencies, delimiter and Common\Files location before a news - enabled backtest.

사이클 대시보드 텔레메트리

패널은 랏 계산과 바스켓 청산에 쓰이는 동일한 상태 스냅샷을 사용합니다.

- tick 주기 갱신은 초당 1회로 제한되며 초기화와 거래 이벤트는 즉시 갱신할 수 있습니다.
- Balance/Equity는 전체 계정입니다. Closed P&L은 OnInit 이후 변화이고 Open P&L/positions는 Symbol + Magic으로 필터한 현재 상태입니다.
- Martingale은 BUY/SELL별 연속 손실, 사이클 손실 횟수 · 총액, recovered, deficit, deficit × Multiplicador target을 표시합니다.
- MaxMartingaleSteps 초과 시 hard reset으로 기존 deficit을 버리고 다음 주문은 base lot을 씁니다. 방향별 최대 1개 포지션만 허용됩니다.
- D'Alembert는 BUY/SELL 현재 레벨과 정규화된 다음 랏을 표시합니다.

- Grid는 legs/volume, 비용 포함 realized, open P&L, cycle P&L, 시작 시 고정 target, remaining을 표시합니다.
- Anchor는 가장 최근 확정 포지션입니다. BUY는 $\text{anchor} - \text{ATR} \times \text{DistanciaMinima}$ 미만, SELL은 그 이상을 엄격히 요구하며 진행은 ATR로 표시됩니다.
- Separate는 flat이 된 방향의 사이클만 끝내고 Unified는 양쪽 모두 flat일 때 끝납니다. 처리 중 주문은 reset을 지연합니다.
- Target은 청산 요청을 시작할 뿐이며 실제 exit commission, fee, slippage로 최종 결과가 조금 낮을 수 있습니다.
- InterfaceLanguage는 11개 언어를 유지합니다. Auto는 Tester에서 English, live에서 터미널 언어를 사용하며 미번역 label은 English로 대체됩니다.

호환성과 제한

보수적인 규칙이며 브로커의 더 엄격한 제한이 우선합니다.

- Percentage와 Fixed - R은 AtivarStop=true가 필요합니다.
- Grid는 Monetary/Fixed Lot, Recovery_None, hedging account만 지원합니다.
- Grid는 take, 양수 DistanciaMinima, 최소 2의 제한이 필요합니다.
- 바스켓이 열려 있는 동안 해당 사이클의 실현 손실, swap, commission, fees는 목표 달성에 필요한 결과에 계속 포함되며 한 레그의 이익만으로 사라지지 않습니다.
- Grid_SeparateProfit에서 BUY와 SELL 사이클은 독립적입니다. 한 방향의 모든 포지션이 사라지면 그 방향 사이클은 종료되고 이후 진입은 종료된 적자를 이월하지 않는 새 사이클입니다.
- D'Alembert는 Fixed Lot, Grid_Disabled, DAlembertStep>0 전용입니다.
- Martingale은 MaxMartingaleSteps/MaxMartingaleLot을 따릅니다.
- OnOppositeOrder는 hedging, 양방향, grid 비활성이 필요합니다.
- News backtest는 Common\Files CSV가 필요합니다.
- 일정은 브로커 서버 시간을 사용합니다.
- 브로커별 suffix와 심볼 사양을 확인합니다.

검색된 set 라이브러리

개수는 파일과 매니페스트에서 읽습니다. 각 set은 연구 가설입니다. Counts and fingerprints were read at generation time.

Folder	Sets	Purpose
01_Forex	168	Per - asset baselines — Forex.
02_Metals	18	Per - asset baselines — Metals.
03_Cryptocurrencies	36	Per - asset baselines — Cryptocurrencies.
04_Indices_Energies	42	Per - asset baselines — Indices Energies.
05_US_Stocks_CFD	300	Per - asset baselines — US Stocks CFD.
06_Research_Matrix	935	Controlled one - axis research.
07_Entry_System_Matrix	3360	Indicator $\times$ entry method $\times$ management matrix.
08_Filter_Stack_Matrix	320	Signal - filter stack combinations.
09_Risk_Engine_Matrix	130	Compatible sizing, risk and recovery models.
10_Exit_Stack_Matrix	720	Exit - control stack combinations.

위험 경고

EA, set, 과거 결과는 미래 성과를 보장하지 않습니다. OOS와 demo로 검증하십시오.

전체 inputs 참조

표는 소스 선언 순서이며 구분 문자열도 .set schema에 포함됩니다.

No.	Section	Subsection	Parameter	Type	Default	Source description	Enum options	Operational notes	
1	General	—	NomedaEstrategia	string	"White Rabbit X"	Strategy Name	—	Use within its declared section and validate the complete combination.	
2	Entries, Signal and Position Management	—	TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	Entry timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Signal evaluation is gated to one decision per closed bar of this timeframe.	
3	Entries, Signal and Position Management	Entry Indicator	myBlankSpaceEntryIndicator	string	""	\	\	===== ===== ===== Entry Indicator ===== ===== ===== \\	\
4	Entries, Signal and Position Management	Entry Indicator	EntryIndicator	ENUM_ENTRY_INDICATOR	EntryIndicator_MACD	Selects the indicator used by Entry Method	EntryIndicator_MACD, EntryIndicator_EMA_Cross, EntryIndicator_Momentum, EntryIndicator_Stochastic, EntryIndicator_TRIX, EntryIndicator_RSI, EntryIndicator_CCI, EntryIndicator_WPR, EntryIndicator_DeMarker, EntryIndicator_MFI, EntryIndicator_OsMA, EntryIndicator_Ichimoku	Selects the engine; Fast_EMA, Slow_EMA and MACD_SMA are reused by that engine.	

5	Entries, Signal and Position Management	Entry Indicator	InpAppliedPrice	ENUM_APPLIED_PRICE	PRICE_CLOSE	Applied price used by the selected indicator	—	Use within its declared section and validate the complete combination.	
6	Entries, Signal and Position Management	Entry Indicator	Fast_EMA	int	12	First period: M ACD/EMA fast; oscillator period; Stochastic %K; Ichimoku Tenkan	—	First sequential period; for Ichimoku this is Tenkan.	
7	Entries, Signal and Position Management	Entry Indicator	Slow_EMA	int	26	Second period: M ACD/EMA slow; Ichimoku Kijun	—	Second sequential period; for Ichimoku this is Kijun.	
8	Entries, Signal and Position Management	Entry Indicator	MACD_SMA	int	9	Third period: MACD signal; oscillator signal; Stochastic %D; Ichimoku Senkou B	—	Third sequential period; for Ichimoku this is Senkou Span B.	
9	Entries, Signal and Position Management	Entry Method	myBlankSpace1	string	""	\	\	===== ===== ===== ===== Entry Method = ===== ===== ===== =====\	\

10	Entries, Signal and Position Management	Entry Method	EntryMethod	ENUM_ENTRY_TRIGGER_MODE	EntryTrigger_All	Reversal, signal cross, reference cross or their combinations	EntryTrigger_Reversal, EntryTrigger_SignalCross, EntryTrigger_ReferenceCross, EntryTrigger_ReversalAndSignalCross, EntryTrigger_ReversalAndReferenceCross, EntryTrigger_SignalAndReferenceCross, EntryTrigger_All	And modes require both events on the same closed bar; All is OR.	
11	Entries, Signal and Position Management	ATR Settings	myBlankSpace42	string	""	\	\	===== ===== ===== == ATR Settings ===== ===== ===== =====\	\
12	Entries, Signal and Position Management	ATR Settings	ATR_TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	Time Frame ATR	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
13	Entries, Signal and Position Management	ATR Settings	PeriodoATR	int	14	ATR Period	—	Use within its declared section and validate the complete combination.	
14	Entries, Signal and Position Management	Stop Loss	myBlankSpace4s2	string	""	\	\	===== ===== ===== ===== Stop Loss ===== ===== ===== =====\	\

15	Entries, Signal and Position Management	Stop Loss	AtivarStop	bool	true	Enable Stop Loss	—	Required by Percentage and Fixed - R sizing; recommended for every non - grid baseline.	
16	Entries, Signal and Position Management	Stop Loss	VelaStop	int	0	Stop Loss Candle	—	Use within its declared section and validate the complete combination.	
17	Entries, Signal and Position Management	Stop Loss	Stop	double	3	Stop Loss ATR Multiplier	—	Use within its declared section and validate the complete combination.	
18	Entries, Signal and Position Management	Take Profit	myBlankSpace101	string	""	\	\	===== ===== ===== ===== Take Profit == ===== ===== ===== ==\	\
19	Entries, Signal and Position Management	Take Profit	TakeOrganico	bool	false	Enable Organic ATR Take Profit	—	Use within its declared section and validate the complete combination.	
20	Entries, Signal and Position Management	Take Profit	AtivarTake	bool	true	Enable Take Profit	—	Required by supported grid operation.	

21	Entries, Signal and Position Management	Take Profit	VelaTake	int	0	Take Profit Candle	—	Use within its declared section and validate the complete combination.	
22	Entries, Signal and Position Management	Take Profit	Take	double	3	Take Profit ATR Multiplier	—	Use within its declared section and validate the complete combination.	
23	Signal Filters	MTF Alignment	myBlankSpaceMTF	string	""	\	\	===== ===== ===== == MTF Alignment ===== ===== ===== ==\	\
24	Signal Filters	MTF Alignment	AtivarFilterMTF	bool	false	Enable MTF Filter	—	Higher - timeframe alignment uses the EA's MACD trend layer.	
25	Signal Filters	MTF Alignment	MTF_RequiresAmbos	bool	false	Require Both Higher Timeframes Aligned	—	Use within its declared section and validate the complete combination.	
26	Signal Filters	Moving Average Filter	myBlankSpaceMA	string	""	\	\	===== ===== ===== Moving Average Filter == ===== ===== ===== ==\	\

27	Signal Filters	Moving Average Filter	AtivarFiltroMA	bool	false	Enable Moving Average Filter	—	Use within its declared section and validate the complete combination.	
28	Signal Filters	Moving Average Filter	MA_TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	MA Timeframe	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
29	Signal Filters	Moving Average Filter	MA_Period	int	200	MA Period	—	Use within its declared section and validate the complete combination.	
30	Signal Filters	Moving Average Filter	MA_Method	ENUM_MA_METHOD	MODE_EMA	MA Method	—	Use within its declared section and validate the complete combination.	
31	Signal Filters	Moving Average Filter	MA_AppliedPrice	ENUM_APPLIED_PRICE	PRICE_CLOSE	Applied Price	—	Use within its declared section and validate the complete combination.	
32	Signal Filters	Moving Average Filter	MetodoMA	MetodoFiltroMA	MA_PrecoEInclinacao	Price and Slope Rule	MA_ApenasPreco, MA_ApenasInclinacao, MA_PrecoEInclinacao, MA_PrecoOuInclinacao	Use within its declared section and validate the complete combination.	

33	Signal Filters	Moving Average Filter	SentidoMA	SentidoFiltroMA	MA_Tendencia	Trend or Reversal Direction	MA_Tendencia, MA_Reversao	Use within its declared section and validate the complete combination.	
34	Signal Filters	Moving Average Filter	MA_Slope Lookback	int	3	Slope Lookback Bars	—	Use within its declared section and validate the complete combination.	
35	Signal Filters	ADX Filter	myBlankSpaceMA1	string	""	\	\	===== ===== ===== == ADX Filter == ===== ===== ===== ==\	\
36	Signal Filters	ADX Filter	AtivarFiltroADX	bool	false	Enable ADX Trend Strength Filter	—	Use within its declared section and validate the complete combination.	
37	Signal Filters	ADX Filter	ADX_TimeFrame	ENUM_ALLOWED_TIMEFRAMES	M1	ADX Time frame	M1, M5, M15, M30, H1, H4, D1, W1	Use within its declared section and validate the complete combination.	
38	Signal Filters	ADX Filter	ADX_Period	int	14	ADX Period	—	Use within its declared section and validate the complete combination.	

39	Signal Filters	ADX Filter	ADX_Limar	double	25	Minimum ADX Value	—	Use within its declared section and validate the complete combination.	
40	Signal Filters	ADX Filter	MetodoADX	MetodoFiltroADX	ADX_ApenasForca	Strength or Strength Plus Direction	ADX_ApenasForca, ADX_ForcaMaisDirecaoDI	Use within its declared section and validate the complete combination.	
41	Signal Filters	Volatility Filter	myBlankSpaceVolatility	string	""	\	\	===== ===== ===== Volatility Filter == ===== ===== =====\	\
42	Signal Filters	Volatility Filter	EntradaATR	bool	false	Enable ATR Volatility Filter	—	Use within its declared section and validate the complete combination.	
43	Signal Filters	Volatility Filter	VolatilityFilter	ENUM_VOLATILITY_MODE	VOL_HIGH	Trade Volatility Condition	VOL_LOW, VOL_HIGH	Use within its declared section and validate the complete combination.	
44	Signal Filters	News Filter	myBlankSpaceNews	string	""	\	\	===== ===== ===== ===== News Filter == ===== ===== ===== ===== =====\	\

45	Signal Filters	News Filter	AtivarFiltroNoticias	bool	false	Enable News Filter	—	Live calendar errors block new entries; backtests require the exported CSV under Common\Files.	
46	Signal Filters	News Filter	NewsSomenteAltoImpacto	bool	false	High Impact Only	—	Use within its declared section and validate the complete combination.	
47	Signal Filters	News Filter	NewsMinutosAntes	int	15	Minutes Blocked Before Event	—	Use within its declared section and validate the complete combination.	
48	Signal Filters	News Filter	NewsMinutosDepois	int	15	Minutes Blocked After Event	—	Use within its declared section and validate the complete combination.	
49	Signal Filters	News Filter	NewsMoedasManual	string	""	Manual Currencies (e.g. "USD, EUR"); empty = auto by symbol	—	When non - empty, overrides automatic currency extraction ; required for most suffixes/n - FX symbols.	

50	Signal Filters	News Filter	NewsCSV File	string	"WhiteRabbit_News.csv"	Common\\Files CSV for Backtests	—	Semicolon CSV in Common\\Files: datetime;currency;importance;event_name, using broker - server time.	
51	Exit Management	—	AtivarBreakEven	bool	true	Enable BreakEven	—	Use within its declared section and validate the complete combination.	
52	Exit Management	—	BreakEvenDistance	double	1.0	BreakEven Distance (SL or ATR Stop Multiplier)	—	Use within its declared section and validate the complete combination.	
53	Exit Management	ATR Trailing	myBlankSpace46	string	""	\	\	===== ===== ===== == ATR Trailing = ===== ===== ===== ==\	\
54	Exit Management	ATR Trailing	AtivarTrailingATR	bool	false	Enable ATR Trailing Stop	—	Use within its declared section and validate the complete combination.	
55	Exit Management	ATR Trailing	MetodoDeCalculo	Candlestick type	CandleClose	Trailing Price Source	CandleOpen, CandleClose, CandleHigh, CandleLow, Preco	Use within its declared section and validate the complete combination.	

56	Exit Management	ATR Trailing	TrailVela	int	0	Trailing Candle	—	Use within its declared section and validate the complete combination.	
57	Exit Management	ATR Trailing	Trail	double	3	Trail	—	Use within its declared section and validate the complete combination.	
58	Exit Management	Reversal Exit	myBlankSpace10	string	""	\	\	===== ===== ===== == Reversal Exit == ===== ===== =====\ 	\
59	Exit Management	Reversal Exit	ReversalExitMode	ENUM_REVERSAL_EXIT_MODE	ReversalExit_OnIndicatorSignal	Declared at source line 319.	ReversalExit_Disabled, ReversalExit_OnOppositeOrder, ReversalExit_OnIndicatorSignal	OnOppositeOrder requires a hedging account, both sides and grid disabled.	
60	Exit Management	Reversal Exit	ReversalExitUseEntryFilters	bool	false	Apply entry filters to indicator exits	—	False uses the raw opposite indicator signal; true also requires entry filters.	
61	Risk and Position Size	—	TradeCapitalPercentage	double	100	Percentage of Total Capital Allocated to EA	—	Allocation must be positive and no greater than the whole EA capital base.	

62	Risk and Position Size	—	PositionSizeMode	ENUM_POSITION_SIZE_MODE	PositionSizeFixedLot	Declared at source line 351.	PositionSize_Percentage, PositionSize_Monetary, PositionSize_FixedLot, PositionSize_FixedR	Exactly one model is active; compatibility depends on stop and grid selections.	
63	Risk and Position Size	—	PositionSizeValue	double	0.01	Percentage=% risk; Monetary=currency per 1.00 lot; FixedLot=lots; FixedR=% of base capital per 1R	—	Meaning changes with PositionSizeMode; never compare raw values across modes.	
64	Risk and Position Size	Fixed - R Controls	myBlankSpaceRF	string	""	\	\	===== ===== ===== Fixed - R Controls ===== ===== ===== =\\	\
65	Risk and Position Size	Fixed - R Controls	CapitalBaseR	double	0	Base Capital for 1R (0 = balance at OnInit)	—	Zero captures balance at initialization; Fixed - R only.	
66	Risk and Position Size	Fixed - R Controls	MaxRiskTradeR	double	0	Maximum Risk per Trade in R (0 = no cap)	—	Zero disables this additional Fixed - R cap.	
67	Risk and Position Size	Daily Loss Limit	myBlankSpaceDL	string	""	\	\	===== ===== ===== Daily Loss Limit == ===== ===== =====\	\

68	Risk and Position Size	Daily Loss Limit	DailyLoss LimitPercent	double	0	Maximum Daily Loss Percentage (0 = disabled)	—	Zero disables the daily limit; use a value below a total account loss.	
69	Risk and Position Size	Equity/Margin Protection	myBlankSpaceRiskProtection	string	""	\	\	===== ===== == Equity/Margin Protection ===== ===== =====\	\
70	Risk and Position Size	Equity/Margin Protection	MaxEquityDrawdownPercent	double	30.0	Maximum EA drawdown before closing positions (0 = disabled)	—	Zero disables the EA equity stop.	
71	Risk and Position Size	Equity/Margin Protection	MinFreeMarginPercent	double	50.0	Minimum free margin to preserve after a new entry (0 = disabled)	—	Zero disables the post-entry free-margin reserve.	
72	Grid and Recovery	—	Recovery Mode	ENUM_RECOVERY_MODE	Recovery_None	Declared at source line 368.	Recovery_None, Recovery_Martingale, Recovery_DAlembert	None, Martingale or D'Alembert are mutually exclusive.	
73	Grid and Recovery	Recovery Target	myBlankSpace457	string	""	\	\	===== ===== ===== = Recovery Target = ===== ===== ===== \\	\

74	Grid and Recovery	Recovery Target	Multiplicator	double	1	Martingale or Grid Target Profit Multiplier	—	Recovery/ grid target multiplier; validate a value greater than one where escalation is intended.	
75	Grid and Recovery	Martingale Limits	myBlankSpace16	string	""	\	\	===== ===== ===== Martingale Limits = ===== ===== =====\	\
76	Grid and Recovery	Martingale Limits	MaxMartingaleSteps	int	0	Consecutive Losses Before Reset (0 = no limit)	—	Zero means no step limit; exceeding a positive limit hard - resets the old deficit and forces the next order to the base lot.	
77	Grid and Recovery	Martingale Limits	MaxMartingaleLot	double	0.0	Maximum Martingale or D'Alembert Lot (0 = broker limit only)	—	Zero means broker maximum only.	
78	Grid and Recovery	D'Alembert Settings	myBlankSpace_dal	string	""	\	\	===== ===== ===== D'Alembert Settings ===== ===== =====\	\
79	Grid and Recovery	D'Alembert Settings	D'AlembertStep	double	0.01	Lot Increment per Loss for D'Alembert	—	Must be positive; supported with Fixed Lot and grid disabled.	

80	Grid and Recovery	Grid Settings	myBlankSpace17	string	""	\	\	===== ===== ===== == Grid Settings ===== ===== ===== ==\	\
81	Grid and Recovery	Grid Settings	GridMode	ENUM_GRID_MODE	Grid_Disabled	Declared at source line 385.	Grid_Disabled, Grid_Separate Profit, Grid_Unified Profit	Supported with Monetary or Fixed Lot sizing, Recovery_None and a hedging account; targets are frozen per cycle.	
82	Grid and Recovery	Grid Settings	UseATRGrid	bool	false	Use ATR Only as Grid Signal	—	Research switch; require an existing basket anchor before adding a grid leg.	
83	Grid and Recovery	Grid Settings	Distance Minima	double	2	ATR Distance Multiplier for Next Grid Order	—	Positive ATR - distance multiplier between grid entries.	
84	Trading Schedule	Trading Hours	myBlankSpaceTradingHours	string	""	\	\	===== ===== ===== == Trading Hours == ===== ===== ===== \	\
85	Trading Schedule	Trading Hours	Feature for auto close	bool	false	Close Positions Outside Trading Hours	—	When enabled, positions are closed whenever server time is outside the interval.	

86	Trading Schedule	Trading Hours	TOD_From_Hour	int	00	Trading Start Hour	—	Use within its declared section and validate the complete combination.	
87	Trading Schedule	Trading Hours	TOD_From_Min	int	00	Trading Start Minute	—	Use within its declared section and validate the complete combination.	
88	Trading Schedule	Trading Hours	TOD_To_Hour	int	23	Trading End Hour	—	Use within its declared section and validate the complete combination.	
89	Trading Schedule	Trading Hours	TOD_To_Min	int	55	Trading End Minute	—	Use within its declared section and validate the complete combination.	
90	Trading Schedule	Trading Days	myBlankSpaceTradingDays	string	""	\	\	===== ===== ===== == Trading Days == ===== ===== ===== =\	\
91	Trading Schedule	Trading Days	TradeMonday	bool	true	Allow Trading on Monday	—	Use within its declared section and validate the complete combination.	

92	Trading Schedule	Trading Days	TradeTuesday	bool	true	Allow Trading on Tuesday	—	Use within its declared section and validate the complete combination.	
93	Trading Schedule	Trading Days	TradeWednesday	bool	true	Allow Trading on Wednesday	—	Use within its declared section and validate the complete combination.	
94	Trading Schedule	Trading Days	TradeThursday	bool	true	Allow Trading on Thursday	—	Use within its declared section and validate the complete combination.	
95	Trading Schedule	Trading Days	TradeFriday	bool	true	Allow Trading on Friday	—	Use within its declared section and validate the complete combination.	
96	Trading Schedule	Trading Days	TradeSaturday	bool	false	Allow Trading on Saturday	—	Explicit weekend permission; useful only when the broker symbol trades Saturday.	
97	Trading Schedule	Trading Days	TradeSunday	bool	false	Allow Trading on Sunday	—	Explicit weekend permission; useful only when the broker symbol trades Sunday.	

98	General Settings	Market Execution	myBlankSpaceExecution	string	""	\	\	===== ===== ===== Market Execution ===== ===== ===== =\	\
99	General Settings	Market Execution	MaxSpread	double	0	Maximum Allowed Spread for New Trades	—	Zero disables the entry spread ceiling.	
100	General Settings	Market Execution	MaxSlippage	int	10	Slippage, ajustado no OnInit	—	Use within its declared section and validate the complete combination.	
101	General Settings	Position Exposure	myBlankSpaceExposure	string	""	\	\	===== ===== ===== Position Exposure ===== ===== ===== \	\
102	General Settings	Position Exposure	MaxLong Trades	int	1	Maximum Simultaneous BUY Positions	—	Zero disables BUY entries; grid sides require zero or at least two, while Martingale permits at most one.	
103	General Settings	Position Exposure	MaxShort Trades	int	1	Maximum Simultaneous SELL Positions	—	Zero disables SELL entries; grid sides require zero or at least two, while Martingale permits at most one.	

104	General Settings	Position Exposure	Hedging	bool	false	Allow Hedging	—	Does not change the account type; the real MT5 account must also support hedging.	
105	General Settings	Identity and Interface	myBlankSpaceInterface	string	""	\	\	===== ===== ==== Identity and Interface ===== ===== =====\	\
106	General Settings	Identity and Interface	MagicNumber	int	384457	Magic Number	—	Must be unique for each independent strategy/symbol scope.	
107	General Settings	Identity and Interface	ModificationSafetyPoints	int	0	Optional extra distance beyond broker limits and current spread	—	Additional points beyond broker distance/spread constraints.	
108	General Settings	Identity and Interface	InterfaceLanguage	ENUM_INTERFACE_LANGUAGE	Language_Auto	Live chart interface language	Language_Auto, Language_English, Language_Portuguese, Language_Russian, Language_Chinese, Language_Spanish, Language_Japanese, Language_German, Language_Korean, Language_French, Language_Italian, Language_Turkish	Eleven live/visual UI languages; Auto uses English in Tester and untranslated labels fall back to English.	

109	General Settings	Chart Dashboard	myBlankSpaceDashboard	string	""	\	\	===== ===== ===== Chart Dashboard = ===== ===== =====\	\
110	General Settings	Chart Dashboard	EnableChartDashboard	bool	true	Show visual P&L panel on live and visual tester charts	—	Live/visual panel; periodic tick refresh is capped at once per second.	
111	General Settings	Chart Dashboard	DashboardCorner	ENUM_B ASE_CORNER	CORNER_LEFT_UP PER	Dashboard chart corner	—	Use within its declared section and validate the complete combination.	
112	General Settings	Chart Dashboard	DashboardOffsetX	int	12	Horizontal offset in pixels	—	Use within its declared section and validate the complete combination.	
113	General Settings	Chart Dashboard	DashboardOffsetY	int	24	Vertical offset in pixels	—	Use within its declared section and validate the complete combination.	
114	General Settings	Chart Dashboard	ShowClosedDealLabels	bool	true	Show monetary and percentage result at each closed trade	—	Use within its declared section and validate the complete combination.	

115	General Settings	Chart Dashboard	MaxVisibleDealLabels	int	120	Maximum closed - trade labels kept on chart	—	Use within its declared section and validate the complete combination.	
116	General Settings	Chart Dashboard	ClosedDealLabelFontSize	int	10	Closed - trade label font size	—	Use within its declared section and validate the complete combination.	
117	General Settings	Chart Dashboard	ApplyEmbeddedChartTheme	bool	true	Apply the White Rabbit X clean chart style on every machine	—	Use within its declared section and validate the complete combination.	
118	Optimization (WFO)	—	AtivarWFO	bool	false	Enable WFO	—	Enables the internal WFO boundary logic; still requires an external chronological process.	
119	Optimization (WFO)	—	MetodoDeEntradaWFO	WFO TIPO	Insample	Optimization Mode	Insample, InSample And OutSample	Use within its declared section and validate the complete combination.	
120	Optimization (WFO)	—	input_end_date	string	"2025.02.28"	Backtest End Date (manual)	—	Manual tester end date; keep synchronized with the selected test range.	

121	Optimization (WFO)	WFO Periods	myBlankSpaceWFO Periods	string	""	\	\	===== ===== ===== ===== WFO Periods = ===== ===== ===== ==\	\
122	Optimization (WFO)	WFO Periods	wfo_windowSize	WFO_TIME_PERIOD	Ano	In - Sample Window Size	Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom	Use within its declared section and validate the complete combination.	
123	Optimization (WFO)	WFO Periods	wfo_customWindow SizeDays	int	0	Custom Window Size in Days (0 = unused)	—	Use within its declared section and validate the complete combination.	
124	Optimization (WFO)	WFO Periods	wfo_stepSize	WFO_TIME_PERIOD	Semestre	Out - of - Sample Step Size	Nenhum, Ano, Semestre, Trimestre, Mes, Semana, Dia, Custom	Use within its declared section and validate the complete combination.	
125	Optimization (WFO)	WFO Periods	wfo_customStepSize Percent	int	0	Custom Step Size in Days or Percentage	—	Custom step: positive=percentage of IS; negative=fixed number of OOS days (for example - 61).	
126	Optimization (WFO)	Optimization Criterion	myBlankSpace4447	string	""	\	\	===== ===== ===== ===== Optimization Criterion ===== ===== ===== =====\	\

127	Optimization (WFO)	Optimization Criterion	selectedFormula	CustomFormulaType	Formula_ProfitPerTradeAdjustedByDD	Custom Optimization Formula	Formula_None, Formula_GridSurvivalScore, Formula_Profit, Formula_ProfitWinTradeDD, Formula_EfficiencyRelativeToDeposit, Formula_AdjustedEfficiencyForGrid, Formula_ProfitRelativeToDDAndDeposit, Formula_ProfitPerTradeAdjustedByDD, Formula_SharpeAdjustedByDD, Formula_PessimisticProfit, Formula_ResilienceToDrawdown, Formula_ReturnUniformity, Formula_SystemRobustness, Formula_LevainCompositeScore, Formula_SomaR	Optimization criterion only; inspect stability and OOS results before selection.	
-----	--------------------	------------------------	-----------------	-------------------	------------------------------------	-----------------------------	---	--	--

EA SHA - 256: D85A30A0836A9BE75F6DFC55868BDC664EE1FC7F5DD0840C029DEB0EF8AC8973 EA
version: 1.12