

Lab5: Packet Tracer - Configure a Wireless Network

Objectives

- = Connect to a wireless router
- = Configure the wireless router
- = Connect a wired device to the wireless router
- = Connect a wireless device to the wireless router
- = Add an AP to the network to extend wireless coverage
- = Update default router settings

Introduction

In this activity, you will configure a wireless router and an access point to accept wireless clients and route IP packets. Furthermore, you will also update some of the default settings.

Instructions


Part 1: Connect to a Wireless Router

Step 1: Connect Admin to WR.

a. Connect **Admin** to **WR** using a straight-through Ethernet cable through the Ethernet ports. Select **Connections**, represented by a lightning bolt, from the bottom-left side of Packet Tracer. Click **Copper Straight-Through**, represented by a solid black line.

b. When the cursor changes to connection mode, click **Admin** and choose **FastEthernet0**. Click **WR** and choose an available Ethernet port to connect the other end of the cable.

WR will act as a switch to the devices connected to the LAN and as a router to the internet.
Admin is now connected to the LAN (**GigabitEthernet 1**). When Packet Tracer displays green triangles on both sides of the connection between **Admin** and **WR**, continue to the next step.




Note: If no green triangles are shown, make sure to enable **Show Link Lights** under **Options > Preferences**. You may also click **Fast Forward Time** just above the **Connections** selection box in the yellow bar.

Step 2: Configure Admin to use DHCP.

To reach the **WR** management page, **Admin** must communicate on the network. A wireless router usually includes a DHCP server, and the DHCP server is usually enabled by default on the LAN. **Admin** will receive IP address information from the DHCP server on **WR**.

- Click **Admin**, and select the **Desktop** tab.
- Click **IP Configuration** and select **DHCP**.



The screenshot shows a web interface with tabs: Physical, Config, Desktop, Programming, and Attributes. The 'Desktop' tab is selected. Below the tabs is a blue header bar labeled 'IP Configuration' with a close button (X). Underneath, there's a dropdown menu for 'Interface' set to 'FastEthernet0'. The main area is titled 'IP Configuration' and contains two radio buttons: 'DHCP' (selected) and 'Static'. To the right of the 'Static' button, it says 'DHCP request successful.' Below these are four input fields: 'IPv4 Address' with value '192.168.0.100', 'Subnet Mask' with value '255.255.255.0', 'Default Gateway' with value '192.168.0.1', and 'DNS Server' with value '0.0.0.0'.

What is the IP address of the computer?

192.168.0.100

What is the subnet mask of the computer?

255.255.255.0

What is the default gateway of the computer?


192.168.0.1

- Close the **IP Configuration** window.

Note: Values can vary within the network range due to normal DHCP operation.

Step 3: Connect to the WR Web Interface.

- In the **Desktop** tab on **Admin**, choose **Web Browser**.
- Enter **192.168.0.1** in the URL field to open the web configuration page of the wireless router.
- Use **admin** for both the username and password.



d. Under the Network Setup heading on the **Basic Setup** page, notice the IP address range for the DHCP server.

Is the IP address for **Admin** within this range? Is it expected? Explain your answer.

Yes, and as expected, because WR is default to distribute IPs via DHCP in the range of 192.168.0.100 to 192.168.0.149, which is exactly where the Admin machine's IP falls.

Step 4: Configure the Internet Port of WR.

In this step, **WR** is configured to route the packets from the wireless clients to internet. You will configure the **Internet** port on **WR** to connect to the internet.

- Under the **Internet Setup** at the top of the **Basic Setup** page, change the Internet IP address method from **Automatic Configuration – DHCP** to **Static IP**.
- Type the IP address to be assigned to the Internet interface as follows:

Internet IP Address: 209.165.200.225

Subnet Mask: 255.255.255.252

Default Gateway: 209.165.200.226

DNS Server: 209.165.201.1


Internet Setup	
Internet Connection type	Static IP
Internet IP Address:	209 . 165 . 200 . 225
Subnet Mask:	255 . 255 . 255 . 252
Default Gateway:	209 . 165 . 200 . 226
DNS 1:	209 . 165 . 201 . 1

- Scroll down the page and click **Save Settings**.

Note: If you get a **Request Timeout** message, close the Admin window and wait for the orange lights to turn into green triangles. Click the fast forward button to make this happen faster. Then reconnect to **WR** from **Admin's** browser using the process explained in Step 3.

d. To verify connectivity, open a new web browser and navigate to **www.cisco.pka** server.

Note It may take a few seconds for the network to converge. Click **Fast Forward Time** or **Alt+D** to speed up the process.



Part 2: Configure the Wireless Settings

In this activity, you will only configure the wireless settings for 2.4 GHz.

Step 1: Configure the WR SSID.

- Navigate to the **WR** GUI interface at **192.168.0.1** in a web browser on **Admin**.
- Navigate to **Wireless > Basic Wireless Settings**.
- Change **Network Name (SSID)** to **aCompany** for only 2.4 GHz. Notice that SSIDs are case-sensitive.
- Change the **Standard Channel** to **6 - 2.437GHz**.
- For this activity, disable both 5 GHz frequencies. Leave the rest of the settings unchanged.


2.4 GHz	
Network Mode:	Auto
Network Name (SSID):	aCompany
SSID Broadcast:	☒ Enabled ☐ Disabled
Standard Channel:	6 - 2.437GHz
Channel Bandwidth:	Auto

- Scroll to the bottom of the window and click **Save Settings**.

Step 2: Configure wireless security settings.

In this step, you configure the wireless security settings using WPA2 security mode with encryption and passphrase.

- Navigate to **Wireless > Wireless Security**.
- Under the 2.4 GHz heading, select **WPA2 Personal** for the Security Mode.
- For the Encryption field, keep the default **AES** setting.
- In the Passphrase field, enter **Cisco123!** as the passphrase.



2.4 GHz

Security Mode: WPA2 Personal

Encryption: AES


Passphrase: Cisco123!


Key Renewal: 3600 seconds

- Click **Save Settings**.
- Verify that the settings in the **Basic Wireless Settings** and **Wireless Security** pages are correct and saved.

Step 3: Connect the Wireless Clients.

- Open **Laptop1**. Select the Desktop tab. Click **PC Wireless**.
- Select the **Connect** tab. Click **Refresh** as necessary. Select the Wireless Network Name **aCompany**.
- Enter the passphrase configured in the previous step. Enter **Cisco123!** In the pre-shared key field and click **Connect**. Close the PC Wireless window.
- Open a web browser and verify that you can navigate to **www.cisco.pka** server.
- Repeat the above steps to connect **Laptop2** to the wireless network.






Part 3: Connect Wireless Clients to an Access Point


An access point (AP) is a device that extends the wireless local area network. An access point is connected to a wired router using an Ethernet cable to project the signal to a desired location.

Step 1: Configure the Access Point.

- a. Connect **Port 0** of **AP** to an available Ethernet port of **WR** using a straight-through Ethernet cable.




- b. Click **AP**. Select the **Config** tab.
- c. Under the INTERFACE heading, select **Port 1**.
- d. In the SSID field, enter **aCompany**.
- e. Select **WPA2-PSK**. Enter the passphrase **Cisco123!** in the Pass Phrase field.
- f. Keep **AES** as the default Encryption Type.



Step 2: Connect the Wireless Clients.

- Open **Laptop3**. Select **Desktop** tab. Click **PC Wireless**.
- Select the **Connect** tab. Click **Refresh** as necessary. Select the Wireless Network Name **aCompany** with the stronger signal (Channel 1) and click **Connect**.
- Open a web browser and verify that you can navigate to **www.cisco.pka** server.



Part 4: Other Administrative Tasks

Step 1: Change the WR Access Password.

- On **Admin**, navigate to WR GUI interface at **192.168.0.1**.
- Navigate to **Administration > Management** and change the current **Router Password** to **cisco**.
- Scroll to the bottom of the window and click **Save Settings**.
- Use the username **admin** and the new password **cisco** when prompted to log in to the wireless router. Click **OK** to continue.
- Click **Continue** and move on to the next step.

Management
Router Access

Router Password:
Re-enter to confirm:

Admin
Physical Config Desktop Programming Attributes
Web Browser
http://192.168.0.1/apply.cgi
Go Stop
Settings are successful.
Continue

Step 2: Change the DHCP address range in WR.

In this step, you will change the internal network address from 192.168.0.0/24 to 192.168.50.0/24. When the LAN network address changes, the IP addresses on the devices in the LAN and WLAN must be renewed to receive new IP addresses before the lease is timed out.

- Navigate to **Setup > Basic Setup**.
- Scroll down the page to **Network Setup**.
- The IP address assigned to **Router IP** is 192.168.0.1. Change it to 192.168.50.1. Verify that IP address still start at .100, and there are 50 available IP addresses in the DHCP pool.
- Add **209.165.201.1** as the DNS server with the DHCP settings.
- Scroll to the bottom of the window and click **Save Settings**.

Network Setup
Router IP
DHCP Server Settings

IP Address:
Subnet Mask:
DHCP Server:
Start IP Address:
Maximum number of Users:
IP Address Range:
Client Lease Time:
Static DNS 1:
Static DNS 2:
Static DNS 3:
WINS:

f. Note that the DHCP range of addresses has been automatically updated to reflect the interface IP address change. The Web Browser will display a **Request Timeout** after a short time.


Why?

Because we recently changed the IP address of the router, which acts as the default gateway, from the old range of 192.168.0.1 to the new range of 192.168.50.1, administrator machines using the old IP address range will no longer be able to communicate with the router's new network until they receive the new IP address.

g. Close the **Admin** web browser.

h. In **Admin Desktop** tab, click **Command Prompt**.

i. Type **ipconfig /renew** to force **Admin** re-acquire its IP information via DHCP.



```
Admin
Physical Config Desktop Programming Attributes
Command Prompt

Cisco Packet Tracer PC Command Line 1.0
C:\>ipconfig

FastEthernet0 Connection: (default port)

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: FE80::206:2AFF:FE1C:CB64
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 192.168.50.103
    Subnet Mask . . . . .: 255.255.255.0
    Default Gateway . . . . .: ::
                                192.168.50.1

Bluetooth Connection:

    Connection-specific DNS Suffix...:
    Link-local IPv6 Address . . . . .: ::
    IPv6 Address . . . . .: ::
    IPv4 Address . . . . .: 0.0.0.0
    Subnet Mask . . . . .: 0.0.0.0
    Default Gateway . . . . .: ::
                                0.0.0.0


C:\>ipconfig /renew

    IP Address . . . . .: 192.168.50.103
    Subnet Mask . . . . .: 255.255.255.0
    Default Gateway . . . . .: 192.168.50.1
    DNS Server . . . . .: 209.165.201.1

C:\>
```



What is the new IP address information for **Admin**?

j. Verify that you can still navigate to **www.cisco.pka** server.





k. Renew the IP address on other laptops to verify that you can still navigate to **www.cisco.pka** server.


Laptop1




Laptop2



Laptop3





I. Notice that **Laptop1** connected to the **AP** instead of **WR**.

Why?

When save the IP address change on the WR, the wireless router reboot causing the Wi-Fi signal from the WR to temporarily drop.

Laptop1 then searches for and switches to an Access Point that is broadcasting with the same SSID, aCompany, and has a more stable and stronger signal at that time.

