


□ PPPoE接入服务器的配置--网络拓扑和基本配置





□ PPPoE接入服务器的配置--认证方法配置

Router(config)#aaa new-model


Router(config)# aaa authentication ppp myPPPoE group radius

• • • • • •

Router(config)# radius-server host 192.168.2.3 auth-port 1645 key radius123



□ PPPoE接入服务器的配置--AAA服务器配置





- □ PPPoE接入服务器的配置--地址池配置
 - o ip local pool PoolName StartIP EndIP
 - o ip local pool myPool 192.168.1.100 192.168.1.200



□ PPPoE接入服务器的配置--虚拟模板配置

Router(config)#interface virtual-template 1

Router(config-if)#ip unnumbered fa0/0

Router(config-if)#peer default ip address pool myPool

Router(config-if)#ppp authentication chap myPPPoE

Router(config-if)#exit



□ PPPoE接入服务器的配置--创建BBA组

Router(config)#bba-group pppoe myBBAGroup

Router(config-bba)#virtual-template 1

Router(config-bba)#exit

Router(config)#



□ PPPoE接入服务器的配置--配置物理接口

Router(config)#interface fa0/0

Router(config-if)#pppoe enable group myBBAGroup

Router(config-if)#exit



□验证配置的PPPoE接入服务器

