How to: RDP to Ubuntu



Software Management System Administration

If like me, you RDP to VMs running in Hyper-V, XenServer or vSphere quite often and you run Ubuntu you likely want to remote to these VMs too. Every time I setup a new Linux VM, I set this up. I documented the manual process for my

own purposes and I thought I'd share. There are alternatives to using RDP of course but this is for those of you who prefer it.

```
To run a command as administrator (user "root"), use "sudo <command>".

See "man sudo_root" for details.

rory@ubuntu:~$ sudo apt-get update
```

Enter **sudo apt-get update** and hit enter. When prompted enter suitable credentials.

```
e □ rory@ubuntu:~
rory@ubuntu:~$ sudo apt-get install xrdp
```

Enter **sudo apt-get install xrdp** and hit enter. This will install xrdp the remote desktop agent.

Enter **sudo apt-get install xfce4** and hit enter. This will install Xfce desktop environment.

```
echo xfce4-session >~/.xsession

rory@ubuntu:~$ echo xfce4-session >~/.xsession
```

Enter echo xfce4-session >~/.xsession and hit enter.

```
e □ rory@ubuntu:~
rory@ubuntu:~$ sudo nano /etc/xrdp/startwm.sh
```

Enter **sudo nano /etc/xrdp/startwm.sh** and hit enter to modify the text file.

Remove the line . /etc/X11/Xsession and add the line startxfce4 and then hit ctrl+X and save the file.




Enter **sudo service xrdp restart** and hit enter.

Enter **hostname -I** and hit enter. Make a note of the IP address.

Enter **sudo usermod -a -G tsusers <username>** and hit enter. This will add your account to the tsusers group which by default is the group with rights to RDP to this machine. Repeat this for all accounts you wish to RDP to the box with.



Launch the RDP client on your Windows machine, Mac or whatever you use and **Connect** to the IP address from your Ubuntu VM.



Enter your account credentials. Remember the username is case sensitive and hit \mathbf{OK} .

