

G18 class lab — the browser Lab map

G18 class lab — the browser Lab map

Everything happens in the app. Open **Lab map** in the left navigation — there is nothing to install and no file to open.

 You are the technician. Open the same company network.

You are the technician. Open the same company network.

You are the **helpdesk**. The PCs on the map belong to Sales, Finance, HR, and the branches — not to you.

 Ticket name = device on the map

Ticket name = device on the map

How you work

1. Sign in with the username and password your instructor gave you.
2. Open **Ticket queue** → **Assigned to me**.
3. Open **Lab map** and type the device from the ticket into **Find a device**.
4. **Click the device** to open it — a `C:\>` prompt on a PC, laptop, printer or VM, and an IOS console on a switch, router or access point. A desk PC also has a **Hardware** tab.
5. Run `ipconfig`, then `ping` the gateway, then `tracert`. Plug a cable if one is missing. Write what you did on the ticket.
6. Escalate **VAS**, **VPN**, **CBS**, or software updates. **Resolve** when the work is finished.

 Find a device: typing a department lists every desk in it, with its address

Find a device: typing a department lists every desk in it, with its address

Working the map

To do this	Do that
Find one device among hundreds	Type its name, address or department into Find a device
Open a command prompt or IOS console	Click the device box
Look inside a PC at its parts	Click the PC, then the Hardware tab, then a part
Plug a cable	Click a free port, then the other free port (syncs live for the class)
Unplug a cable	Click the cable (syncs live for the class)
Cancel a half-started cable	Click empty space on the map
Zoom	+ / – buttons, or Ctrl+scroll
See it bigger	Open full screen
Reset cabling to design	Reset to design (instructor only)

Each device box shows its name and its address. Hover a device or a cable for the full detail, including the public address it uses on the internet.

Reset to design puts the cabling and every device configuration back to the shipped design. Faults named by lab-map tickets that are still open are left in place — cables stay unplugged and broken PC parts stay broken — so those tickets remain solvable.

Some hardware faults take the command prompt away. A PC with no power, or one that will not boot, cannot be typed into: the window says what it is doing instead of giving you a cursor, and the **Hardware** tab is how you get it back.

What is in the lab

The Lab map: the data centre on the left, twelve HQ departments in columns behind their own routers, Batelco and the nine branches on the right

The Lab map: the data centre on the left, twelve HQ departments in columns behind their own routers, Batelco and the nine branches on the right

Where things sit:

Zone	Location on map	What is there
Data centre	Left	SW-VIRT and VM-* on VLAN 60, behind RD-DC
HQ departments	Middle (twelve columns)	Sales through Support — each with its own RD-* router, switch(es), desks and printer
HQ edge	Above department routers	R1-EDGE
Batelco WAN	Upper right	BAT-HAMALA plus area exchanges
Hosted cloud	Top right via Dubai	BAT-DUBAI → R-AZURE → SW-CLOUD → CLOUD-VM-*
Branches	Bottom right	Branch A-I, each behind its own router
Wireless	Selected sites	APs under Reception, Operations, Warehouse, Training, and Branches A-B

239 cables in the shipped design. A missing cable is the whole fault on a wiring ticket: no line on the map, and ping fails from that device. Click two free ports to plug a cable — the change syncs for the class. Hover a cable to see which kind it is.

Laptops, Wi-Fi and DHCP

A laptop is not a desk PC with a battery. It has no address typed into it — it asks CLOUD-VM-DHCP for one — and it has no cable, so it has to be associated with an access point first.

- wifi status says whether you are on the air and how strong the signal is; wifi scan lists what the laptop can hear, which may include an access point in the next department that is too weak to use.
- wifi join ProCloud-Staff Bahrain#2024 joins the staff network. The Training room is ProCloud-Training / Train#2024 .
- ipconfig showing 169.254.x.x means the laptop asked for an address and got no answer. That is a DHCP fault, not a Wi-Fi fault — work out which of the four steps failed: the link, the department router that relays the request, the path to 10.10.70.21 , or the service on the VM itself.
- ipconfig /release and ipconfig /renew do what they do on Windows. /renew on a PC with a typed-in address is an error, not a repair.

Printers have a front panel

A printer on this map is no longer only an address. Click it and you get its panel: `status` tells you what it is complaining about, and `clear`, `paper`, `toner`, `cancel`, `online` and `offline` are the things you would do standing in front of it. `print PRN-FIN` from a user's PC is the test page.

A jam is not a network fault, and `restart` will not clear one — that is the point of these tickets. Ping the printer first: if it answers, stop looking at the network and go and read the panel.

The three ways out of a department

1. Your gateway (the `.1` on your floor) is your **department's own router**, the `RD-*` box directly above your switch. Sales talking to Finance is already three routers: `RD-SALES`, `R1-EDGE`, `RD-FIN`.
2. Branches reach HQ through their own router, then their **area exchange**, then the **Hamala core**, then HQ's exchange, then `R1-EDGE`, then the department router.
3. Anything on the internet leaves through `R1-EDGE`, which translates the whole site to one public address (`203.0.113.34`). The hosted cloud VMs each have their own public address instead.

Use this when a ticket says “Sales cannot reach the CRM” or “Branch B cannot open the shop site”: find the device, check its address, then follow that path hop by hop with `tracert`.