

Insight Connect

Installation and Licensing

Proprietary and Restricted Rights Notices

This software and related documentation are proprietary to UGS Corporation.

©2007 UGS Corp. All Rights Reserved.

All trademarks belong to their respective holders.

Contents

System Requirements	1-1
Minimum System Configuration	1- 1
Graphics Cards	1- 2
Installing and Uninstalling the Application	2-1
Installing with Setup	2- 1
Uninstalling	2- 2
Licensing Options	3-1
Node-Locked (Standalone) Configuration	3- 1
Floating Configuration	3- 1
Dongles	3- 1
License File	3- 2
Configuring Node-Locked Licensing	4-1
Loading a Node-Locked License	4- 1
Configuring Floating Licensing	5-1
Identifying a License Server	5- 1
Installing and Configuring the License Manager	5- 1
Installing the Sentinel Driver	5- 3
Loading the Application for Floating Licenses	5- 3
Contact UGS	6-1

Chapter

1 *System Requirements*

Minimum System Configuration

Insight Server Minimum System Configuration

Server Hardware

- 32-bit (x86) or 64-bit (x64) processor.
- 512 megabytes (MB) of random access memory (RAM).
- 550 MB available disk space. The drive must be formatted as an NTFS file system.

Server Software

- Windows Server 2003 operating system.
- SharePoint Portal Server 2003 or Windows SharePoint Services 2.0.
- Web application server with:
 - Microsoft ASP.NET
 - Internet Information Services (IIS) 6.0

Server Database

- SQL Server 2000 or SQL Server 2005, with the latest service pack.

Network

- Multiple server configurations must be members of a Microsoft Windows 4.0, Windows 2000, or Windows Server 2003 domain.
- Internet Explorer 6.0.



If you are using non-English operating system and SharePoint, you need to load the Microsoft .NET language packs from: <http://www.microsoft.com/downloads/>

Insight Server Recommended System Configuration

- 32-bit (x86) or 64-bit (x64) processor.
- Dual processors.
- 4 GB RAM.

Disk I/O is one of the largest factors that prevents optimum Insight performance. For optimum SQL and SharePoint performance, you should organize your server hard drives as follows:

- One physical hard drive for Windows Server 2003 and all additional software loaded on the server, mirrored RAID 1.
- One physical hard drive for the SQL transaction log files, mirrored RAID 1.
- All remaining drives in a RAID 5 configuration to be used for SQL storage should be organized as described in the Creating Multiple .mdf Files section found below.
- GBIC network, highly available, low latency.

It is also helpful to use the fastest RPM hard drives that are available.

Insight Client Minimum System Configuration

- 32-bit (x86) or 64-bit (x64) processor.
- 1+ GB of RAM.
- Internet Explorer 6.0 or later.

Graphics Cards

Solid Edge and Insight are compatible with any graphic card that supports Windows XP or Windows Vista. Contact your card manufacturer to determine whether their graphics adapter or driver supports these operating systems.

You can find a list of graphics cards and associated drivers specifically tested with Solid Edge and Insight at the request of the manufacturers at <http://www.solidedge.com/graphics/default.htm>. This list should not be interpreted as the only cards that are compatible. The graphic card information is provided solely as a service to our customers. No warranties or commitments are expressed or implied. Inquiries regarding specific graphics card features should be directed to the respective vendors.

Chapter

2 *Installing and Uninstalling the Application*

To install Insight Connect, use any of the following methods:

- Insert the Insight Connect installation disk in the CD-ROM drive. If autorun is enabled, Insight Connect setup begins.
- In Windows Explorer, double-click the file (CD-ROM drive):\setup.exe.
- Use the Run command on the Start menu to run (CD-ROM drive):\setup.exe.

Keep these things in mind when installing Insight Connect:


- For information on addressing error messages you may encounter while installing, contact the Global Technical Access Center (GTAC) for product support at 800-955-0000.
- You must load and remove the application from an account that has Administrator privileges. The application will run under User, Administrator, or Guest privileges.
- Installation always delivers system files to the drive that contains the Windows operating system, regardless of the drive you specify for the installation.
- License Manager (FLEXlm) must be installed from the application DVD to manage floating license seats.



License Manager will not install on a 64-bit operation system. Floating client systems can be 64-bit operating systems, but floating servers must be 32-bit operating systems.

Installing with Setup

Use the setup window to set installation options, such as the installation directory.



Running the Solid Edge setup program when the product is already installed results in three options. You can:

- Modify the existing installation. Choose this option to install or uninstall template files or add-ins.
- Repair the existing installation. Choose this option to repair problems like missing files and invalid shortcuts.
- Remove the existing installation. Choose this option to remove the application from the computer.

Uninstalling

Use the Add/Remove Programs utility (located in the operating system Control Panel) to remove the application.

Select Insight Connect V20 from the list of installed products, and click Remove.



Always reboot your machine after uninstalling an application, prior to initiating the installation of another version of the product.

For more information on product enhancements, installation and removal, see the *readme.htm* file in the product folder.

Chapter

3 *Licensing Options*

When you purchase Insight Connect, you can choose between two licensing options: node-locked (standalone) or floating (server managed).

With node-locked licensing, the license is locked to serial number of the system disk drive (C:). With floating licensing, the FLEXlm software manages licenses for use on a network. A system administrator typically configures the license server.

Node-Locked (Standalone) Configuration

Node-locked or Standalone license configuration refers to each machine running the application having its own license file. To activate your license, start the License Utility and key in your 12-character License Key found printed inside the CD cover.

Floating Configuration

Floating licensing represents the ability to have multiple clients accessing the software through a license server. With a floating configuration, you can install the application on as many computers as needed on your network, and then have users check out licenses from a pool, not to exceed the total number of purchased seats.

The license server can be any computer on your network that is running a 32-bit Windows operating system. The only limitation is that the machine selected as the license server must be highly available for the users to access whenever needed and the license server must have a server dongle installed.

The license file used in a floating configuration establishes the location of the license server and the number of available licenses. The FLEXlm utilities that are necessary to simplify the process and to make full use of your license are delivered on your product CD/DVD.


Floating licenses should not be shared across country borders. It is strongly recommended that the floating licenses only be shared across a single LAN to minimize any additional points of network interruption.

Dongles

With floating licensing, the license server must have a server dongle installed. A hardware key, or dongle, is a small device that plugs into your computer and works with the software to provide licensing in a floating license configuration. The dongle plugs into the USB port of your computer.



Parallel server dongles are available upon request from GTAC for 32-bit operating systems.



The Sentinel driver can be installed from the Sentinel folder on the product DVD. Double-click *sentinel.exe* and follow the installation instructions to complete the installation of the driver.

License File

Both the node-locked and floating options require a license file that is customized to your installation. You will not be able to run Insight Connect without completing the licensing phase of the product installation.

An electronic copy of your license file (SELicense.dat) has been emailed to the point of contact on record for your company.

If you cannot locate this file, you can download it from the UGS Support web page at <http://www.ugs.com/Support/LicenseManagement>. Log in using your WebKey account, and then enter the Sold-To/Install ID number you want to download a license for.

Chapter

4 *Configuring Node-Locked Licensing*

To use a node-locked license, you must install the product and complete the licensing phase after installation.

Loading a Node-Locked License

Install Insight Connect from the product installation disk.


After installation, if you start the application with the delivered license file, licensing help is displayed. However, if you have altered or replaced the delivered license file, license validation occurs automatically.

To use License Wizard to generate a valid SELicense.dat:

1. Start the License Wizard.
 - ☐ On the Start menu, choose Programs® Insight Connect V20® License Wizard.
2. On the License Wizard dialog box, select Permanent Node-Locked and enter the license key for the purchased product, and click Next.



The 12-character License Key is printed inside the CD cover.



3. Click Finish to dismiss the License Wizard.

Chapter

5 *Configuring Floating Licensing*

Configuring floating licenses involves identifying a license server, installing and configuring FLEXlm, and installing Insight Connect.

Identifying a License Server

The license server is the computer on your network on which the FLEXlm software will reside. The license server can be any computer on your network that is running a 32-bit Windows operating system. The server and the client machines must be running the TCP/IP protocol and must be able to communicate with the server over the network. The license server must have the provided server dongle installed for floating licensing to work.


Installing and Configuring the License Manager

If you need to install the FLEXlm software, it is included on your product installation disk. To install FLEXlm, log in with administrative privileges and run `<DVD-ROM>:\ResKit\License Manager\setup.exe`, where `<DVD-ROM>` is the drive letter of the DVD-ROM drive. Follow the installation prompts. If Insight Connect is not installed on the licensing server, install the drivers from the ResKit folder.


To configure FLEXlm, log in with administrative privileges and follow these steps:

1. Copy your license file (SElicense.dat) to the `<DRIVE>:\SEFlex\program` folder, where `<DRIVE>` is the drive letter of the hard drive where you installed FLEXlm.
2. Double-click `lmtools.exe` in the `<DRIVE>:\SEFlex\program` folder to display the LMTOOLS dialog box.


- On the Service/License File page, click Configuration Using Services. Ensure that FLEXlm License Manager is highlighted in the list.



- On the Configure Services page, specify the location of the License Manager daemon *lmgrd.exe*, and the product license file, *SElicense.dat*. Also specify a location for the debug log file.
- Select the Use Services and Start Server at Power Up options.



6. Click Save Service. If prompted to save the FLEXlm settings, click Yes.



7. On the Start/Stop/Reread page, click Start Server to start licensing.

Installing the Sentinel Driver

The FLEXlm floating license configuration requires the use of a dongle (hardware key). The dongle plugs into the USB or parallel ports on your license server and requires the installation of Rainbow's Sentinel driver.



Parallel server dongles are available upon request from GTAC for 32-bit operating systems.

If you need to install the Sentinel driver manually, the Sentinel driver is located in the Sentinel folder on the product DVD. Double-click *sentinel.exe* and follow the installation instructions to complete the installation of the driver.

Loading the Application for Floating Licenses

Install Insight Connect on each client that will be running Insight connect. Copy the *SELicense.dat* file from the server to each client. Place it in the Insight Connect V20\Program folder.



- If you do not have a copy of your license file (SELicense.dat) saved to disk, please follow the instructions for downloading *SELicense.dat* or contact the person responsible for managing FLEXlm at your company to determine the license file location.

Chapter

6 *Contact UGS*

In the United States or Canada, call the Global Technical Access Center (GTAC):

1. Dial 1-800-955-0000.
2. Press 2 for technical software support.
3. Enter your Sold-to/Server ID, followed by the # sign.
4. Press 2 for Solid Edge.
5. Press 1 for Solid Edge application issues.

Outside the United States or Canada, contact your local UGS Channel Partner.