

NAME

gma go push-images – advertise images and update client caches

SYNOPSIS

(If using the full GMA core tool suite)

gma go push-images [options as described below...]

(Otherwise)

push-images -h

push-images -help

push-images [-D] [-H *host*] [-l *logfile*] [-list-profiles] [-P *password*] [-p *port*] [-S *profile*] [-u *user*] *mapfile*...

push-images [-debug] [-host *host*] [-list-profiles] [-log *logfile*] [-password *password*] [-port *port*] [-preferences *configfile*] [-select *profile*] [-username *user*] *mapfile*...

DESCRIPTION

Push-images provides a way to push a set of server-stored map images out to all the connected clients so that they will become aware of the location of where the images may be found.

Each named *mapfile* is read for image definition records (IMG types). For each one encountered, that image definition is sent to the server, which will add it to its internal database of known images and notes the server location where the graphic file may be downloaded. The server will then relay this information to all clients currently connected to it. Those clients will then download the files to their local disk caches so they are prepared to use the files on their map displays.

OPTIONS

The command-line options described below have a long form (e.g., -port) and a short form (e.g., -p) which are equivalent. In either case, the option may be introduced with either one or two hyphens (e.g., -port or --port). Options which take parameter values may have the value separated from the option name by a space or an equals sign (e.g., -port=2323 or -port 2323), except for boolean flags which may be given alone (e.g., -m) to indicate that the option is set to “true” or may be given an explicit value which must be attached to the option with an equals sign (e.g., -m=true or -m=false).

You **may not** combine multiple single-letter options into a single composite argument, (e.g., the options -r and -m would need to be entered as two separate options, not as -rm).

Any of these options will override the settings read from *preferences.json*.

-D, -debug *flags*

This adds debugging messages to push-image’s output. The *flags* value is a comma-separated list of debug flag names, which may be any of the following:

all	Enable all possible debugging flags.
none	If you want to explicitly disable debugging (e.g., if debugging is enabled in your configuration file but you want to turn it off via command-line option), you can specify <i>none</i> for the <i>flags</i> value to override the previous flag list and effectively disable debugging. If <i>none</i> appears in a comma-separated flag list, it cancels all the previously-set flags, but any other flag names which occur after it will be set.
auth	Authentication operations
binary	When printing certain values such as data transmitted over the network, include a hex dump of the actual binary data in addition to other debugging messages.
events	Show background events such as expiring timers and received process signals.
i/o	Show input/output operations used to get data in and out of the client.

`messages` Show the server messages sent and received.
`misc` Show miscellaneous debugging messages
`-H, -host host`
 Specifies the server's hostname.
`-l, -log file`
 Directs log messages (including any debugging output) to the named *file* instead of the standard output. You may explicitly specify the standard output by using a single hyphen as the file name (e.g., "`-log=-`").
`-list-profiles`
 Prints a list of all the profiles defined in the mapper preferences and exits.
`-P, -password password`
 If the server has authentication enabled, this specifies the password to be sent to log in. If the GM password is given, then the `push-images` user will have GM privileges on the server; otherwise normal player privileges will be granted, as with any client.
`-p, -port port`
 Specifies the server's TCP port number. The GMA map server's default port, 2323, will be assumed by default.
`-preferences configfile`
 Load preferences from the named JSON file instead of the default `~/.gma/mapper/preferences.json`.
`-S, -select profile`
 Use the named *profile* from the mapper preferences for the connection information instead of the one currently designated as the mapper's current profile.
`-u, -username user`
 This specifies the user name by which the server will know you. If you log in with the GM credentials, the server will assign you the name "GM" regardless of what you request here. If you don't use the GM credentials, you may not ask for the name "GM". If you do not specify a username, it will default to your local system username if possible.

SEE ALSO

`gma(6)`, `gma-mapper(5)`, `gma-mapper(6)`.

AUTHOR

Steve Willoughby / `steve@madscience.zone`.

BUGS**COPYRIGHT**

Part of the GMA software suite, copyright © 1992–2026 by Steven L. Willoughby, Aloha, Oregon, USA. All Rights Reserved. Distributed under BSD-3-Clause License.