


//makegamesplay
i.games

WebGL Build Host

User Guide - run your Unity Web build on any device and read its console live

Unity 2022.3 LTS+ · WebGL & WebGPU · Windows / macOS / Linux Editor · No dependencies

Point WebGL Build Host at your build folder and press Start. It serves the build over HTTPS on your network, shows a QR code and copyable URLs, and gives every browser that opens it a live console tab inside the Editor - so you can watch what happens on the actual device.



IN THIS GUIDE

- 1. Install and quick start
- 2. The window
- 3. The device console
- 4. Public link (cloudflared)
- 5. Troubleshooting

1 Install and quick start

Install

- **Asset Store:** import the package; it lands under `Assets/MakeGamesPlay/WebBuildHost/`.
- **UPM git URL:** Window > Package Manager > + > Add package from git URL:
<https://github.com/MakeGamesPlay/unity-webgl-build-host.git>


Requirements: Unity 2022.3 LTS or newer (covers the Unity 6 Web platform). Tested on 6000.5.0f1, 6000.4.11f1, 6000.3.17f1, 6000.0.77f1 and 2022.3.62f3. The Editor can run on Windows, macOS, or Linux; a prebuilt server is bundled for each. No Python, Node, or other runtime needed.

Quick start

1. Open **Tools > WebGL Build Host**.
2. Choose your Web build output folder.
3. Press **Start**.
4. Scan the QR code with your device, or open one of the listed URLs.
5. Accept the self-signed certificate prompt on the device (Advanced, then Proceed).
6. Each device appears as a console tab. Press **Stop** when you are done.

Why HTTPS? The self-signed certificate gives every device a secure context, which browsers require for the camera, microphone, WebXR, and multithreading (`SharedArrayBuffer`).


2 The window



Control	What it does
Build folder	The Web build output folder to serve (the one containing index.html).
Start / Stop	Starts or stops the server. It runs as its own process, so it keeps serving across recompiles, new builds, and Editor restarts; the window reconnects on its own.
URLs + QR code	Copyable local and HTTPS LAN URLs, and a scan-to-open QR code for the recommended URL.
Public link	Optional Cloudflare quick tunnel for testers outside your network. See section 4.
Headers	The server always sends what Unity Web builds need: Content-Encoding for .br/.gz files, application/wasm, and COOP/COEP.
Dev builds	Development Builds are served with Cache-Control: no-store, so a reload on the device always picks up the latest build.

3 The device console

Every browser that opens the build gets its own tab streaming its console output and uncaught errors into the Editor.



- **Tabs per device** with live/stale indicators.
- **Colour-coded levels** with per-level filters and counts, search, frame numbers, and duplicate collapsing.
- **Copy** (multi-select), **Save** to a text file, and **Clear** (also frees the server-side buffer).
- **Per-device actions:** Reload the page, Identify (flashes the device), and Copy bug report (a ready-to-paste Markdown summary).

4 Public link (cloudflared)

By default the build is reachable only on your local network. The public link option serves it through a Cloudflare quick tunnel: a temporary public HTTPS URL, with no Cloudflare account needed. Useful when the tester is somewhere else, the network blocks device-to-device traffic (common on guest and corporate Wi-Fi), or you want to test over mobile data.

Quick tunnels use Cloudflare's free `cloudflared` tool. The window checks whether it is installed and shows the install command for your platform if not:

Platform	Install
Windows	<code>winget install --id Cloudflare.cloudflared</code>
macOS	<code>brew install cloudflared</code>
Linux	Cloudflare's apt/rpm repo, or a binary from the releases page.

The host checks the tunnel's health every 15 seconds and marks it offline if it stops responding (for example after the machine sleeps); Stop and Start to reconnect.

5 Troubleshooting

Symptom	Fix
Certificate warning on the device	Expected: the HTTPS certificate is self-signed for local use. Tap Advanced, then Proceed.
No public link appears	Install c1oudflared (section 4) and confirm it is on the PATH, or use the LAN URL.
A device cannot reach the LAN URL	The device and the Editor need to be on the same network, and the firewall needs to allow the port. The public link works around networks that block device-to-device traffic.
Public link shows offline	The quick tunnel stopped responding (machine sleep and network changes are common causes). Stop and Start the server to reconnect.
Build loads but no logs appear	The console streams from pages served by this host. Confirm the device opened one of the window's URLs and the tab shows a live indicator.

More: the project README at github.com/MakeGamesPlay/unity-webgl-build-host.