

Autopilot Imaging: Start to Finish Manual

Windows Autopilot — Zero-Touch Device Provisioning

Step 1 — Collect the Hardware Hash

- Open PowerShell as Administrator on the device.
- Run: `Set-ExecutionPolicy -Scope Process -ExecutionPolicy Unrestricted` → type Y
- Run: `Install-Script -Name Get-WindowsAutopilotInfo` → type Y through prompts
- Run: `Get-WindowsAutopilotInfo -OutputFile C:\autopilot.csv`
- Copy C:\autopilot.csv to USB or email to yourself.

Step 2 — Import into Intune

- Go to endpoint.microsoft.com → Devices → Enrollment → Windows Autopilot → Devices → Import
- Upload the CSV file.
- Click Sync and wait 5 minutes.
- Confirm the device serial number appears with Profile status = Assigned.

Step 3 — Add to Entra Security Group

- Go to entra.microsoft.com → Groups → [Autopilot Corp Group] → Members → Add members
- Search for the device and add it.

Step 4 — Reset to OOB

- On the device run: `%windir%\system32\sysprep\sysprep.exe /oobe /shutdown`
- Device will shut down. Ensure it is on wired Ethernet before powering back on.

Step 5 — Pre-Provisioning

- Power on → at the first OOB screen press Windows key 5 times.
- Select Windows Autopilot provisioning → Provision.
- Wait for green success screen → Reseal.

Step 6 — User Setup

- Power back on.
- Sign in with a corporate work account.
- Confirm device lands on desktop.

Step 7 — Verify Enrollment

- Confirm Datto RMM agent is present: C:\Program Files (x86)\CentraStage\CagService.exe
- Verify device appears in Datto RMM → Sites → Corporate → Devices
- Verify device appears in Intune → Devices → Windows
- Verify device appears in Entra → Devices → All Devices