

Fruit Cake (Kex)

Egg-sugar batter with butter, flour and rum, baked on Moulinex programme 18 with raisins and candied fruit added at the beeps.

1 cake, 1000 g

3 h 12 min

Easy

1 cook

1 ASSUMPTIONS

What I decided for you — override anything here

Whisk eggs in Kenwood mixer Recipe says deep bowl; mixer whisk frees hands for fruit prep and weighs sugar. Hand-whisk 5 min as override.	Programme 18 is fixed 1000 g Manual: programme 18 offers only 1000 g, total 1:29, no delay start. Matches the recipe's 1000 g weight.
Whisk speed set to high Recipe gives no speed. Aim for pale, thick mass after 5 minutes; lower the speed if batter splashes.	Type 45 flour = plain flour Fine-milled wheat flour; Rimi plain flour photo used. Any fine plain wheat flour works.
Vanilla sugar packet = 8 g Dr. Oetker-size packet assumed; use your packet's label. A pinch of salt is about 1 g.	Butter softened before starting Take 230 g butter out about 1 hour ahead; it should dent under a finger. Cold butter will not blend in.
Fruit goes in at the beeps Manual: ingredient signal shows about 1:23 on a 1:29 cycle, so about 6 minutes after start, as in the recipe.	10 min keep-warm and 60 min cool Programme 18 includes 1 h keep-warm. Extra 10 min is optional per the recipe; cooling time follows the manual's bread advice.

2 REQUIRED


TIME

hands-on 0:30

unattended 2:44

3 h 12 min

🕒 **TIMELINE**



🔄 **CHECKPOINTS — ALL TRUE BEFORE MOVING ON**

- 🔄 **Pan loaded · 0:22**

Batter, rum, butter, flour, baking powder in pan; fruit weighed aside
- 🔄 **Fruit-in · 0:34**

Beeps heard, raisins and candied fruit added, lid closed
- 🔄 **Cake-out · 2:12**

Cake on rack, both paddles removed

 TOOLS AND PARTS



Kenwood mixer

Weighs sugar, whisks eggs 5 min

 High speed, 5 min

 n/a




5L bowl



Whisk



Grey spatula



Kitchen scale

Weighs fruit, butter and flour

 Grams, tare between items





Moulinex bread maker

Mixes and bakes the cake

 1000 g fixed, medium crust

 Program 18 (Cake)





Wire rack

Cools the cake

 60 min, room temperature

 **INGREDIENTS**

	eggs	5	batter
	sugar	165 g	batter
	vanilla sugar	1 packet (8 g)	batter
	fine salt	1 pinch	batter
	dark rum	1½ tbsp	added to pan
	soft butter	230 g	added to pan
	plain flour	330 g	type 45, fine
	baking powder	2½ tsp	added to pan
	raisins	75 g	at beep
	candied fruit	75 g	at beep

3 STEPS

1 Crack eggs

Cook

0

5 eggs

eggs

5

Crack 5 eggs into the 5L bowl, keeping shell out of the bowl.

✓ 5 eggs in bowl, no shell.



Kenwood mixer



5L bowl

2 Weigh sugar

Cook



165 g

sugar

165 g

Press tare on the integrated scale, then pour 165 g white sugar onto the eggs.

✓ Scale reads 165 g.



Kenwood mixer

3 Add vanilla sugar

Cook



8 g

vanilla sugar

1 packet (8 g)

Tip 1 packet (8 g) vanilla sugar into the bowl.

✓ Packet emptied into bowl.



Kenwood mixer



5L bowl

4 Add salt

Cook



1 g

fine salt

1 pinch

Add 1 pinch (about 1 g) fine salt to the bowl.

✓ Pinch of salt in bowl.



Kenwood mixer



5L bowl

5

Weigh raisins

Cook



75 g



raisins

75 g

Place a small bowl on the scale, tare, then weigh 75 g raisins and set aside.

✔ Scale reads 75 g.



Kitchen scale

6

Weigh candied fruit

Cook



75 g




candied fruit

75 g

Tare a second small bowl and weigh 75 g candied fruit, set aside next to the raisins.

✔ Scale reads 75 g.



Kitchen scale

7

Fit whisk

Cook



off

Fit the whisk on the bowl-tool socket and lower the mixer head onto the 5L bowl.

✔ Whisk seated, head locked down.



Kenwood mixer



Whisk

8

Whisk eggs and sugar

Cook



high speed

5 min

Whisk eggs, sugar, vanilla sugar and salt on high speed for 5 minutes.

✔ Mass pale, thick, sugar dissolved.



Kenwood mixer



Whisk

9 Pour batter into pan

 Cook



🕒 paddles in pan

Lift the whisk out, then scrape all the whisked batter into the bread pan with the grey spatula.

🕒 Bowl empty, batter in pan.



Grey spatula



Moulinex bread maker

10 Add rum

 Cook



🕒 1½ tbsp



dark rum

1½ tbsp

Measure 1½ tbsp dark rum with the tablespoon measure and pour it over the batter.

🕒 1½ level tablespoons in pan.



Moulinex bread maker

11 Add softened butter

 Cook



🕒 230 g



soft butter

230 g

Stand the pan on the scale, tare, then add 230 g soft butter in lumps.

🕒 Scale reads 230 g.



Kitchen scale

12 Add flour

 Cook



🕒 330 g



plain flour

330 g

Tare the scale again and spoon 330 g plain flour on top of the butter.

🕒 Scale reads 330 g.



Kitchen scale

13 Add baking powder

Cook



2½ tsp



baking powder

2½ tsp

Measure 2½ level teaspoons baking powder with the teaspoon measure and sprinkle over the flour.

☑ 2½ level teaspoons in pan.



Moulinex bread maker

14 Clip pan into machine

Cook



2 clicks

Lower the pan into the machine and press one side, then the other, until it clicks onto the drive.

☑ Pan clipped on both sides.



Moulinex bread maker

15 Plug in machine


Cook



default 1

Close the lid and plug into an earthed socket; wait for the beep.

☑ Beep; programme 1 and medium crust shown.



Control panel:
menu, weight,
crust, on/off



Moulinex bread maker

16 Select programme 18

Cook




Program 18

1000 g fixed

Press the menu button repeatedly until 18 shows; weight is fixed at 1000 g for this programme.

☑ Display shows 18 and 1:29.



Control panel:
menu, weight,
crust, on/off



Moulinex bread maker

17 Set medium crust


👤 Cook



🔹 crust medium

Press the crust button until the medium indicator lights (default).

🕒 Medium crust indicator lit.



Control panel:
menu, weight,
crust, on/off



Moulinex bread
maker

18 Start programme 18

👤 Cook




🕒 Program 18

🕒 1:29

Press the on/off button once; the run light comes on and timer dots blink.

🕒 Run light on, 1:29 counting down.



Control panel:
menu, weight,
crust, on/off



Moulinex bread
maker

19 Wait for first beeps

👤 Cook



🕒 6 min

🔊 ingredient beeps

Leave lid closed for about 6 minutes until the series of beeps sounds, display near 1:23.

🕒 Beeps sound, timer about 1:23.



Moulinex bread
maker

20 Add raisins

👤 Cook



🕒 75 g



raisins

75 g

Open the lid and add the 75 g raisins into the pan without spilling outside it.

🕒 All 75 g raisins in pan.



Moulinex bread
maker

21 Add candied fruit

 Cook



 75 g



candied fruit

75 g

Add the 75 g candied fruit and close the lid at once.

☑ Candied fruit in, lid closed.



Moulinex bread
maker

22 Wait for programme end

 Cook



⌚ Program 18 ⌚ 1 h 23 min

Leave the machine alone until the display reaches 0:00 and several beeps sound, about 1 h 23 min later.

☑ 0:00 shown, several beeps.



Moulinex bread
maker

23 Keep warm 10 minutes

 Cook



⌚ 10 min ⌚ optional

For a well-baked cake, leave it in the keep-warm cycle for 10 more minutes (optional).

☑ 10 minutes elapsed.



Moulinex bread
maker

24 Unplug machine

 Cook



⚠ hot

Pull the plug from the socket.

☑ Plug out, display dark.



Moulinex bread
maker

25 Unclip hot pan

 Cook



 oven gloves

With oven gloves, tilt the pan slightly to one side and unclip it; handle and lid inside are hot.

- ✓ Pan lifted out on the worktop.



Moulinex bread maker

26 Turn cake out

 Cook



 1 cake

Tip the cake out of the pan onto a wire rack.

- ✓ Cake free of the pan.



Moulinex bread maker

27 Remove stuck paddles

 Cook



 2 paddles

If a kneading paddle stays in the cake, lift it out with the hook, repeating for the second paddle.

- ✓ No paddle left in cake.



Moulinex bread maker

28 Cool cake on rack

 Cook




 60 min

Leave the cake on the wire rack for 60 minutes before slicing.

- ✓ Cake cool to the touch.

Bread pan, loading order



Add in numbered order; fruit joins at the beeps.

⚠ Wash hands and bowl after raw egg

⚠ Pan, handle and lid inside are hot: use oven gloves

⚠ Do not wash pan parts in a dishwasher