DCS AI COPILOT — WHAT DO I SAY WHEN?

EAT → CROSSING → COMMENCING

1 Marshal gives EAT

SAY: “EAT TWO ONE”

Stores the next **:21**. Full-time example: “EAT ONE FOUR TWO ONE”.

2 Cross marshal fix

SAY: “CROSSING”

Records now and calculates the hold to EAT. Say it again at a later crossing to replan.

3 Leave the hold

SAY: “COMMENCING”

Starts approach guidance. The clock reaching EAT does not commence automatically.

4 Check the plan

SAY: “CASE THREE STATUS”

Opens the CASE III page without changing the plan.

Notes

Need	Say	Result
Save a reminder	**NOTE TANKER NORTH**	Saves everything after NOTE
Show notes	**NOTES**	Returns to notes/targets
Remove all notes	**CLEAR NOTES**	CASE III is preserved

PTT: Hold → wait for **RECORDING** → speak the whole phrase → release → check **LAST TRANSCRIPT** and **LAST ERROR**.

CLEAR CASE and CLEAR NOTES are different commands.

VOICE COMMAND QUICK REFERENCE

Action	Primary phrase	Useful aliases
Open/check CASE III	**CASE THREE STATUS**	CASE THREE, CASE 3, CASE III, CASE TREE, CASE FREE, THIS THREE
Set EAT	**EAT THREE TWO**	E A T 14:32; assignment labels TIME, PUSH TIME, EXPECTED APPROACH TIME
Mark fix crossing	**CROSSING**	CROSSING NOW; in CASE III: MARSHAL, MARSHAL CROSS, MARSHAL CROSSING
Begin approach	**COMMENCING**	COMMENCE, COMMENCE NOW
Reset CASE III	**CLEAR CASE**	CLEAR CASE THREE, RESET CASE THREE, CLEAR CASE TREE
Manual PC-clock sync	**SYNC CLOCK 1421**	Digits may be spoken separately; only valid with PC time source
Create note	**NOTE <text>**	NOTERA, ANTECKNA, ANTECKNING
Show notes	**NOTES**	SHOW NOTES, BACK TO NOTES
Clear notes	**CLEAR NOTES**	CLEAR, CLEAR NOTE, RENSA, RENSA ANTECKNINGAR
Theme	**DAY MODE / NIGHT MODE**	DAYTIME / NIGHTTIME

Marshal assignment example

> **SAY:** “CASE THREE, MARSHAL TWO ZERO ZERO TWO TWO, ANGELS SEVEN, TIME THREE TWO, BUTTON ONE FIVE, FINAL BEARING ONE SEVEN ZERO, TACAN SEVEN TWO X, ICLS ONE.”

Available labeled fields: radial/marshal, DME, angels, time/EAT, button, final bearing/FB, TACAN and ICLS. Fields may be spoken separately. Invalid fields are rejected rather than partially applied.

Time source

- **MISSION:** DCS-BIOS mission start + model time. It follows simulation time and freezes when DCS is paused; no local extrapolation.
- **PC:** used until mission-time data arrives.
- **MANUAL:** with PC source only, “SYNC CLOCK HHMM” offsets CASE III without changing Windows time.
- If mission packets stop, the last mission reading remains selected and is marked not live; Copilot does not silently switch to PC time.

MICROPHONE & TROUBLESHOOTING

Select the input

1. Start DCS AI Copilot and open its dashboard.
2. In **VOICE**, select the desired physical microphone.
3. Press **Use microphone**.
4. Hold PTT and verify **RECORDING**.
5. Say “NOTE MICROPHONE TEST”, release, and check **LAST TRANSCRIPT**.

The selection is saved by exact device name + Windows host API. It does not alter Windows, SRS, Discord, DCS or VR audio settings.

Which duplicate should I choose?

MME, DirectSound, WASAPI and WDM-KS can be different Windows paths to the same physical microphone. There is no universal requirement to use MME. Choose the correct physical name, test it, and keep the entry that records reliably. A webcam is a common accidental default.

Fast fault checks

Problem	Check
Not listed	Windows Sound Input → dashboard refresh → restart Copilot with device connected
Wrong input	Select exact device + host API; do not rely on Windows default
Windows works, Copilot fails	Privacy permission, input level, exclusive use, another host-API entry, LAST ERROR
PTT but no transcript	RECORDING visible, speak after it appears, API key/quota/network, queue not full
Wrong words/numbers	Mic distance/noise, speak digits distinctly, check LAST TRANSCRIPT
Bluetooth changed	Re-select the currently listed headset/input profile
USB reconnected	Name-based UI choice usually survives; a manual numeric index may change

No automatic microphone fallback. If the selected device is disconnected, reconnect it or explicitly select another input.

> **Dashboard fields:** selected MICROPHONE, VOICE STATUS, STT MODEL/TIME, PTT state, LAST TRANSCRIPT, LAST ERROR, time source and CASE III state.