
FTP Operation



Note that Ports 1216 & 1217 are ephemeral ports. Any port [1024, 65535] will work.

FTP Commands

COMMAND	DESCRIPTION
USER username	User name on the FTP server
PASS password	User's password on the FTP server
SYST	Type of operating system requested
TYPE type	File type to be transferred: A (ASCII), I (Image/Binary)
PORT n1,n2,n3,n4,n5,n6	Client IP address (n1-n4) and port number (n5, n6)
RETR filename.type	Retrieve (get) a file
STOR filename.type	Store (put) a file
LIST filelist	List files or directories
QUIT	Log off from server

FTP Reply Codes

REPLY	DESCRIPTION
1 yz	Positive reply, wait for another reply before sending a new command
2 yz	Positive reply, a new command can be sent
3 yz	Positive reply, another command is awaited
4 yZ	Negative reply, try again
5 yz	Negative reply, do not retry
X 0 Z	Syntax
X1Z	Information
X 2 Z	Control or data connection
X3 Z	Authentication
X4Z	Unspecified
x5Z	File status

Active FTP

Active (with PORT)

This is the standard FTP mode for Windows.

Operation

The FTP client:

Opens a data port and listens to it, awaiting for a client to connect to Sends PORT message, with its own IP address the data port number

The FTP server:

Must open a new connection (as a client) using data port

We can say that the FTP client and server change their roles for the data connection (the client is now a server, the server acts like a client).

All the data should flow through that connection When the data ends, that connection is disestablished Very important: synchronization of the data connection

Passive FTP

Passive (with PASV)

This is the standard FTP mode for Unix (and most servers like this better).

Operation

The FTP client:

Sends the message PASV, asking what is the data port When receives the message 227, it knows the data port


The FTP server:


When receives PASV, opens a new data port Waits until the client connects to it


All the data should flow through that connection When the data ends, that connection is disestablished Very important: synchronization of the data connection


Active FTP mode


p. 50**, RFC 959**
































































Passive FTP mode





































Source: Computer Networking and the Internet (5/e) by Fred Halsall

















PASSIVE FTP Operation SERVER CLIENT control connection Data connection Data connection control connection Port **Port Port** Port 2024 1121 21 1120 **Active open** Passive open TCP control connection 220 FTP server ready to Port 21 established **USER <username>** 331 password required PASS <password> Port n5, n6 220 user <username> logged in (or Port 50069 in this example) **PASV** 227 Entering PASV mode (192,168,150,90,195,149) **LIST** dir 150 Opening ASCII mode data connection for file list Client does an active open to Port n5,n6 Send file through data connection 226 File transfer complete **QUIT** User is prompted for a command 221 Goodbye 48

Source: Computer Networking and the Internet (5/e) by Fred Halsall

PASSIVE FTP Operation SERVER CLIENT Data connection control connection Data connection control connection Port **Port Port** Port 2024 1121 21 1120 **Active open Passive open** TCP control connection 220 FTP server ready to Port 21 established **USER <username>** 331 password required PASS <password> Port n5, n6 220 user <username> logged in (or Port 50069 in this example) **PASV** 227 Entering PASV mode (192,168,150,90,195,149) **LIST** dir 150 Opening ASCII mode data connection for file list Client does an active open to Port n5,n6 Send file through data connection 226 File transfer complete **QUIT** User is prompted for a command Server closes data connection 221 Goodbye time 49 first, then control connection

<u>Security Issues</u>

PASSIVE:

Administrators may not want to use PASSIVE because the FTP server can open any *ephemeral port number*.

Many FTP servers are configured with an *ephemeral port range* of 1024 to 65535.

It means that the Firewall configuration has to allow full access to all ephemeral ports for any connections. This may be considered insecure.

ACTIVE:

On the other hand, the client's local firewall may prevent the data connection FTP to work for the same reason.