Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring AWS Inspector Connectors

The AWS Inspector connector allows Stellar Cyber to ingest scan events from AWS Inspector.

Amazon Inspector is a vulnerability management service. It discovers and scans Amazon EC2 instances, container images in Amazon ECR, and Lambda functions. When Amazon Inspector detects a software vulnerability or unintended network exposure, it creates a finding, which is a detailed report about the issue.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: AWS Inspector

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Inspector Findings (not configurable in the user interface)	Syslog	msg_class: `aws_inspector_finding` msg_origin.source: `aws_inspector` msg_origin.vendor:

Content Type	Index	Locating Records
		`aws` msg_origin.category: `security_scan`

Domain

N/A

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- For Access Key / Secret Key Auth Method: Access Key and Secret Key, plus Region
- For IAM Role Auth Method: Source Account Access Key, Source Account Secret Key, and IAM Role ARN, plus Region

Adding an AWS Inspector Connector

To add an AWS Inspector connector:

1. Obtain AWS Inspector credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion


Obtaining AWS Inspector Credentials

There are two authentication methods: **Access Key / Secret Key** or **IAM Role** (IAM Assume Role).

Configuring Credentials for Access Key / Secret Key

To configure the credentials for **Access Key / Secret Key** Auth Method:


1. Log in to the IAM Console with your AWS account ID, your IAM user name, and password. You must have the permissions required to create access keys for a user.
2. Choose **Users**, then click the user name, and click **Security credentials**.




3. In the **Access keys** section, choose **Create access key**. Access keys have two parts: an access key and a secret access key. Click **Create access key**.



4. On the **Access key best practices & alternatives** page, choose **Other** and then choose **Next**.



5. (Optional) On the **Set description tag** page, enter a description.
6. Click **Create access key**.
7. On the **Retrieve access keys** page, choose **Show** to reveal the value of the user's secret access key. Save the access key and secret access key in a secure location. You will need them when configuring the connector in Stellar Cyber.




8. Click **Done**.


For **Access Key / Secret Key** Auth Method, attach the policy to the user. See [Attach Permissions Policies to User]. For **IAM Role** Auth Method, attach the policy to the IAM role. See [Configuring Credentials for IAM Role].

Attach Permissions Policies to User


1. In the AWS Management Console, Services, navigate to Identity and Access Management (IAM) and click **Users**.




2. Find your user on the **Users** page and select it.
3. In the **Permissions** tab, click **Add permissions** > **Add permissions**.



4. Select **Attach policies directly**.




5. Select the following permissions: AmazonInspectorReadOnlyAccess and AmazonInspector2ReadOnlyAccess. (In the Search box, you can type inspector.)
6. Click **Next**.
7. Click **Add permissions**.
8. The Permissions policies are attached to the user.




Configuring Credentials for IAM Role

To configure the credentials for **IAM Role** (IAM Assume Role) Auth Method:


1. In the AWS Management Console, Services, navigate to Identity and Access Management (IAM) and click **Roles**.



2. Click **Create Role**.



3. Click **Custom trust policy**.



4. Using the example below as a guide, edit the JSON policy document.


> The following is just an EXAMPLE. You must modify this JSON to match the resources in your own environment.

AWS Inspector custom trust policy

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "Statement1",
            "Effect": "Allow",
            "Principal": {
                "AWS": "arn:aws:iam::001xxxxxx433:user/<username>"
            },
            "Action": "sts:AssumeRole"
        }
    ]
}
```


5. Click **Next**.

6. Select the following permissions: AmazonInspectorReadOnlyAccess and AmazonInspector2ReadOnlyAccess. (In the Search box, you can type inspector.)




7. Click **Next**.


8. Enter a **Role name**.



9. Click **Create role**.



10. Find your role name on the **Roles** page and select it.




11. Copy your ARN, which you will need when configuring the connector in Stellar Cyber.


Adding the Connector in Stellar Cyber

With the credential and log information available, you can now add the AWS Inspector connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Vulnerability Scanner** from the **Category** dropdown.
5. Choose **AWS Inspector** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.


12. Choose the **Auth Method** to use **Access Key / Secret Key** or **IAM Role**.

    For **Access Key / Secret Key** Auth Method:

    a. Enter the **Access Key** you noted above in Configuring Credentials for Access Key / Secret Key.

    b. Enter the **Secret Key** you noted above.

    For **IAM Role** Auth Method:




The asterisk (*) indicates a required field.

a. Enter the **Source Account Access Key** you noted above in Configuring Credentials for Access Key / Secret Key.

b. Enter the **Source Account Secret Key**.

c. Enter the **IAM Role ARN** that you noted above in Configuring Credentials for IAM Role.

13. Choose a **Region** from the available regions in the dropdown.
14. Choose the **Interval (min)**. This is how often the logs are collected.
15. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
16. Click **Next**. The final confirmation tab appears.



17. Click **Submit**.


The new connector is immediately active and starts collecting logs.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

> The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits,

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
			user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.