Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Amazon Security Lake Connectors

This connector allows Stellar Cyber to ingest logs from the Amazon Security Lake and add the records to the Stellar Cyber data lake.

Integration with Amazon Security Lake enables organizations to securely store and manage their security data, providing real-time threat detection and response capabilities through Stellar Cyber's advanced security analytics and machine learning algorithms.

This connector uses the standardized format for Open Cybersecurity Schema Framework (OCSF). It supports OCSF versions 1.0.0 and 1.1.0.

The data in OCSF format, which is sent and pulled by third party vendors, is stored in the Amazon Security Lake. This connector is a subscriber integration that pulls data from the lake.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Amazon Security Lake

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **N/A**

Collected Data

Content Type	Index	Locating Records
OCSF-formatted data from Amazon Security Lake	Syslog (default) Traffic (for vpcflow) AWS Events (for cloudtrail)	msg_class: `<metadata.product.feature.name>` Default msg_class:

Content Type	Index	Locating Records

		`amazon_security_lake_log`
		Examples:
		`management_data_and_insights` (for default)
		`vpcflow` (if `metadata.product.name` is Amazon VPC)
		`cloudtrail` (if `metadata.product.name` is CloudTrail)
		
		msg_origin.source:
		`<metadata.product.name>`
		Default msg_origin.source:
		`amazon_security_lake`
		Example:
		`cloudtrail` (if `metadata.product.name` is Amazon VPC)
		
		msg_origin.vendor:
		`<metadata.product.vendor_name>`
		Example:
		`aws`
		
		msg_origin.category:
		`websecurity` (for default)
		`paas` (for Amazon VPC or CloudTrail)
		
		msg_origin.processor.type:
		`log_collector`
		
		msg_origin.processor.name:
		`amazon_security_lake`
		
		This connector can have several different

Content Type	Index	Locating Records
		[redacted] `msg_class` and `msg_origin_source` values. The values are assigned dynamically based on the original data source.

Domain

N/A

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- AWS Role ID, External ID, and SQS Queue URL, plus Region

Adding an Amazon Security Lake Connector

To add an Amazon Security Lake connector:

1. Obtain Amazon Security Lake credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining Amazon Security Lake Credentials

This connector uses Amazon Simple Queue Service (SQS) queues and S3 buckets to pull data from the Amazon Security Lake.

Follow guidance on Amazon Security Lake documentation.

Permissions

You need the following permissions to create the SQS queue:

- s3:GetBucketNotification
- s3:PutBucketNotification
- sqs:CreateQueue
- sqs:DeleteQueue
- sqs:GetQueueAttributes
- sqs:GetQueueUrl
- sqs:SetQueueAttributes

When you set up data access for the Amazon Security Lake subscriber in the Enabling Subscriber Data Access procedure, the SQS queue is automatically created.

You will also need the following permissions to perform actions:


- iam:CreateRole
- iam:DeleteRolePolicy
- iam:GetRole
- iam:PutRolePolicy
- lakeformation:GrantPermissions
- lakeformation:ListPermissions
- lakeformation:RegisterResource
- lakeformation:RevokePermissions
- ram:GetResourceShareAssociations
- ram:GetResourceShares
- ram:UpdateResourceShare

Use IAM to verify your permissions. Review the IAM policies that are attached to your IAM identity. Then, compare the information in those policies to the list of (permissions) actions that you must have to notify subscribers when new data is written to the data lake.


Enabling Subscriber Data Access

To enable subscriber data access:

1. Log in as an administrative user to the Security Lake console at https://console.aws.amazon.com/securitylake.
2. Use the **AWS Region** dropdown to choose a **Region** in which to create the subscriber.
3. Choose **Subscribers**.




4. Click **Create subscriber**.




5. For **Subscriber details**, enter a **Subscriber name**. You can also enter an optional **Description**.

The **Region** is automatically populated as your currently selected AWS Region. It cannot be change


6. For **Log and event sources**, select **All log and event sources**.
7. For **Data access method**, choose **S3**.



8. For **Subscriber credentials**, enter **Account Id** and **External Id**.
    - The **Account Id** is the ID of the AWS account on which Stellar Cyber is running.
    - The **External Id** is a unique identifier. The suggested **External Id** is the Stellar Cyber tenant ID of the tenant running the connector. To find your tenant ID, navigate to **System | ORGANIZATION MANAGEMENT | Tenants** and locate it in the table.
9. For **Notification details**, choose **SQS queue**.
10. Click **Create**.
11. Navigate to **Subscribers | Details**. Copy the **AWS role ID** and the **Subscription endpoint**. You will need them when configuring the connector in Stellar Cyber.



12. Navigate to **Amazon SQS | Queues**.




13. For the specific **Subscription endpoint** noted above, copy the SQS queue **URL**. You will need it when configuring the connector in Stellar Cyber.

Adding the Connector in Stellar Cyber


With the access information handy, you can add an Amazon Security Lake connector in Stellar Cyber:

1. Log in to Stellar Cyber.

2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Web Security** from the **Category** dropdown.
5. Choose **Amazon Security Lake** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:


- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. This identifies which tenant is allowed to use the connector.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Enter the AWS **Role ID** you noted above in Obtain your Amazon Security Lake credentials.
13. Enter the **External ID** you noted above.
14. Choose the **Region** from the available AWS regions in the dropdown.
15. Enter the **SQS Queue URL** you noted above.
16. Click **Next**. The final confirmation tab appears.



17. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

> The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits,

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
			user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** depending on the type of data received:

   - For the default, change the **Indices** to **Syslog**.
   - For a `msg_class` of `vpcflow`, change the **Indices** to **Traffic**.
   - For a `msg_class` of `cloudtrail`, change the **Indices** to **AWS Events**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.