Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Aruba Central Connectors 6.1.0

This connector allows Stellar Cyber to ingest logs from Aruba Central and add the records to the data lake. It integrates with the Aruba Central API to query for Audit Logs and Monitoring Events.

There is a base API rate limit of 5,000 API calls per day for all accounts. The rate limit can be dynamically increased with Foundation or Advanced Licenses.

Due to a vendor API limitation, this connector can only retrieve the first 10,000 records per request.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Aruba Central

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Audit Logs
Monitoring Events
	Syslog	msg_class:
		`aruba_central_audit_log`
		`aruba_central_monitoring`
		
		msg_origin.source:

Content Type	Index	Locating Records
		`aruba_central` msg_origin.vendor: `hpe` msg_origin.category: `netmgmt`

Domain

<Base URL> or <Custom URL>

where <Base URL> or <Custom URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Base URL or Custom URL, Username, Password, Client ID, Client Secret, and Customer ID

Adding an Aruba Central Connector

To add an Aruba Central connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining Aruba Central Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Aruba Central credentials:

- Base URL—The base URL for API access, which you can select from the dropdown menu. Refer to the table in the Aruba Central documentation. This URL is determined by the geographical cluster in which you registered the account of HPE Aruba Networking Central.
- Custom URL—The custom URL, which you can enter in the **Custom URL** field if a URL is not available in the Base URL dropdown menu.
- Username and Password—The credentials used to authenticate a user on the Aruba Central Portal. Follow the guidance in the Aruba Central documentation.

- Client ID and Client Secret—The credentials used to authenticate with the Aruba Central API.
- Customer ID—The unique identifier for your Aruba Central account.

With the authentication mechanism for this connector, it is easy to be locked out. Be cautious of the following scenarios:

- Sharing credentials among Stellar Cyber connectors or with any third party.
- Attempting to authenticate with the wrong credentials consecutively.
- Clicking the **Test** button and then immediately enabling the collector. (The amount of time between successful logins (cooldown time) is 30 minutes for each successful login attempt.)
- Disabling and enabling the connector immediately.


Follow these procedures to:

- Add a new user to HPE GreenLake
- Log in with the new user to HPE GreenLake
- Obtain the Base URL, Client ID, Client Secret, and Customer ID


Adding a New User to HPE GreenLake

To add a new user:


1. Login to HPE GreenLake as an administrative user.
2. Select **User Management** from the Quick Links.




3. In the Users page, click **Invite users**.




4. In the Invite User page, enter the user's Email Address and select a Role.



5. Click **Send Invite**.
6. To grant access for the new user, select **Assign Role**.



7. Select a Service manager, a Role, and select Limit Resource Access. There are view only roles and operator roles.




8. Click **Assign Role**.


Logging in with the New User to HPE GreenLake

To log in with the new user:

1. The new user will receive an email, accept the invitation to activate the account, and then login to HPE GreenLake.



2. In Getting Started, the new user can then click **Launch** to start using Aruba Central.




3. Note the username and password of the new user. These credentials are used in the configuration of the Aruba Central connector.


Obtaining the Base URL, Client ID, Client Secret, and Customer ID

To obtain the base URL, client ID, client secret, and customer ID:


1. In the Aruba Central Portal, select **Organization**.



2. Select the **Platform Integration** tab and then select **REST API**.




3. Note the URL (the part before swagger) in the **APIs** tab. It will be used in the configuration of the Aruba Central connector. In this example, the base URL is https://apigw-uswest4.central.arubanetworks.com.




4. Select the Account Home icon at the top right of the user interface and click API Gateway, then select the **My Apps & Tokens** tab.



5. Click **Add Apps & Tokens**.
6. In the NEW TOKEN page, click **Generate**.



7. Note the Client ID and Client Secret. They will be used in the configuration of the Aruba Central connector.



8. Select the user icon at the top right of the user interface.




9. Note the Customer ID for that user. It will be used in the configuration of the Aruba Central connector.


Adding the Connector in Stellar Cyber

To add an Aruba Central connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Network Management** from the **Category** dropdown.
5. Choose **Aruba Central** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.


   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.




The asterisk (*) indicates a required field.

12. Select the **Base URL** from the dropdown menu.
13. Or, select **Custom URL** from the **Base URL** dropdown menu and enter a URL in the **Custom URL** field.



14. Enter the **Username** and **Password** you noted above in Obtaining Aruba Central Credentials.
15. Enter the **Client ID** and **Client Secret** you noted above.
16. Enter the **Customer ID** you noted above.
17. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
18. Choose the **Interval (min)**. This is how often the logs are collected.

19. Choose the **Content Type** you would like to collect. The logs for **Audit Logs** and **Monitoring Events** are supported.
20. Click **Next**. The final confirmation tab appears.



21. Click **Submit**.

The new connector is immediately active.


Testing the Connector

In addition to testing for connectivity, the **Test** button for the Aruba Central connector tests that the Base URL and authentication credentials are correct and data requests for the requested content types return successful responses.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the

connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.