Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Azure NSG Connectors 6.1.0

You can connect Stellar Cyber to the Azure Network Security Group (NSG) firewall so that you can quickly and easily implement firewall rules from within Stellar Cyber, while you are threat hunting. You can configure firewall actions or manually trigger a firewall action from the event display.

Connector Overview: Azure NSG

Capabilities

- Collect: **No**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **N/A**

Collected Data

N/A

Domain

<Auth URL> and <Base URL>

where <Auth URL> and <Base URL> are variables from the configuration of this connector

Response Actions

Action	Required Fields
Block IP/Unblock IP	`srcip` or `dstip`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Auth URL, Base URL, Tenant ID, Client ID, Client Secret, Subscription ID, Resource Group Name, and Network Security Group Name

Adding an Azure NSG Connector

To add an Azure NSG firewall connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector

Obtaining Azure NSG Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following Azure NSG firewall credentials:

- Auth URL—The authentication URL for API access. The default is https://login.microsoftonline.com.
- Base URL—The base URL for API access. The default is https://management.azure.com.
- Tenant ID—The tenant from which to request permission, also known as the Directory ID.
- Client ID—The client ID, also known as the Application ID that the app registration portal assigned when the app was registered.
- Client Secret—The password that you generated for your app in the app registration portal, also known as the API Access Key.
- Subscription ID—The credentials that uniquely identify the Microsoft Azure subscription.
- Resource Group Name—The name of the resource group that contains the network security group. The resource group must exist.
- Network Security Group Name—The name of the network security group. The NSG must exist in the resource group.

Prerequisites


Create a network security group under a resource group. Follow the guidance in the Microsoft documentation to:

- Create an Azure resource group
- Create an Azure network security group


Registering an Application

Follow the guidance in the Microsoft documentation to register an application.


1. With an administrative account, sign in to the Microsoft Entra admin center.
2. In the navigation pane, select **App registrations**. A pane for adding and managing **App registrations** is displayed.



3. Click **New registration**. A pane is opened for your new parameters.




4. Enter a display **Name** for your application.
5. Choose a supported account type. **Accounts in this organizational directory only** is typical.
6. The **Redirect URI** setting is not required.
7. Click **Register**. The initial app registration is completed and a summary of it is displayed.




8. Copy the following details to a file:
    - **Display Name**
    - **Application (client) ID**, which is the **Client ID** you will use to add the connector in Stellar Cyber
    - **Directory (tenant) ID**, which is the **Tenant ID** you will use to add the connector in Stellar Cyber


There is no need to grant API permissions for the app.

9. To add a client secret to the application, select **Certificates & secrets** and **New client secret**.



10. Add a Description and select an expiry.
11. Click **Add**. The client s et is displayed in the **Client secrets** list.




12. Copy the **Value**. This is the **Client Secret** you will use to add the connector in Stellar Cyber.


Assigning a Role to the NSG

To assign the Network Contributor role to the registered app in the Network Security Group:


1. Navigate to **Network security groups** and locate your existing NSG.




2. Click **Access control (IAM)**.
3. Click **Add** and select **Add role assignment**.
4. In the **Add role assignment** page, click the **Role** tab.




5. Enter Network and select Network Contributor.
6. Click **Next**.
7. In the **Members** tab, click **Select members**.




8. In the **Select members** page, select the previously registered app and click **Select**. It appears in the **Add role assignment** page.



9. Click **Review + assign**.
10. To verify, click **Access control (IAM)**.




11. Click **View**.
12. Click the **Role assignments** tab.
13. You can use the search box to locate the member and view the assigned role.



Locating the Subscription ID

To locate the Subscription ID:


1. Navigate to **Subscriptions**.
2. View the Subscription name and Subscription ID.




Adding the Connector in Stellar Cyber

To add a new Azure NSG firewall connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Firewall** from the **Category** dropdown.
5. Choose **Azure NSG (Network Security Group)** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.
7. Enter a **Name**.

Notes:


- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

11. Enter the **Auth URL** you noted above in Obtaining Azure NSG Credentials.
12. Enter the **Base URL** you noted above.
13. Enter the **Tenant ID** you noted above.
14. Enter the **Client ID** you noted above.
15. Enter the **Client Secret** you noted above.
16. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
17. Enter the **Subscription ID** you noted above.
18. Enter the **Resource Group Name** you noted above.
19. Enter the **Network Security Group Name** you noted above.
20. Select a **Region** from the drop-down.
21. Click **Next**. The final confirmation tab appears.



22. Click **Submit**.


The new firewall connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.

3. Click **Test** at the right side of that row. The test runs immediately.

Note that you ma[illegible]n only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota	The server or user license/quota will eventually recover. The connector will periodically retry the

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
		is exceeded.	query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

© 2026 Stellar Cyber . All rights reserved.