Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Cisco Firewall Management Center (FMC) Connectors 6.1.0

This connector allows you to Block an IP using an API call to the Cisco FMC (formerly Firepower Management Center) firewall you configure below.

Connector Overview: Cisco FMC

Capabilities

- Collect: **No**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP** or **Sensor** 6.1.0
- Interval: **N/A**

Collected Data

N/A

Domain

https://<Device IP Address>

where <Device IP Address> is a variable from the configuration of this connector

Response Actions

Action	Required Fields
Block IP	`srcip` or `dstip`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- User Name and Password for API access
- Device IP Address: This is the Cisco FMC IP address
- Source IP Group, Destination IP Group (are required for the API but can be empty)
- A Cisco FMC policy to block an IP address, a source IP group rule, and a destination IP group rule
- Cisco FMC must be enabled for API access


Adding a Cisco FMC Connector

To add a Cisco FMC connector:

1. Configure Cisco FMC and obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector

Configuring Cisco FMC and Obtaining Credentials


1. Follow guidance on the FMC website to enable API functionality for the firewall.
2. Make note of the host IP address for your Cisco FMC instance. This is used as the **Device IP Address** during configuration.



3. Create a user for use with the API:
    a. Log into the **Cisco FMC console** as an **administrative** user.

    Do not use an administrator user for your connector configuration.


    b. Display the **Settings** menu and select the option for **Users**.



    c. From the Users screen, click **Create User**.

    d. In the dialog that displays, configure a user for use with Stellar Cyber that has at least the **Network Admin** role.

    Do not create the user with administrative privileges.




e. Make note of the **User Name** and **Password** that you create.

The password should not include non-ASCII special characters.


f. Click **Save**.

4. Create a **Source IP Network Group** for use with Stellar Cyber.

a. Navigate to the **Objects** tab on the **Network** page. Click **Add Network** and select **Add Group** from the dropdown.




b. In the dialog that displays, enter a name for the group, to be associated with Stellar Cyber.



c. Select **Allow Overrides**.

It is not necessary to add networks to the group.

d. Click **Save**.




e. Click **Yes**.

5. Repeat the previous steps to create a **Destination IP Network Group**.


6. Configure a policy to block the IP address.

a. Navigate to **Policies | Access Control**.



b. Click **New Policy**.

c. In the dialog that displays, enter a name for the policy. Make sure **Block all traffic** is selected.




d. For the **Targeted Devices**, select a device from the **Available Devices** and click **Add to policy**.

e. Click **Save**.

7. Add a rule to block the source IP group.

a. Enter a rule name and select **Enabled**.



b. Select **Block** from the **Action** dropdown.


c. For the **Source Networks**, select the **Source IP Network Group** for use with Stellar Cyber from the **Available Networks** and click **Add to Source Networks**.

d. For the **Destination Networks**, select **any** from the **Available Networks** and click **Add to Destination**.

e. Click **Save**.

8. Add a rule to block the destination IP group.

a. Enter a rule name and select **Enabled**.




b. Select **Block** from the **Action** dropdown.

c. For the **Source Networks**, select **any** from the **Available Networks** and click **Add to Source Networks**.

d. For the **Destination Networks**, select the **Destination IP Network Group** for use with Stellar Cyber from the **Available Networks** and click **Add to Destination**.

e. Click **Save**.

f. You can view the policy and the rules as follows:




9. You should have the following information ready to configure your connector:

- User Name and Password
- Device IP Address
- Source IP Group
- Destination IP Group
- Cisco FMC must be enabled for API access


Adding the Connector in Stellar Cyber

With the access information handy, you can add a Cisco FMC connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Firewall** from the **Category** dropdown.

5. Choose **Cisco FMC** from the **Type** dropdown.




   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.
7. Enter a **Name**.


   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. This identifies which tenant is allowed to use the connector.
9. Choose the device on which to run the connector.
10. Click **Next**. The **Configuration** tab appears.



   The asterisk (*) indicates a required field.

11. Using the data you collected in the previous section, complete the following fields:
    - **User Name**
    - **Password**
    - **Device IP Address**
    - **Source IP Group**
    - **Destination IP Group**
12. Click **Next**. The final confirmation tab appears.



13. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

© 2026 Stellar Cyber . All rights reserved.