Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Cisco Meraki Firewall Connectors

6.3.0

You can connect Stellar Cyber to firewalls so that you can quickly and easily implement firewall rules on those firewalls from within Stellar Cyber, while you are threat hunting. You can configure firewall actions or manually trigger a firewall action from the event display. With a Cisco Meraki firewall connector configured, you can create a Stellar Cyber rule to automatically or manually block on that firewall.

Connector Overview: Cisco Meraki Firewall

Capabilities

- Collect: **No**
- Respond: **Yes**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **N/A**

Collected Data

N/A

Domain

https://api.meraki.com/api/v1

Response Actions

Action	Required Fields
Block IP	`srcip` or `dstip`

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Base URL, API Key, Organization Name, and Network or Template Name

Adding a Cisco Meraki Firewall Connector

To add a Cisco Meraki firewall connector:

1. Enable API access
2. Add the connector in Stellar Cyber
3. Test the connector

Enabling API Access


Other than having your firewall rules enabled, you will need to obtain the following three things from your Cisco Meraki account:

- Base URL
- API Key
- Organization Name
- Network Name


Obtaining Organization Name, Network Name, and API Key

To obtain the organization name, network name, and API key:

1. Access the Cisco Meraki Dashboard as a user with administrative privileges.
2. Select your **Organization** from the navigation menu on the left side of the dashboard. Then select **Organization>Settings**, below that.




3. When the right pane refreshes to display the **Settings**, make note of **Organization Name** located at the top of the pane.
4. Next, scroll down the page to **API Access** and ensure the corresponding checkbox is enabled.




5. From the top right of the page, click your user name and then select **My Profile**.

6. When your account details display, scroll to the **API Access** block and click, the button to **Generate a new API key**.



7. Make note of that key as you will not be able to view it later, then check the note box and click Done.




8. Now, use the navigation pane to display your organization's networks. You will need either the **Name** or **Template Name** of each network for which you want to create a connector:

    - If the network is NOT bound to any template, use the **Network Name** when you add the connector in Stellar Cyber.
    - If the network IS bound to a template, use the **Template Name** when you add the connector in Stellar Cyber.

    As described below, using the correct type of name for your configuration ensures that **Block IP** and **Revert** actions work correctly.

    If you want to use more than one network, you can create multiple connector instances with one for each network or template name.



After you obtain this information, you can proceed to configuring the connector in Stellar Cyber. Based on the examples above, you should now have:

- **API Key**: 5b2efd9fee131d2b9810caf5423f1c17a61751be
- **Organization Name**: Test Lab
- **Network Name**: Stellar-Meraki-MX64

Obtaining Base URL 6.3.0

The default Base URL is https://api.meraki.com/api/v1, which is for most regions, such as US and Europe.

For organizations hosted in other countries, enter the following:


- For Canada, https://api.meraki.ca/api/v1
- For China, use https://api.meraki.cn/api/v1
- For India, use https://api.meraki.in/api/v1
- For US Government, use https://api.gov-meraki.com/api/v1

Refer to the Cisco Meraki documentation for the Cisco Meraki Dashboard API or the Base URI.


Adding the Connector in Stellar Cyber

To add a new Meraki firewall connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Firewall** from the **Category** dropdown.
5. Choose **Cisco Meraki Firewall** from the **Type** dropdown.




   The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Respond**, which is enabled already.

7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. Click **Next**. The **Configuration** tab appears.



   The asterisk (*) indicates a required field.


11. Enter the **Base URL** for your region that you noted above in Enabling API Access.
12. Enter the **API Key** to access the firewall that you noted above in Enabling API Access.
13. Enter the **Organization Name** you noted above.
14. Enter the **Network Name** or **Template Name** you noted above.

    You can specify either a network name or a template name. Keep in mind that if the network is bound to a template, you **must use** the template name in order for the **Block IP** and **Revert** actions to work correctly. The **Test** button still works correctly if you use the network name for a network that is bound to a template, but the actions only work correctly if you use the template name. This is summarized in the table below.

Meraki Firewall Name Configuration	Added in Stellar Cyber Using...	Supported Operations
Network Name, no template	Network Name	**Test** button, **Block IP**, and **Revert** actions all work correctly.
Network Name, bound to template	Template Name	**Test** button, **Block IP**, and **Revert** actions all work correctly.
Network Name, bound	Network Name	**Test** button works but Block IP does not work correctly. Fails with error message similar to the following: `"{"errors":["Cannot override L3 firewall rules on a`

Meraki Firewall Name Configuration	Added in Stellar Cyber Using...	Supported Operations
to template		network bound to a template - the firewall rules are inherited from the template"]}."

15. Click **Next**. The final confirmation tab appears.



16. Click **Submit**.


The new firewall connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.



© 2026 Stellar Cyber . All rights reserved.