Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Cloudflare Connectors

This connector allows you to use the Cloudlfare Logpull API to ingest retained log files to the Stellar Cyber data lake.

Cloudflare connectors use the Logpull API. Logpull is only available to Cloudflare customers on the Enterprise plan. Make sure that you have the following:

- a Cloudflare account on an Enterprise plan
- an Enterprise subscription for the zone

For the available permissions for tokens and roles as they relate to logs, refer to Get started > Permissions.

This connector is improved to use less memory. Under certain scenarios if there is an error reaching the third-party API, some duplicate messages may be sent.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Cloudflare

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records
Logs (not configurable in the user interface)	Syslog	msg_class: `cloudflare_logpull_logs` msg_origin.source: `cloudflare_logpull` msg_origin.vendor: `cloudflare` msg_origin.category: `websec` `waf`

Domain

https://api.cloudflare.com

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Zone ID and API Token

Adding a Cloudflare Connector

To add a Cloudflare connector:

1. Obtain the required credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion


Obtaining the Required Credentials

To configure this connector in Stellar Cyber, you will need the following information from your Cloudflare deployment:

- **Zone ID**: Specify the Zone ID, Cloudflare's unique identifier for each domain in your account. You will be using this ID to configure the connector.
- **API Token**: You will need to create an API token for use by the Stellar Cyber connector.
- **Field list**: Review whether you want to collect the **Default** fields according to how the defaults are set in your Cloudflare deployment, or whether you want **All** fields that are applicable to the dataset you have associated with that Zone. (Refer to the Cloudflare documentation for a description of the log fields available per dataset.)

Note that the applicable logs are not retained by default. To support the retrieval of logs with the Logpull API, you must enable log retention. If enabling log retention does not work according to Cloudflare's documentation, you may need to modify the API call using the curl command below.

1. Log into the Cloudflare dashboard using a user with the **Administrator Read only** role.



2. Select the account and the domain for which you want to collect data. This step ensures you save the correct Zone ID.
3. From the **Overview** page, locate the section titled **API** and the field for **Zone ID**, then click the link **Click to copy**. For example:



4. Paste that value in a file to use when you configure the connector below.
5. Click the link for **Get your API Token**.
6. Follow Cloudflare's guidance to Create an API token. You can create an API from a template or you can create a custom token.

   Specify the following permissions: **Zone**, **desired dataset**, **Edit**. (See note below about **Edit** versus **Read** permissions).

   For example, below is a custom token, with the permissions for **Zone**, **Logs**, and **Edit** specified:



   The **Edit** permission is needed for the API token so that this connector can turn on log retention. If you can turn on log retention, only **Read** permission is needed for the API token.

   Use the following command to turn on log retention:

   ```
   curl -i -H "Authorization: Bearer <API TOKEN>" POST "https://api.cloudflare.com/client/v4/zones/<ZONE_ID>/logs/control/retention/flag" -d '{"flag":true}'
   ```


   where <API TOKEN> and <ZONE ID> are your API token and Zone ID.

7. Save the API token in the same file in which you saved the Zone ID, then proceed to the next section.


Adding the Connector in Stellar Cyber

With the Zone ID and API token handy, you can add the Cloudflare connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Web Security** from the **Category** dropdown.
5. Choose **Cloudflare** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:


- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Enter the **Zone ID** you noted above in Obtaining the Required Credentials.
13. Enter the **API Token** you noted above.
14. Choose the **Interval (min)**. This is how often the logs are collected.
15. Select the **Log Fields** you want to collect:
    - **All Fields**: all fields applicable to the dataset associated with the Zone
    - **Default Fields**: default fields set in your Cloudflare deployment
16. Click **Next**. The final confirmation tab appears.



17. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.

© 2026 Stellar Cyber . All rights reserved.