Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Okta SSO

You can configure Stellar Cyber to use Okta SSO for **Authentication** or **Authentication and Authorization**:


1. **Add Stellar Cyber as a New Application in Okta**
2. **Add Attributes for Assigned Users**
3. **Assign Okta Users to Authenticate**
4. **Activate Multifactor Authentication (MFA)**
5. **Configure SSO Authentication in Stellar Cyber**

Add Stellar Cyber as a New Application in Okta

To add Stellar Cyber as a new application in Okta:

1. Log in to Okta and select **Applications | Applications**.


   The **Applications** page appears.




2. Select **Create App Integration**.

   The **Create a new app integration** wizard appears.

3. On the **Sign-in method** page, select **SAML 2.0** and then select **Next**.



4. On the **General Settings** tab on the **Create SAML Integration** page, enter an **App name**, optionally upload a logo, and then select **Next**.



5. On the **SAML Settings** tab, enter the following values for the **Single sign on URL** and the **Audience URI (SP Entity ID)**.
    - A global SSO configuration for a SaaS deployment:
        - **Single sign on URL**: `https://your.stellar.cyber.address/saml/login/callback/org_id/<org-id>`
        - **Audience URI (SP Entity ID)**: `https://your.stellar.cyber.address`
    - A tenant-specific SSO configuration for a SaaS deployment:
        - **Single sign on URL**: `https://your.stellar.cyber.address/saml/login/callback/org_id/<org-id>/cust_id/<tenant-id>`
        - **Audience URI (SP Entity ID)**: `https://your.stellar.cyber.address`

    The **Single sign on URL** in the Okta UI is the URL to which Okta sends its SAML authentication response. Different identity providers use different names for this URL as shown in the following table:

Identity Provider	Term for the Assertion Consumer Service (ACS) URL
Active Directory Federation Services	Relying party SAML 2.0 SSO service URL
Microsoft Entra ID	Reply URL
Okta	Single sign on URL
OneLogin	Assertion Consumer (ACS) URL
Rippling	Assertion Consumer Service URL

6. If you are configuring SSO for the whole server, you can enter the following `Name/Value` pairs. You will use these as attributes later. This configuration does not apply to a [tenant-specific SSO] configuration.

CustomAttributeName	Source Attribute*	Values (setlater)	Global SSO	Tenant-specific SSO
stellar_scope	appuser.stellar_scope	root partner tenant	Required for **Authorization**	Not applicable
stellar_privi	appuser.stellar_privilege	super_admin	Required for **Authorization**	

vilege		platform_admin security_admin user	
stellar_tena	appuser.stellar_tenant	ID number for conf	(Optional) Specify an individual tenant ID, not name. The ID is available on the Tenants List page.

stellar_tenant_group	appuser.stellar_tenant_group	configured tenant group ID number for any configured tenant group	(Optional) Specify a tenant group ID, not name. This is typically available for use by MSSP users with the **Partner** role. The Tenant Group ID is displayed on the Tenant Groups page.




- Values in these fields are case sensitive and syntax matters. Use the exact indicated syntax and verify there aren't any typos.
- If you have created a custom privilege with spaces or dashes, use an underscore instead. **Example**: A custom privilege of **STML-Super Admin** must be entered as `STML_Super_Admin`.



7. Select **Next**.
8. Enter your feedback on the **Feedback** page and then select **Finish**.

   The new app is immediately created and activated.
9. On the **Sign On** tab of the application you just created, expand **More details**.
10. Copy the **Sign on URL** and download the signing certificate (X.509 certificate).

    These are the **Entry Point** and certificate that you will use to configure Stellar Cyber.



You must next add the same four attributes that you set for the application to the user profile that will be applied to those who use the application.

Add Attributes for Assigned Users

These attributes let you manage authorization for Stellar Cyber users (not applicable for per-tenant SSO).

To add attributes for users:

1. Select **Directory | Profile Editor**.


   The **Profile Editor** page appears with the **Users** tab active by default.
2. Select the profile for the application you created and then **Add Attribute**.

   The **Add Attribute** dialog box appears.
3. Leave the **Data type** as **string**, enter a **Display name** and one of the **Variable names** you previously created.

   The Display name will be shown ifn the UI instead of the variable name and can be whatever you decide to name it (for, example, "Scope" for the `stellar_scope` variable). On the other hand, the variable must be entered exactly as you defined it for the application. The following are the four variable names:


   - appuser.stellar_scope
   - appuser.stellar_privilege
   - appuser.stellar_tenant
   - appuser.stellar_tenant_group

4. Leave the other settings at their default values and select **Save and Add Another** until you've added all four.



5. After the last one, select **Save** .
6. **Save** the configuration.

   The new attributes appear at the bottom of the profile editor.



You must now assign the users whom Okta will authenticate to the application.

Assign Okta Users to Authenticate

Assign users to the application in Okta, and if you are configuring **Authentication** only, create a corresponding list of users to add to Stellar Cyber. Users are automatically added to Stellar Cyber when you configure SSO to perform both **Authentication and Authorization**.

Only users who already have accounts in the Okta system can be assigned to the application.

1. Select **Applications | Applications**, select the name of the application you created, and then select the **Assignments** tab.
2. In the **Assign** dropdown list, choose **Assign to People**.


   The assignment dialog box appears, listing user accounts in Okta.
3. Select **Assign** for a user that you want Okta to authenticate for access to Stellar Cyber.

   Okta displays the selected user's username and the Display names of the four variables you defined for the user profile that corresponds to this application.
4. Enter the scope, which can be **root**, **tenant**, or **partner**.
5. Enter the privilege, which can be **super_admin**, **platform_admin**, **security_admin**, or **user**.

   You can also enter a custom privilege you defined in Stellar Cyber, under **Admin | Role-Based Access Control**.
6. Enter the exact tenant ID as defined in Stellar Cyber.
7. Enter the exact tenant group ID as defined in Stellar Cyber.

If you set the scope as **root** and leave the tenant field empty, the root user will have access to all tenants.

8. When the scope is **partner**, enter the exact name or ID of a tenant group as defined in Stellar Cyber.
9. To assign other users to the application, **Save and Go Back**.
10. Repeat the assignment for all users whom you want Okta to authenticate when they access Stellar Cyber.
11. When finished, select **Done**.




If you are using two-factor authentication, you must enable a multi-factor authentication option. Otherwise, you can proceed to configuring SSO in Stellar Cyber.

Activate Multifactor Authentication (MFA)


You can optionally enable MFA for your users. The steps here allow you to specify which client you prefer for authentication. It uses the Google Authenticator app.

Configuration of multi-factor authentication in Okta is independent of whether you enable 2FA in Stellar Cyber. It is possible for you require your users to authenticate with MFA in Okta and again with 2FA in Stellar Cyber

1. Select **Security | Authenticators | Add authenticator**.
2. Select **Add** for **Google Authenticator**.



Okta automatically adds Google authenticator to the Catch-all Rule, which is applied by default to all applications. The rule requires any two factor types for users to authenticate themselves, such as a password and a code from Google Authenticator.



You can now configure SSO authentication in Stellar Cyber.

Configure SSO Authentication in Stellar Cyber

With all your details collected, you are now ready to configure SSO Authentication in Stellar Cyber. The steps below are generally applicable for use for global configuration or per-tenant configuration.

Prepare for Users

- **For Authentication Only SSO**: First, manually add all users on the Stellar Cyber Platform. After this manual entry, users can log in with SSO.
- **For Authentication & Authorization SSO**: Configure all users through the IdP.
- **For Local access (bypass) when SSO is enabled**: If Stellar Cyber loses connectivity with your IdP, users configured for SSO cannot log in. As a preventive bypass method, manually create a new user in the Stellar Cyber Platform with root scope and with a valid email address that has "`+admin`" appended to a valid user name, as follows: `<user>+admin@yourorganization.com` (`joe+admin@yourorganization.com`). The user you create must be able to receive a password reset email at `<user>@yourorganization.com`. This email alias is what Stellar Cyber uses to permit the bypass of an SSO for a local login. After you create this separate user account, the user can log in two ways:
    - An SSO user with `<user>@yourorganization.com`

      or
    - A local user at `https://your.stellar.cyber.address/login` using `<user>+admin@yourorganization.com`

If SSO is configured, it's recommended to keep an active administrative account in the Stellar Cyber user management.

Enable SSO

1. Log in to Stellar Cyber and select **System | ORGANIZATION MANAGEMENT | Settings**.
2. In the **Authentication Settings** section, select **SSO (SAML)** as the **Authentication Method**.
3. Select **Metadata URL** or **Manual Config**:

   If you select **Metadata URL**:

   - **Issuer URL**: If this setting is present, enter the Stellar Cyber URL.
   - **Metadata URL**: Paste the URL you copied from the IdP. The URL must begin with either `https://` or `http://`. Different vendors use different names for the Metadata URL:

Identity Provider	Term for Metadata URL
Active Directory Federation Services	Federation Metadata URL

Identity Provider	Term for Metadata URL
Microsoft Entra ID	App Federation Metadata URL
Okta	Metadata URL
OneLogin	Issuer URL
Rippling	Metadata URL

If you select **Manual Config**:

- **Issuer URL**: If this setting is present, enter the Stellar Cyber URL.
- **Entry Point**: Paste the entry point URL you copied from the IdP.

  You must include **http://** or **https://** before the URLs. Different vendors use different names:

Identity Provider	Term for Entry Point URL
Active Directory Federation Services	SAML Endpoint
Microsoft Entra ID	Login URL or SAML-P Sign-on Endpoint
Okta	Sign on URL
OneLogin	SAML 2.0 Endpoint (HTTP)
Rippling	SAML 2.0 Endpoint (HTTP)

- **IDP Certificate**: Upload the certificate file you downloaded from the IdP.

4. Select **Require Signed Response** only if the IdP requires it.

   Verify whether your IdP requires signed SAML responses. Some IdPs, such as Okta, require them by default. If so, then enable **Require Signed Response** here as well.

5. Select **Allow Clock Skew** to allow for system time differences between Stellar Cyber and your IdP. Authentication messages have an expiration. If the system times on Stellar Cyber and your IdP are not synchronized, the messages might expire before they even get to Stellar Cyber. The result is that users cannot log in, because they cannot authenticate.
6. Choose your IdP setting: **Authentication Only** or **Authentication and Authorization**. Note the following:

   - A Global selection of **Authentication and Authorization** applies to all users (root, partner, and tenant), so the option to change authentication method for a specific tenant is not applicable when the Global method is set to **Authentication and Authorization**. You cannot log in to Tenant SSO when Global SSO is set to **Authentication and Authorization**. If you want to use SSO but also allow local users and tenant override, you must set the Global authentication method either to **Local** or to use the IdP with **Authentication Only**.
   - Although you can customize SSO configuration on a per-tenant basis, the **Authorization** capability is only supported at the global level. Overrides

you make at the tenant level are for **Authentication** only, so the toggle for **Authentication and Authorization** is not offered in the tenant editor.

- The authentication method for partners is the same as that for root users. Any authentication overrides for tenant-level users in a tenant group have no effect on the authentication method for the partners who manage the group.

- Choose **Authentication Only** for Stellar Cyber to authenticate users from your IdP, but manage scope and privilege locally. If you choose this, you must create the user in Stellar Cyber before adding them to your IdP.
- Choose **Authentication and Authorization** for Stellar Cyber to authenticate users from your IdP, along with their scope and level of privilege. You must configure authorization on your IdP before enabling this, otherwise users cannot log in. If you choose this, you do not need to create the user in Stellar Cyber. Stellar Cyber creates the user and assigns scope and privilege based on the information passed from the IdP.

> When Global Settings is configured for **Authentication & Authorization**, the option to **Create** new users manually is hidden because new users must come from the IdP source.

7. Choose a **Two-Factor Authentication** option that matches your IdP configuration:
   - **Off**: If you choose this option, Stellar Cyber user accounts are not offered a 2FA option.
   - **Mandatory**: If you choose this option, all users for every tenant are required to use 2FA when logging in to Stellar Cyber.
   - **Optional**: If you choose this option:
     - The 2FA option can be customized for individual tenants under **System | ORGANIZATION MANAGEMENT | Tenants**.
     - Individual users can choose to enable 2FA under their **User Profile** in the Stellar Cyber UI.
     - You can enforce 2FA for specific users under **System | ORGANIZATION MANAGEMENT | Users** when adding or editing a user

> - The overall Global Settings for 2FA affect authentication for partners and tenant users. For example, if 2FA is **Mandatory**, all users must use 2FA.
> - Enabling 2FA here is independent of what you have configured on your SSO service. Enabling it here causes a separate 2FA prompt to be displayed upon logging in to Stellar Cyber.

- The 2FA page from Stellar Cyber refers to use of Google Authenticator, but other authenticator applications also work.

8. Review your settings and then **Submit** them.

© 2026 Stellar Cyber . All rights reserved.