Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring OneLogin SSO

From Stellar Cyber v5.4.0, do not use the default Stellar Cyber integration application in OneLogin. Instead follow the steps below to create a new application.

If you already use OneLogin to manage access to other products in your organization, you can also configure it as the Identity Provider (IdP) for users accessing the Stellar Cyber Platform. Integrating Stellar Cyber with OneLogin lets you extend centralized user access control to Stellar Cyber through Single-Sign On (SSO) and SAML (Security Assertion Markup Language).

For information about authentication and authorization through SSO, see **Integrating with an IdP**.

Adding Stellar Cyber as a New Application in OneLogin

The setup of OneLogin to act as the IdP for Stellar Cyber users involves the addition of Stellar Cyber user accounts, creation of a Stellar Cyber application, and then the assignment of the application to the users.

Add Stellar Cyber User Accounts to OneLogin

You can import a set of users in bulk in a CSV file or add them individually. The following instructions are for adding an individual user whom you want to OneLogin to authenticate when the user attempts to log in to Stellar Cyber.

1. Log in to the OneLogin UI as a OneLogin administrator.
2. Select **System | ORGANIZATION MANAGEMENT | Users | New User**.

   The **New User** configuration page appears.
3. Enter values for the **First name**, **Last name**, and **Email**, and then **Save User**.
4. When using a OneLogin SSO for both user authentication and authorization, select **More Actions | Change Password**, enter a default password, select **Force user to update**, and then **Update**.

   When users first log in with the default password, they will be prompted to change it.

5. Select **Save User** to save the user configuration.
6. Repeat to add additional users.

Create a New Stellar Cyber Application in OneLogin

To add Stellar Cyber as a new application in OneLogin:

1. Select **Administration | Applications | Applications | Add App**.


   The **Find Applications** page appears.

2. Search for SAML Test Connector (IdP) and choose it in the applications list.

   The **SAML Test Connector (IdP)** application appears.

3. Change the name of the application (for example, “Stellar Cyber SSO”), optionally set rectangular and square icons and add a description, and then **Save** the application to create a new one.

   Artwork for Stellar Cyber logos is available for download in the media kit.

   After you **Save** the application with a new name, more options appear in the left menu.

4. Select **Configuration** and enter the following SAML (Security Assertion Markup Language) settings:

   Audience: Also referred to as *EntityID*, this identifies the SP (Service Provider) for which SAML assertions are intended. For SSO (Single Sign-On) authentication of Stellar Cyber users, enter the IP address or FQDN of the Stellar Cyber Platform where users log in; that is, `https://your.stellar.cyber.address`. Note that it must be preceded by `https://`

   For example, if the Stellar Cyber UI login is at 10.1.1.20, enter `https://10.1.1.20`

   Recipient: This specifies the endpoint URL that processes SAML assertions. Enter the same Stellar Cyber IP address or FQDN as you did for **Audience**.

   For example, enter `https://10.1.1.20`

   ACS (Consumer) URL Validator: Also referred to as *ACS URL Pattern*, this validates the ACS (Assertion Consumer Service) URL to which OneLogin sends SAML responses and requires a regular expression pattern, using a backslash to escape the dots. The Stellar Cyber URL varies depending on whether it's for global SSO on the Stellar Cyber Platform or if it's for tenant SSO.

   Global SSO example:
   `https://10\.1\.1\.20/saml/login/callback/org_id/<org-id>`

Tenant
SSO example: `https://10\.1\.1\.20/saml/login/callback/org_id/<org-id>/cust_id\/<tenant-id>`

ACS (Consumer) URL: This defines the SP endpoint (Stellar Cyber) that receives and processes SAML assertions.


Examples

Global SSO example:
`https://10\.1\.1\.20/saml/login/callback/org_id/51408620`

Tenant
SSO example: `https://10\.1\.1\.20/saml/login/callback/org_id/51408620/cust_id/59125044`

The **ACS (Consumer) URL** in the OneLogin UI is the URL to which OneLogin sends its SAML authentication response. Different identity providers use different names for this URL as shown in the following table:

Identity Provider	Term for the Assertion Consumer Service (ACS) URL
Active Directory Federation Services	Relying party SAML 2.0 SSO service URL
Microsoft Entra ID	Reply URL
Okta	Single sign on URL
OneLogin	Assertion Consumer (ACS) URL
Rippling	Assertion Consumer Service URL



5. **Save** the configuration.
6. Select **Parameters**, leave the default setting **Configured by admin** selected, and select the **Add** (**+**) icon.
7. In the **New Field** dialog box that appears, enter the following attributes and then **Save** the configuration:

   Field name: `stellar_scope`

   Include in SAML assertion: (select)
8. After you save the configuration and the dialog box changes from “New Field” to “Edit Field stellar_scope”, leave the **Value** at its default setting of **- No default -** , and **Save** again.
9. Repeat the previous three steps to define the scope, role, and privilege for three other Stellar Cyber user types:

`stellar_privilege`

`stellar_tenant`


`stellar_tenant_group`

> The first two attributes (`stellar_cyber` and `stellar_privilege`) are required for all users. The last two (`stellar_tenant` and `stellar_tenant_group`) are only required for users in a multi-tenant deployment.

10. **Save** the parameters.
11. Select **SSO**, leave the other settings as they are, set **SAML Signature Algorithm** as **SHA-256**, and then **Save** the **SSO** settings.
12. Copy details to use in the Stellar Cyber SSO (SAML) configuration later.

    If you configure Stellar Cyber to use the OneLogin metadata URL, copy the **Issuer URL**.

    When manually configuring Stellar Cyber to work with OneLogin, you will need the **SAML 2.0 Endpoint (URL)** displayed here and the **X.509 certificate** that you can see by selecting **View Details** for **X.509 Certificate**. Copy and paste them in a text editor now or return here to copy and paste them into the Stellar Cyber SSO (SAML) manual configuration later.




Assign the Application to the User

Assign the Stellar Cyber application to a user and set the user's scope, role, and privileges.

1. Select **Administration | Users | Users** and then select one of the user accounts you previously added.
2. In the settings for this user, select **Applications**.
3. On the Applications tab, select the **Add** (**+**) icon.

   The Assign new login to <username> dialog box appears.
4. Choose the Stellar Cyber application you just created—for example, Stellar Cyber SSO—and then select **Continue**.
5. Select **Allow the user to sign in**, enter values for the attributes you previously defined—for example, **stellar_privilege** = **super_admin** and **stellar_scope** = **root**—and then **Save** your changes.



By default, a root admin has access to “All Tenants”. You don’t need to set “All Tenants” as a value in the **stellar_tenant** field. For a partner, enter a tenant group, which provides access to all tenants in the group. For a user, specify a single tenant.

For information about user scope and privilege, see **Integrating with an IdP**.

6. **Save User**.

Configure Authentication in Stellar Cyber

With all your details collected, you are now ready to configure SSO Authentication in Stellar Cyber. The steps below are generally applicable for use for global configuration or per-tenant configuration.

Prepare for Users

- **For Authentication Only SSO**: First, manually add all users on the Stellar Cyber Platform. After this manual entry, users can log in with SSO. Use the list of User Principal Names that you saved.
- **For Authentication & Authorization SSO**: Configure all users through the IdP.
- **For Local access (bypass) when SSO is enabled**: If Stellar Cyber loses connectivity with your IdP, users configured for SSO cannot log in. As a preventive bypass method, manually create a new user in the Stellar Cyber Platform with root scope and with a valid email address that has "`+admin`" appended to a valid user name, as follows: `<user>+admin@yourorganization.com` (`joe+admin@yourorganization.com`). The user you create must be able to receive a password reset email at `<user>@yourorganization.com`. This email alias is what Stellar Cyber uses to permit the bypass of an SSO for a local login. After you create this separate user account, the user can log in two ways:
    - An SSO user with `<user>@yourorganization.com`

      or
    - A local user at `https://your.stellar.cyber.address/login` using `<user>+admin@yourorganization.com`

If SSO is configured, it's recommended to keep an active administrative account in the Stellar Cyber user management.

Set up SSO

1. Log in to Stellar Cyber and select **System | ORGANIZATION MANAGEMENT | Settings**.

2. In the **Authentication Settings** section, select **SSO (SAML)** as the **Authentication Method**.
3. Select **Metadata URL** or **Manual Config**:

   If you select **Metadata URL**:

   - **Issuer URL**: If this setting is present, enter the Stellar Cyber URL.
   - **Metadata URL**: Paste the URL you copied from the IdP. The URL must begin with either `https://` or `http://`. Different vendors use different names for the Metadata URL:

Identity Provider	Term for Metadata URL
Active Directory Federation Services	Federation Metadata URL
Microsoft Entra ID	App Federation Metadata URL
Okta	Metadata URL
OneLogin	Issuer URL
Rippling	Metadata URL

   If you select **Manual Config**:

   - **Issuer URL**: If this setting is present, enter the Stellar Cyber URL.
   - **Entry Point**: Paste the entry point URL you copied from the IdP.

     You must include **http://** or **https://** before the URLs. Different vendors use different names:

Identity Provider	Term for Entry Point URL
Active Directory Federation Services	SAML Endpoint
Microsoft Entra ID	Login URL or SAML-P Sign-on Endpoint
Okta	Sign on URL
OneLogin	SAML 2.0 Endpoint (HTTP)
Rippling	SAML 2.0 Endpoint (HTTP)

   - **IDP Certificate**: Upload the certificate file you downloaded from the IdP.
4. Select **Require Signed Response** only if the IdP requires it.

   Verify whether your IdP requires signed SAML responses. Some IdPs, such as Okta, require them by default. If so, then enable **Require Signed Response** here as well.
5. Select **Allow Clock Skew** to allow for system time differences between Stellar Cyber and your IdP. Authentication messages have an expiration. If the system times on Stellar Cyber and your IdP are not synchronized, the messages might expire before they even get to Stellar Cyber. The result is that users cannot log in, because they cannot authenticate.
6. Choose your IdP setting: **Authentication Only** or **Authentication and Authorization**. Note the following:

- A Global selection of **Authentication and Authorization** applies to all users (r partner, and tenant), so the option to change authentication method for a specific tenant is not applicable when the Global method is set to **Authentication and Authorization**. You cannot log in to Tenant SSO when Global SSO is set to **Authentication and Authorization**. If you want to use SSO but also allow local users and tenant override, you must set the Global authentication method either to **Local** or to use the IdP with **Authentication Only**.
- Although you can customize SSO configuration on a per-tenant basis, the **Authorization** capability is only supported at the global level. Overrides you make at the tenant level are for **Authentication** only, so the toggle for **Authentication and Authorization** is not offered in the tenant editor.
- The authentication method for partners is the same as that for root users. Any authentication overrides for tenant-level users in a tenant group have no effect on the authentication method for the partners who manage the group.

- Choose **Authentication Only** for Stellar Cyber to authenticate users from your IdP, but manage scope and privilege locally. If you choose this, you must create the user in Stellar Cyber before adding them to your IdP.
- Choose **Authentication and Authorization** for Stellar Cyber to authenticate users from your IdP, along with their scope and level of privilege. You must configure authorization on your IdP before enabling this, otherwise users cannot log in. If you choose this, you do not need to create the user in Stellar Cyber. Stellar Cyber creates the user and assigns scope and privilege based on the information passed from the IdP.

  When Global Settings is configured for **Authentication & Authorization**, the option to **Create** new users manually is hidden because new users must come from the IdP source.

7. Choose a **Two-Factor Authentication** option that matches your IdP configuration:
   - **Off**: If you choose this option, Stellar Cyber user accounts are not offered a 2FA option.
   - **Mandatory**: If you choose this option, all users for every tenant are required to use 2FA when logging in to Stellar Cyber.
   - **Optional**: If you choose this option:
     - The 2FA option can be customized for individual tenants under **System | ORGANIZATION MANAGEMENT | Tenants**.
     - Individual users can choose to enable 2FA under their **User Profile** in the Stellar Cyber UI.
     - You can enforce 2FA for specific users under **System | ORGANIZATION MANAGEMENT | Users** when adding or editing a

user

- The overall Global Settings for 2FA affect authentication for partners and tenant users. For example, if 2FA is **Mandatory**, all users must use 2FA.
- Enabling 2FA here is independent of what you have configured on your SSO service. Enabling it here causes a separate 2FA prompt to be displayed upon logging in to Stellar Cyber.
- The 2FA page from Stellar Cyber refers to use of Google Authenticator, but other authenticator applications also work.

8. Review your settings and then **Submit** them.

© 2026 Stellar Cyber . All rights reserved.