Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Rippling SSO


You can configure Stellar Cyber to use Rippling single sign-on (SSO) for user authentication. In Security Assertion Markup Language (SAML) terminology, Stellar Cyber then becomes the Service Provider (SP) and Rippling becomes the Identity Provider (IdP) for Stellar Cyber admin user authentication.

Adding Stellar Cyber as a New Application in Rippling

Add Stellar Cyber as a new application in Rippling.

Create Custom Fields and Edit Users

1. Log in to Rippling as a user with super admin or full admin permissions, or as an administrator with permission to manage a Rippling or third-party application.
2. Select **Settings | Data Manager | Employee | Employee Information** and then select the **New custom field** icon (**+**) at the top of the **Field** panel.



3. Select **Start from scratch** and create the following custom fields as explained in Collect a custom field from new hires when they onboard to Rippling.

You must be logged in to a Rippling account to view the knowledge base article.

Custom Field Name	Default Value	Values	Required

`stellar_scope`	root	`root`
		`partner`
		`tenant`
			Yes

Custom Field Name	Default Value	Values	Required

`stellar_privilege`	Platform Admin	`super_admin`
		`platform_admin`
		`security_admin`
		`user`
			Yes


`stellar_tenant`	(none)	(can be empty)	Yes
`stellar_tenant_group`	(none)	(can be empty)	Yes

4. Select the **People** icon in the left navigation panel to access the list of employees and select the name of a user account for someone who will be a Stellar Cyber administrative user.

   This opens the user's account settings.

5. Select **Custom Fields | Edit** and add the custom fields you just created, choosing the appropriate scope and privilege level for the user.

6. Select **Role Information | Edit**, and set **Will get access to work email** as **Yes**.




7. **Save** your edits.

8. Repeat the previous steps for all users who need to log in to Stellar Cyber.

Create a Custom Application for Stellar Cyber

1. Select **IT Management** (icon) **| Custom App | Create new Custom app**.




2. On the **Create new app** page, enter the following and then select **Continue**:

   Name: Enter a name such as **StellarDPApp**.

   Select Categories: **Security**

   Upload Logo: (Select an image of the Stellar Cyber logo, which you can download from the Stellar Cyber Media Kit.)

   What type of app would you like to create?: **Single Sign-on (SAML)**



3. On **Select Installer**, select **I'm the** `<application_name>` **admin, I'll install it** and then select **Continue**.

Set up SSO for Stellar Cyber through Rippling

1. On the **Create new app** page, copy or download the following and then select **Continue**:

   Single Sign-on URL or Target URL: Copy this for later use as the **Entry Point** if you manually configure SSO in Stellar Cyber.

   Issuer or IdP Entity ID: Enter the Stellar Cyber URL.

   X509 Certificate: Download this so you can later upload it to Stellar Cyber if you manually configure SSO there.

   IdP Metadata URL: Copy this for later if you use **Metadata URL** when configuring SSO in Stellar Cyber.

2. Enter the following URL so that Rippling can submit SAML assertions (SAML messages) to Stellar Cyber.

   Assertion Consumer Service URL: (Note that the URL varies depending on whether it's for global SSO on Stellar Cyber or per-tenant SSO.)

   Global SSO:
   `https://your.stellar.cyber.address/saml/login/callback/org_id/<org-id>`

   Tenant
   SSO: `https://your.stellar.cyber.address/saml/login/callback/org_id/<org-id>/cust_id/<tenant-id>`

   The **Assertion Consumer Service URL** in the Rippling UI is the URL to which Rippling sends its SAML authentication response. Different identity providers use different names for this URL as shown in the following table:


Identity Provider	Term for the Assertion Consumer Service (ACS) URL
Active Directory Federation Services	Relying party SAML 2.0 SSO service URL
Microsoft Entra ID	Reply URL
Okta	Single sign on URL
OneLogin	Assertion Consumer (ACS) URL
Rippling	Assertion Consumer Service URL

3. Enter the following URL so that Rippling can uniquely identify Stellar Cyber account.

   Service Provider Entity ID: `https://your.stellar.cyber.address`

4. Select **Move to Next Step**.
5. On **SSO App Access** **es**, set up a rule to determine who will get SSO access—for example, **Set up rules for which new hires or transitions should have an account**—and then select **Create custom policy**.
6. Under “Which departments should get access to `<application_name>`?”, select **Only departments I specify**, choose one or more departments, and then select **Save changes**.
7. On **SSO Provision Time**, define when to start applying the SSO app access rules by selecting **As soon as they’ve signed their offer letter or agreement** and then **Continue**.
8. On **SSO for admin**, let anyone with a full admin account in Rippling sign in to the `<application_name>` admin account by selecting **Let Stellar Cyber, Inc. admins sign in to** `<application_name>` **admin account** and then selecting **Continue**.

   The next step in the SSO setup is **Verify SSO Integration**. However, before doing this, you must first configure SSO authentication with Rippling in Stellar Cyber. Either keep Rippling open to the **Verify SSO Integration** page or log back in and return to it after setting up SSO with Rippling on Stellar Cyber.



Configuring SSO Authentication in Stellar Cyber

With all your details collected, you are now ready to configure SSO Authentication in Stellar Cyber. The steps below are generally applicable for a global or per-tenant configuration.

Prepare for Users

- **For Authentication Only SSO**: First, manually add all users on the Stellar Cyber Platform. After this manual entry, users can log in with SSO. Use the list of User Principal Names that you saved.
- **For Authentication & Authorization SSO**: Configure all users through the IdP.
- **For Local access (bypass) when SSO is enabled**: If Stellar Cyber loses connectivity with your IdP, users configured for SSO cannot log in. As a preventive bypass method, manually create a new user in the Stellar Cyber Platform with root scope and with a valid email address that has "`+admin`" appended to a valid user name, as follows: `<user>+admin@yourorganization.com` (`joe+admin@yourorganization.com`). The user you create must be able to receive a password reset email at `<user>@yourorganization.com`. This email alias is what Stellar Cyber uses to permit the bypass of an SSO for a local login. After you create this separate user account, the user can log in two ways:

- An SSO user with `<user>@yourorganization.com`

  or

- A local user at `https://your.stellar.cyber.address/login` using `<user>+admin@yourorganization.com`

If SSO is configured, it's recommended to keep an active administrative account in the Stellar Cyber user management.

Enable SSO

1. Log in to Stellar Cyber and select **System | ORGANIZATION MANAGEMENT | Settings**.
2. In the **Authentication Settings** section, select **SSO (SAML)** as the **Authentication Method**.
3. Select **Metadata URL** or **Manual Config**:

   If you select **Metadata URL**:

   - **Issuer URL**: If this setting is present, enter the Stellar Cyber URL.
   - **Metadata URL**: Paste the URL you copied from the IdP. The URL must begin with either `https://` or `http://`. Different vendors use different names for the Metadata URL:

Identity Provider	Term for Metadata URL
Active Directory Federation Services	Federation Metadata URL
Microsoft Entra ID	App Federation Metadata URL
Okta	Metadata URL
OneLogin	Issuer URL
Rippling	Metadata URL

   If you select **Manual Config**:

   - **Issuer URL**: If this setting is present, enter the Stellar Cyber URL.
   - **Entry Point**: Paste the entry point URL you copied from the IdP.

     You must include **http://** or **https://** before the URLs. Different vendors use different names:

Identity Provider	Term for Entry Point URL
Active Directory Federation Services	SAML Endpoint
Microsoft Entra ID	Login URL or SAML-P Sign-on Endpoint
Okta	Sign on URL
OneLogin	SAML 2.0 Endpoint (HTTP)
Rippling	SAML 2.0 Endpoint (HTTP)

   - **IDP Certificate**: Upload the certificate file you downloaded from the IdP.
4. Select **Require Signed Response** only if the IdP requires it.

Verify whether your IdP requires signed SAML responses. Some IdPs, such as Okta, require them by default. If so, then enable **Require Signed Response** here as well.

5. Select **Allow Clock Skew** to allow for system time differences between Stellar Cyber and your IdP. Authentication messages have an expiration. If the system times on Stellar Cyber and your IdP are not synchronized, the messages might expire before they even get to Stellar Cyber. The result is that users cannot log in, because they cannot authenticate.
6. Choose your IdP setting: **Authentication Only** or **Authentication and Authorization**. Note the following:

   - A Global selection of **Authentication and Authorization** applies to all users (root, partner, and tenant), so the option to change authentication method for a specific tenant is not applicable when the Global method is set to **Authentication and Authorization**. You cannot log in to Tenant SSO when Global SSO is set to **Authentication and Authorization**. If you want to use SSO but also allow local users and tenant override, you must set the Global authentication method either to **Local** or to use the IdP with **Authentication Only**.
   - Although you can customize SSO configuration on a per-tenant basis, the **Authorization** capability is only supported at the global level. Overrides you make at the tenant level are for **Authentication** only, so the toggle for **Authentication and Authorization** is not offered in the tenant editor.
   - The authentication method for partners is the same as that for root users. Any authentication overrides for tenant-level users in a tenant group have no effect on the authentication method for the partners who manage the group.

   - Choose **Authentication Only** for Stellar Cyber to authenticate users from your IdP, but manage scope and privilege locally. If you choose this, you must create the user in Stellar Cyber before adding them to your IdP.
   - Choose **Authentication and Authorization** for Stellar Cyber to authenticate users from your IdP, along with their scope and level of privilege. You must configure authorization on your IdP before enabling this, otherwise users cannot log in. If you choose this, you do not need to create the user in Stellar Cyber. Stellar Cyber creates the user and assigns scope and privilege based on the information passed from the IdP.

     When Global Settings is configured for **Authentication & Authorization**, the option to **Create** new users manually is hidden because new users must come from the IdP source.

7. Choose a **Two-Factor Authentication** option that matches your IdP configuration:

- **Off**: If you choose this option, Stellar Cyber user accounts are not offered a 2FA option.
- **Mandatory**: If you choose this option, all users for every tenant are required to use 2FA when logging in to Stellar Cyber.
- **Optional**: If you choose this option:
    - The 2FA option can be customized for individual tenants under **System | ORGANIZATION MANAGEMENT | Tenants**.
    - Individual users can choose to enable 2FA under their **User Profile** in the Stellar Cyber UI.
    - You can enforce 2FA for specific users under **System | ORGANIZATION MANAGEMENT | Users** when adding or editing a user




- The overall Global Settings for 2FA affect authentication for partners and tenant users. For example, if 2FA is **Mandatory**, all users must use 2FA.
- Enabling 2FA here is independent of what you have configured on your SSO service. Enabling it here causes a separate 2FA prompt to be displayed upon logging in to Stellar Cyber.
- The 2FA page from Stellar Cyber refers to use of Google Authenticator, but other authenticator applications also work.

8. Review your settings and then **Submit** them.


Testing SSO Integration

To test the setup with your email address, return to the Verify SSO Integration in Rippling and do the following:

1. On the **Verify SSO Integration** page, select **+ Connect via Rippling** and confirm that you were able to connect.



2. Select **IT Management** | **Custom App** | **Manage Custom Apps** and check that the Status for your Stellar Cyber application is **Active**.



3. Select **HR Management** | **People**, open one of the users, and select **Role Information** for this user.
4. Make sure that **Will get access to work email** is **Yes** for this user and for all users who must use Rippling SSO to log in to Stellar Cyber.
5. Select **Custom fields** and check that **stellar_privilege** is **Platform Admin** and **stellar_scope** is **root** (or one of the other values set in the custom fields) for this user and all users who must use Rippling SSO to log in to Stellar Cyber.
6. For users who need administrative access to Stellar Cyber, select **IT Management | Identity Management |** Custom App **| Manage Custom Apps | Visit App |** (for <application-name>) **| Overview**, and in the Employee Access table, select **Grant Access**.

© 2026 Stellar Cyber . All rights reserved.