Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Role-Based Access Control

Learn more at Stellar Cyber Academy.

The following link takes you to a course on the Stellar Cyber Academy technical training portal where you can learn more about this topic by watching the suggested lessons.

M02 Administration Essentials for Tenants, Users, and System (03h:46m)

User Management with Role-Based Action Control (20m:00s)

Discover how to manage user privileges using role-based access control (RBAC) within the Stellar Cyber Platform. Follow a demonstration on configuring privilege profiles — including Super Admin, Platform Admin, and Security Admin — and learn how to assign roles and scopes to control access levels across tenants. Explore how RBAC configurations help meet organizational security needs while ensuring compliance with access control policies.

The first time you access a link on the portal during a session, you must log in to access content.

You can use role-based access control (RBAC) to manage access to Stellar Cyber by assigning *scopes* and *privileges* to users. Use scope to manage access to tenants. Use privilege to manage access to functions. You assign scope and privilege when adding or editing users.

Use the options in the **System | ORGANIZATION MANAGEMENT | Role-Based Access Control** page to perform the following tasks:

- Create or edit privilege profiles
- Delete privilege profiles
- Use Your IdP to Manage RBAC


Creating or Editing a Profile

Scopes are managed and maintained by Stellar Cyber; you cannot create or change scopes.

Privileges are managed through profiles, which you can create and change. Stellar Cyber provides four default privilege profile templates (which are marked **Default** in the **View Other**

Profiles | Select a Profile Type panel):

- **Super Admin** – Provides full access to the system.
- **Platform Admin** – Provides full access, except for RBAC and selected system settings (external storage and standby management, for example).
- **Security Admin** – Lets you view, edit, and add sensors, recipients, connectors, reports, dashboards, queries, and others but not delete them. View-only access to most system pages.
- **User** – Provides view-only access to most system options, including queries.



You can click any of the listed profile types to see its associated privileges. Privileges listed with a ✓ in the display are enabled as part of the corresponding profile while those with an x are disabled. Privileges are nested under the top-level entries in the **Profile Configuration** page according to their relative position within the main areas of product functionality.

You can use these default profiles as-is and assign them to users, or you can create new, custom profiles based on these templates. You cannot edit the default profiles.

Whether you create a new profile or edit an existing one, you have the same options for defining privileges.

User Management and RBAC

In general, you can only delete users with a lower-level permission than your own account. This means:

- Super Admin users can delete users with any permissions except the default Super Admin account and their own account.
- Platform Admin users can delete Security Admin users and regular Users.

The exception to this rule is Security Admin users. Security Admin users only have View permissions for users by default. They do not have add, edit, or delete user privileges.

Creating a New Profile

When you create new profiles, they show up in the **Select a Profile Type** panel with the four default templates (and any other custom profiles). However, they do not have the **Default** indicator. There is no limit to the number of new profiles you can create.

To create a profile:

1. Select **System | ORGANIZATION MANAGEMENT | Role-Based Access Control**, and then select **View Other Profiles**.


   The **Select a Profile Type** panel appears.

2. Select a profile.

You can select any profile—one of the defaults or a previously created custom profile. The selected profile th appears.

3. Select **Create New Profile from this Template**.

   The **Create a Profile** screen appears.



4. Enter the name of the new profile.
5. Select one of the **Behavior for new features in future releases** options.

   These options define how this profile manages the privileges for features added to Stellar Cyber in the future. The options are:

   - **Inherit from Template** – When new Stellar Cyber features are released, the privilege profile templates are updated to include privileges for the new features. Choose **Inherit from Template** if you want your custom template to inherit those updated privileges as-is.

     A custom profile always inherits from one of the 4 default templates. If you create a new profile from an existing custom profile, the new one inherits from the same template as the existing one.

   - **Read Only** – Choose **Read Only** if you want your custom template to add new features with read-only access privileges.
   - **None** – Choose **None** if you want your custom template to add new features without allowing access to them.

6. Select **Save**.

   The new profile appears with the new name you defined and editable privileges.

7. Define privileges.
8. **Save Changes**.

   Your changes take effect immediately, but you remain in the new profile to make more changes.

You can now assign this profile to users on the **System | ORGANIZATION MANAGEMENT | Users** page. It appears as an option in the **User Privilege** drop-down list.

For very conservative RBAC, create a new profile and choose **No Access** and assign that profile to your users. While you can use a default profile template, that template will inherit a level of access to the new features. By creating a new profile and choosing **No Access**, you can review the new features and determine which access privileges, if any, to give users.

Editing a Profile

You can edit a profile at any time. To edit a profile:

1. Select **System | ORG ZATION MANAGEMENT | Role-Based Access Control** and then select **View Other Profiles**.

   The **Select a Profile Type** panel appears.

2. Select a custom profile (you cannot edit the four default profile templates).

   The selected profile appears.

3. Define privileges.

4. **Save Changes**.


   Your changes take effect immediately, but you remain in the new profile to make more changes.

Defining Privileges

You can define access privileges globally and at the feature group, feature, and function levels. To define privileges, simply toggle privileges on or off.

If you see ✓and ✓ instead of toggles, you are looking at one of the four default templates, which you cannot edit. Create or view another profile.

Select **Reset**, at the bottom of the page, to reset all privileges to the last save.



Feature Group-Level Privileges

You can enable or disable an entire group of features. If you disable this, pages for features in this group do not appear in Stellar Cyber for users with this user profile.

When you disable a feature group, all features and features in this group are also disabled.

To quickly enable all privileges for a group, toggle the group to disabled and then back to enabled. When you toggle it to enabled, all privileges underneath are also enabled.

For example, if you disable **Help**, the **"?"** icon doesn't appear in the menu bar. If you disable **Knowledge Base** or **Release Notes**, the Knowledge Base or Release Notes drop-down menus don't appear.

Feature-Level Privileges

You can enable or disable individual features. If you disable a feature, the link to the page for it does not appear in the menu for users with this user profile. For example, you can disable **Alerts**, which turns off the **Detections | Alerts** page.

The **Root Only** note indicates that a feature is only available for users with the **Root** scope, in addition to this privilege. Users must have both **Root** scope and this privilege.

To quickly enable all privileges under a page, toggle the page to disabled and back. When you toggle it to enabled, all leges underneath are also enabled.

Function-Level Privileges


You can enable or disable functions under a feature. If you disable a function, that function appears but is disactivated in the Stellar Cyber UI for users with this user profile.

For example, if you disable **Delete Alert Types**, the option to delete alert types appears on the Alerts page but is grayed out.

To grant view-only privileges, disable all functions under a page, but leave the page enabled. The user can view the page (because it is enabled), but cannot perform any functions.

Privileges Example

For this example let's look at some of the privileges for the **System | Administration** menu.



At the top, the **Administration** group of features is enabled for this profile. Users with this profile assigned will see the features in this group in the Stellar Cyber UI.

Under that grouping, features for **Licensing** and **User Management** are enabled. Users will see links to pages for these features in the navigation menu.

The **Licensing** feature also requires **Root** scope. Users will only see this feature if they have **Root** scope as well as this profile.

Deleting a Privilege Profile

To delete a privilege profile:

1. Select **System | ORGANIZATION MANAGEMENT | Role-Based Access Control** and then select **View Other Profiles**.

   The **Select a Profile Type**panel appears.

2. Select a custom profile (you cannot delete the four default profile templates).

   The profile appears.

3. Select **Delete**.

   The profile is immediately deleted.

You cannot delete a profile if it's assigned to users. To quickly see the users a profile is assigned to and change it:

1. Select **System | ORGANIZATION MANAGEMENT | Users**.

2. Select the **Privilege** column to sort the table on privilege and then look for users with the privilege profile.
3. Select to edit the user.
4. Assign a different privilege profile in the **User Privilege** drop-down list.
5. **Submit**.

Using Your IdP to Manage RBAC

If you use an IdP to provide SSO to Stellar Cyber, you can also use the IdP to manage RBAC:

1. Configure authorization on your IdP.
2. Configure SSO as the **Authentication Method** on the **System | ORGANIZATION MANAGEMENT | Settings** page, if you haven't done so already.
3. Choose **Authentication and Authorization** in the **Use IDP for** setting in the SSO configuration.
4. **Submit**.

© 2026 Stellar Cyber . All rights reserved.