Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring a Central Windows Log Collector

You can configure a single Windows computer to collect logs from source computers and forward them to the sensor. The collector and source computers must be able to communicate, and must be on the same Active Directory domain.

To configure a central windows computer to collect logs from source computers and forward them to a sensor, you will:

- Configure a central Windows computer (collector) to collect logs.
- Configure the source Windows computers to forward their logs to the collector.
- Configure the sensor in Stellar Cyber.

Our examples use Windows 10. Other versions of Windows might have different field names or locations.

Configuring the Collector to Collect Logs

You must configure the collector to:

- start the event collector service
- subscribe to the events

Starting the Collector Service


To start the collector service:

1. Log in to the collector.
2. Run a terminal session as an administrator.
3. Run the `wecutil quick-config` command.
4. Enter `Y` to proceed. The Windows Event Collector service begins.
5. Enter `exit` to end the terminal session.


Subscribing to Events

To subscribe to events:

1. Log in to the collector.
2. Open the **Computer M[redacted]gement** app.
3. Open **System Tools** | **Event Viewer**.
4. Right-click on **Subscriptions**.
5. Click on **Select Subscriptions...**. The **Subscription Properties** screen appears.



6. Enter a **Subscription name**.
7. Enter a **Description**.
8. Click **Select Computers**. The **Computers** dialog box appears.
9. Choose the source computers you want to receive logs from. Click **Test** to test the connection if you want.
10. Click **OK**.
11. Click **Select Events...**. The **Query Filter** screen appears.
12. Select the events you want to receive. Note the names of the events you selected, as you'll need to configure the source computers to send those events.
13. Click the **Event** logs dropdown.
14. Select **Windows Logs**.
15. Open **Applications and Service Logs** | **Microsoft**.
16. Select **Windows**.



17. Click outside of the dropdown to close it.
18. Click **OK**.
19. Click **OK**. You should now see events in the **Event Viewer**.

Configuring Source Forwarding Computers

You can configure multiple Windows computers to send logs to the collector. You must configure the source forwarding computers to:

- enable remote management

- set the collector as the destination for the logs
- send logs to the collec

Enabling Remote Management


To configure a source forwarding computer for remote management:

1. Log in to the forwarding computer.
2. Run a terminal session as an administrator.
3. Run the `winrm quickconfig` command.
4. Enter `Y` to start the service with delayed auto start.
5. Enter `Y` to enable the exception.
6. Enter `exit` to end the terminal session.

Setting the Collector as the Log Destination

To configure the source forwarding computer to send logs to the collector:

1. Log in to the forwarding computer.
2. Open the **Computer Management** app.
3. Open **System Tools** | **Local Users and Groups** | **Groups**.



4. Right-click on **Event Log Readers**.
5. Click on **Add to Group...**. The **Event Log Readers Properties** dialog box appears.
6. Click **Add...**. The **Select Users** dialog box appears.
7. Click **Object Types...**. The **Object Types** dialog box appears.
8. Ensure that **Computers** is enabled.
9. Click **OK**.
10. Select the collector.
11. Click **OK**.
12. Click **OK**.

Sending Event Logs to the Collector


To configure the source forwarding computer to send the event logs to the collector:

1. Log in to the forwarding computer.
2. Run a terminal session as an administrator.

3. Run the `wevtutil gl` command for each event name. For example, for security events:

   ```
   wevtutil gl security
   ```

   A display similar to the following appears.

   Note the string following **channelAccess**.

4. Run:

   ```
   wevtutil sl Security /ca:O:BAG:SYD:(A;;0xf0007;;;SY)(A;;0x7;;;BA)
   (A;;0x1;;;BO)(A;;0x1;;;SO)(A;;0x1;;;S-1-5-32-573)(A;;0x1;;;S-1-5-20)
   ```

5. Run the `wevtutil gl security` command again. The **channelAccess** string should now match the new string.
6. Repeat for each event category.
7. To verify that the logs are enabled, run:

   ```
   get log ForwardedEvents
   ```

   ```
   get log Microsoft Windows TCPIP/Operational
   ```

8. Reboot the computer.

Configuring the Sensor

To configure the sensor to receive the logs from the collector, on Stellar Cyber:

1. Click **System | DATA SOURCE MANAGEMENT | Sensors | Sensor Profiles**. The **Sensor Profile Configuration** page appears.
2. Click to edit the profile used by the sensor. The **Edit Sensor Profile** screen appears.
3. Open the **Windows** options.
4. Open the **Other Channels** options.
5. Enter **Microsoft Windows TCPIP/Operational** in the **Types** field.
6. Click **Add**. **Microsoft Windows TCPIP/Operational** appears in the **Added** box.
7. Click **Submit**.

The sensor can now receive the events forwarded by the collector.

© 2026 Stellar Cyber . All rights reserved.

