Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring CrowdStrike (Hosts/Events) Connectors 6.4.0

Stellar Cyber's CrowdStrike connector integrates CrowdStrike's streaming API to collect detections and events with the existing connector capability that collects host information.

Integration with CrowdStrike enhances Stellar Cyber's threat detection and response capabilities by providing real-time visibility into endpoint security events and enabling automated incident response workflows to contain and mitigate threats. Combining CrowdStrike's endpoint protection with Stellar Cyber's advanced security analytics and machine learning algorithms provides a comprehensive security solution for organizations.

Through the Vulnerability content type and the Vulnerability Management API, this connector supports CrowdStrike Falcon Spotlight. 6.2.0

With this CrowdStrike connector, you can also perform response actions (contain or hide hosts) on the assets that CrowdStrike Falcon manages.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: CrowdStrike

Capabilities

- Collect: **Yes**
- Respond: **Yes**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **Configurable** (Applicable only to Hosts)

Collected Data

Content Type	Index	Locating Records

Host 
File Integrity Monitoring
Vulnerability 6.2.0
Events:
AuthActivityAuditEvent
CSPMIOAStreamingEvent
CSPMSearchStreamingEvent
CustomerIOCEvent
DetectionSummaryEvent
EppDetectionSummaryEvent 5.5.0
FirewallMatchEvent
HashSpreadingEvent
IdentityProtectionEvent
IDPDetectionSummaryEvent
IncidentSummaryEvent
MobileDetectionSummaryEvent
ReconNotificationSummaryEvent
RemoteResponseSessionEndEvent
RemoteResponseSessionStartEvent
ScheduledReportNotificationEvent
UserActivityAuditEvent
Other Events
	Syslog, Assets
	Scans (for Vulnerability) 6.2.0
		msg_class:
		`crowdstrike_host`
		`crowdstrike_fim`
		`crowdstrike_vulnerability` 6.2.0
		`crowdstrike_<Event label>` (example: crowdstrike_FirewallMatchEvent)
		`crowdstrike_detection_summary`
		`crowdstrike_<event type from metadata in streaming API>` (example: crowdstrike_XdrDetectionSummaryEvent)
		
		msg_origin.source:
		`crowdstrike`
		
		msg_origin.vendor:
		`crowdstrike`
		
		msg_origin.category:
		`endpoint`

Domain

<Base URL>

where <Base URL> is a variable from the configuration of this connector

Response Actions

Action	Required Fields	API
Contain (Isolate) Host Hide Host	`dstip`, `srcip`, or `hostip`	`https://api.crowdstrike.com//devices/entities/devices-actions/v2` with parameters of host ID or device ID and an action which is one of contain, lift_containment, hide_host or unhide_host.

Third Party Native Alert Integration Details 6.4.0

This connector ingests logs from CrowdStrike to get the raw alerts that are stored in the Syslog index. Select the EppDetectionSummaryEvent content type or the `crowdstrike_{metadata.eventType}` (example: crowdstrike_XdrDetectionSummaryEvent) default content type.

Stellar Cyber maps CrowdStrike events. The events are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

Deduplication is by `tenantid` a[illegible]`owdstrike.event.CompositeId`.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- Base URL, Client ID, and Client Secret
- The API Key must have the following:
  - For **Hosts**, enable **Read** and **Write** to collect and to contain or hide hosts as a response action.
  - For **Vulnerabilities**, enable **Read** to access the Vulnerability Management API.
  - For **Audit Events** and **Detections**, enable **Read** for those as well as **Read** for **Event Streams**.

Locating Records 6.4.0

To search the alerts in the Alerts index or the Original Records in the Syslog index, use the query: `((msg_class:crowdstrike_detection_summary AND crowdstrike.metadata.eventType:EppDetectionSummaryEvent AND _exists_: event.threat.name) OR msg_class: crowdstrike_XdrDetectionSummaryEvent)`

Adding a CrowdStrike Connector

To add a CrowdStrike connector in Stellar Cyber:


1. Generate the CrowdStrike Falcon API key you will use in Stellar Cyber
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify that assets are received from CrowdStrike

Generating the CrowdStrike Falcon API Key

With streaming APIs enabled, you can generate the CrowdStrike Falcon API key:


Use our example as a guideline, as you might be using a different software version.

1. Log in to CrowdStrike Falcon at https://falcon.crowdstrike.com/.
2. Click **API Clients and Keys**.



   The **API Clients and Keys** page appears.

3. Click **Add new API client**.



The **Add new API client** window appears.

4. Enter the **Client Name**.
5. Enable **Read** and **Write** for **Hosts** to contain or hide hosts as a response action.


   Enable **Read** for **Vulnerabilities** to access the Vulnerability Management API. 6.2.0

   Enable **Read** for **Event Streams** and the following content, if you also want to collect the corresponding data: **Audit Events** and **Detections**.

   Read for **Event Streams** is required for the content other than Hosts, as of v4.3.5.



6. Click **Add**. The **API client created** window appears.




7. Copy the **Client ID** and **Secret** and note the **Base URL**. You will need these in the next section.


Adding the Connector in Stellar Cyber

With the configuration information handy, you can add the CrowdStrike connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **CrowdStrike** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. Choose the **Function**. If you want to collect logs, click the **Collect** check-box. If you want to contain or hide hosts, click the **Respond** check-box.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. Use of the connector is restricted to the tenant you select.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Enter the **Base URL**. This is the URL of your CrowdStrike portal, and can be:
    - US: **api.crowdstrike.com**
    - US-2: **api.us-2.crowdstrike.com**

- EU-1: **api.eu-1.crowdstrike.com**
- US-GOV-1: **a[redacted]ggar.gcw.crowdstrike.com**

> If you are using a government account, contact CrowdStrike support to enable event streaming.

13. Enter the **Client ID** you noted above in Generating the CrowdStrike Falcon API Key.
14. Enter the **Client Secret** you noted above.
15. Enter the **Interval (min)** if you chose **Collect**. This is how often the logs are collected for **Host** content.


> Interval is applicable only to **Host** content because the other types are collected with a streaming API.

16. Select the **Content Type** for which you enabled the API key. You can filter the event types you want to include or exclude, using these content tags:

Host	• FirewallMatchEvent • HashSpreadingEvent • IdentityProtectionEvent • IDPDetectionSummaryEvent • IncidentSummaryEvent • MobileDetectionSummaryEvent • ReconNotificationSummaryEvent • RemoteResponseSessionEndEvent • RemoteResponseSessionStartEvent • ScheduledReportNotificationEvent • UserActivityAuditEvent
File Integrity Monitoring	
Vulnerability	
Assorted Events: • AuthActivityAuditEvent • CSPMIOAStreamingEvent • CSPMSearchStreamingEvent • CustomerIOCEvent • DetectionSummaryEvent • EppDetectionSummaryEvent	**Other Events**: (Use this tag if you want to collect event types not specifically listed above)

You can optionally add the type **Other Events** to collect any remaining content types.

17. Click **Next**. The final confirmation tab appears.



18. Click **Submit**.


The new connector is immediately active. You can now contain or hide hosts from the event display, and view or edit those actions on the **Endpoint Actions** page.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

   Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Content

To verify Stellar Cyber is receiving content from CrowdStrike:

For **Host**:

1. Select **Assets | Asset Analytics**.
2. Select the **MAC-Identified Assets** tab.
3. Enter `crowdstrike` in the Search field. The results list is updated.

For other content:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.
2. Change the **Indices** for the type of content you collected:
   - For all content types, change the **Indices** to **Syslog**.
   - For **Host** only, change the **Indices** to **Assets**.
   - For **Vulnerability** only, change the **Indices** to **Scans**. 6.2.0

   The table immediately updates to show ingested Interflow records.



© 2026 Stellar Cyber . All rights reserved.