Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring CrowdStrike FDR Connectors 6.0.0

This connector allows Stellar Cyber to ingest logs from CrowdStrike Falcon Data Replicator (FDR) and add the records to the data lake. This connector supports ingestion of secondary events as attachments. It requires the Falcon Insight XDR license.

CrowdStrike FDR uses S3 buckets and Simple Queue Service (SQS) queues for data streaming.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: CrowdStrike FDR

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **No**
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Aid Master
App Info
Managed Assets
Not Managed Assets
User Info
	Syslog	msg_class:
		`crowdstrike_fdr_aidmaster`
		`crowdstrike_fdr_appinfo`
		`crowdstrike_fdr_managedassets`
		`crowdstrike_fdr_notmanagedassets`

Content Type	Index	Locating Records

	`crowdstrike_fdr_userinfo`
	
	msg_origin.source:
	`crowdstrike_fdr`
	
	msg_origin.vendor:
	`crowdstrike`
	
	msg_origin.category:
	`endpoint`

Domain

N/A

Response Actions

N/A

Third Party Native Alert Integration Details

N/A

Required Credentials and Configurations

- Access Key, Secret Key, and SQS Queue URL, plus Region

Adding a CrowdStrike FDR Connector

To add a CrowdStrike FDR connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining CrowdStrike FDR Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following CrowdStrike FDR credentials. Follow the guidance in the CrowdStrike FDR documentation, for example, *Falcon Data Replicator (FDR) schema API*.

- Access Key—The unique identifier for an API client, used for authentication and also known as a client ID.
- Secret Key—The secret key used for authentication and also known as a client secret.
- SQS Queue URL—The unique identifier for an Amazon Simple Queue Service (SQS) queue. The URL is a specific address that points to the SQS queue.

The API client credentials must have the following scope enabled:

API client scope requirements

To interact with the FDR schema APIs, your API clien ntials must have the following scope enabled:


- **Falcon Data Replicator: Read**

API clients are managed through API Clients and Keys [/api-clients-and-keys] (**Support and resources > Resources and tools > API Clients and Keys**) in the Falcon console.

Create the client ID and client secret from the CrowdStrike platform:

1. Log in to CrowdStrike Falcon at https://falcon.crowdstrike.com/.
2. Click **Support and resources**.
3. Click **Resources and tools**.
4. Click **API Clients and Keys**.
5. Click **Add new API client**.
6. Enter the **Client Name**.
7. Select **API Scopes**, including Falcon Data Replicator: Read.
8. Click **Add**.
9. Copy the **Client ID** and **Secret**.


For the SQS Queue URL, refer to the following section in the *CrowdStrike Falcon Data Replicator (FDR): SQS Add-on for Splunk Installation and Configuration Guide*.




Adding the Connector in Stellar Cyber

To add a CrowdStrike FDR connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **CrowdStrike FDR** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.

Notes:

- This field does not accept multibyte characters.
- It is recommended that you follow a naming convention such as tenantname-connectortype.


8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Enter the **Access Key** you noted above in Obtaining CrowdStrike FDR Credentials.
13. Enter the **Secret Key** you noted above.
14. Choose the **Region** from the dropdown.

15. Enter the **SQS Queue URL** you noted above.
16. Choose the **Interval (r**. This is how often the logs are collected.
17. Choose the **Content Type** you would like to collect. The logs for **Aid Master**, **App Info**, **Managed Assets**, **Not Managed Assets**, and **User Info** are supported.
18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.


The new connector is immediately active.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

The table immediately updates to show ingested Interflow records.



© 2026 Stellar Cyber . All rights reserved.