Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring CyberArk EPM Connectors 6.0.0 6.2.0

This connector allows Stellar Cyber to ingest logs from CyberArk Endpoint Privilege Manager (EPM) and add the records to the data lake. It integrates with the CyberArk EPM API to query for Events and Policy Audits.

Refer to the rate limit information in the CyberArk documentation. In addition, only one CyberArk EPM connector can run at a time.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: CyberArk EPM

Capabilities

- Collect: **Yes**
- Respond: **No**
- Native Alerts Mapped: **Yes** 6.2.0
- Runs on: **DP**
- Interval: **Configurable**

Collected Data

Content Type	Index	Locating Records

Events
Policy Audits
	Syslog	msg_class:
		`cyberark_epm_event`
		`cyberark_epm_policy_audit`
		
		msg_origin.source:
		`cyberark_epm`

Content Type	Index	Locating Records
		msg_origin.vendor: `cyberark` msg_origin.category: `endpoint`

Domain

<Base URL> or <Custom Base URL>

where <Base URL> or <Custom Base URL> is a variable from the configuration of this connector

Response Actions

N/A

Third Party Native Alert Integration Details 6.2.0

This connector ingests logs from CyberArk EPM to get the raw alerts that are stored in the Syslog index. Select the Events content type.

Stellar Cyber maps CyberArk EPM events. The events are read from the Syslog index, enriched with Stellar Cyber fields, and mapped (with deduplication) to the Alerts index.

The following threat detection categories are supported: AttackAttempt, AttackBlock, SuspiciousActivityAttempt, and SuspiciousActivityBlock.

Deduplication is by `tenantid`, `cyberark_epm.eventType`, `cyberark_epm.policyName`, `cyberark_epm.filePath`, and `cyberark_epm.userName`.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- Base URL or Custom Base URL, Username, and Password

Locating Records 6.2.0

To search the alerts in the Alerts index or the Original Records in the Syslog index, use the query: `msg_class: cyberark_epm_event AND _exists_: event.threat.name AND cyberark_epm.eventType: (AttackAttempt | AttackBlock | SuspiciousActivityAttempt | SuspiciousActivityBlock)`

Adding a CyberArk EPM Connector

To add a CyberArk EPM connector:

1. Obtain credentials
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion

Obtaining CyberArk EPM Credentials

Before you configure the connector in Stellar Cyber, you must obtain the following CyberArk EPM credentials:


- Base URL—The base URL for API access, which you can select from the dropdown menu. Follow the guidance in the CyberArk documentation for the EPM dispatcher server name to use for your region.
- Custom Base URL—The custom base URL, which you can enter if a server is not available in the Base URL dropdown menu.
- Username and Password—The authentication credentials, which are used to retrieve an access token to be used in subsequent requests. Follow the guidance in the CyberArk documentation for EPM authentication.

The content types, Events and Policy Audits only search data within a set ID. You must make an initial query to get the full list of sets. Then you can make API requests to get the events and policy audits for each set ID. Follow the guidance in the CyberArk documentation for getting the list of sets.


Adding the Connector in Stellar Cyber

To add a CyberArk EPM connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



   The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **CyberArk EPM** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. For this connector, the supported **Function** is **Collect**, which is enabled already.
7. Enter a **Name**.


   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears.



The asterisk (*) indicates a required field.

12. Select the **Base URL** you noted above in Obtaining CyberArk EPM Credentials.
13. Or, enter the **Custom Base URL** you noted above.
14. Enter the **Username** and **Password** you noted above.
15. Choose the **Interval (min)**. This is how often the logs are collected.
16. Choose the **Content Type** you would like to collect. The logs for **Events** and **Policy Audits** are supported.
17. (Optional) Click **Disable SSL Certificate Verification** if you want to disable SSL certificate verification. Only disable SSL certificates if you have a necessary reason to, otherwise, it is not a good security practice and may expose the connection to security risks.
18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.

The new connector is immediately active.


Testing the Connector

In addition to testing for connectivity, the **Test** button for the CyberArk EPM connector tests that the Base URL, Username and Password are correct and data requests for the requested content types return successful responses.

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog**.

   The table immediately updates to show ingested Interflow records.



© 2026 Stellar Cyber . All rights reserved.