Stellar Cyber 6.6.0s is now live! Discover all the updates in the release notes!

Configuring Cybereason Connectors

A Stellar Cyber Cybereason connector allows you to ingest Cybereason MalOp and Sensor data, discover assets, and contain hosts using API calls to the Cybereason server managing those hosts.

Stellar Cyber connectors with the Collect function (collectors) may skip collecting some data when the ingestion volume is large, which potentially can lead to data loss. This can happen when the processing capacity of the collector is exceeded.

Connector Overview: Cybereason

Capabilities

- Collect: **Yes**
- Respond: **Yes**
- Native Alerts Mapped: **Yes**
- Runs on: **DP**
- Interval: **Configurable for MalOp; 24 hrs for Sensor**

Collected Data

Content Type	Index	API
Sensor	Assets Sensor Monitoring Syslog	`https://<server>:port/rest/sensors/query`
MalOp	Alerts Syslog	`https://<your server>:port/rest/detection/inbox`

Domain

https://<Server>:<Port>

where <Server> and <Port> are variables from the configuration of this connector

Response Actions

Action	Required Fields	API
Contain (Isolate) Host	cybereason.pylumId	https://<your server address>/rest/monitor/global/commands/isolate https://<your server address>/rest/monitor/global/commands/un-isolate

Third Party Native Alert Integration Details

Sensors	This content is not applicable for alert mapping.
MalOp	Stellar Cyber can generate alerts based on the Cybereason sensor and MalOp data, however the MalOp records are most applicable for direct mapping. The value in `malopDetectionType` is reformatted and used for the alert name. Stellar Cyber has evaluated each possible alert and assigned a corresponding MITRE | ATT&CK Stage, Tactic and Technique.

For details, see Integration of Third Party Native Alerts.

Required Credentials and Configurations

- Username, Password, Server, and Port



User account must have API privileges

Locating Records

Use the following fields as a guide to query for records:

- **msg_origin.vendor**: cy[illegible]eason
- **msg_origin.category**: [illegible]point

MalOp	Sensors
msg_class: `cybereason_malops_all_types` **msg_origin.source**: `cybereason_malops_all_types` prior to v4.3.4 **msg_class**: `cybereason_malops` **msg_origin.source**: `cybereason_malops`	**msg_class**: `cybereason_sensors` **msg_origin.source**: `cybereason_sensors`

Adding a Cybereason Connector

To add a Cybereason connector:

1. Configure Cybereason access
2. Add the connector in Stellar Cyber
3. Test the connector
4. Verify ingestion


Configuring Cybereason Access

You must configure Cybereason management before you add the connector in Stellar Cyber and obtain the following details:


- Username
- Password
- Server address and port for API communication

To obtain the information:

1. Log in to the Cybereason console as an administrative user.
2. Follow guidance in the Cybereason documentation to ensure the server is enabled for API access.
3. Create a user account for use with Stellar Cyber connector that has API privileges (refer to "Create a User" in the Cybereason documentation, for example: https://nest.cybereason.com/user/login?destination=/documentation/product-documentation/201/create-edit-and-remove-users) .



For the **Sensor** content type, you may need to select the following user roles:



For details, refer to Required Roles Per Endpoint in the Cybereason documentation.


4. Make note of the Cybereason username and password before proceeding to the next step.

The password should not include non-ASCII special characters.


Adding the Connector in Stellar Cyber

To add a Cybereason client connector in Stellar Cyber:

1. Log in to Stellar Cyber.
2. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.




3. Click **Create** and select **Connector**.



The **General** tab of the **Add Connector** screen appears. The information on this tab cannot be changed after you add the connector.

4. Choose **Endpoint Security** from the **Category** dropdown.
5. Choose **Cybereason** from the **Type** dropdown.




The asterisk (*) indicates a required field.

6. Choose the **Function**: **Collect** to collect logs; **Respond** to contain hosts.

7. Enter a **Name**.

   Notes:
   - This field does not accept multibyte characters.
   - It is recommended that you follow a naming convention such as tenantname-connectortype.

8. Choose a **Tenant Name**. The Interflow records created by this connector include this tenant name.
9. Choose the device on which to run the connector.
10. (Optional) When the **Function** is **Collect**, you can apply **Log Filters**. For information, see Managing Log Filters.
11. Click **Next**. The **Configuration** tab appears. Complete this screen with the data you collected from your Cybereason setup steps in the previous section.



   The asterisk (*) indicates a required field.


12. Enter the **Username** for use with the API call you noted above in Configuring Cybereason Access.
13. Enter the **Password** corresponding to that username you noted above.
14. Enter the address of the Cybereason **Server** receiving API calls (for example: integration.cybereason.net).
15. Enter the associated **Port** for that server.
16. Enter the **Interval (min)**. If you chose **Collect**, this is how often the logs are collected.

    The interval setting applies to the **MalOp** content type. The logs for **Sensor** are queried every 24 hours.

17. Choose the **Content Type**. The logs for **MalOp** and **Sensor** are supported.

    The **Sensor** content type is required to support **Respond** actions.

18. Click **Next**. The final confirmation tab appears.



19. Click **Submit**.


The new connector is immediat ctive.

Testing the Connector

When you add (or edit) a connector, we recommend that you run a test to validate the connectivity parameters you entered. The test validates authentication and connectivity.

For connectors running on a sensor, Stellar Cyber recommends that you allow 30-60 seconds for new or modified configuration details to be propagated to the sensor before performing a test.

1. Click **System | INTEGRATIONS | Connectors**. The **Connector Overview** appears.



2. Locate the connector by name that you added, or modified, or that you want to test.
3. Click **Test** at the right side of that row. The test runs immediately.

Note that you may run only one test at a time.

Stellar Cyber conducts a basic connectivity test for the connector and reports a success or failure result. A successful test indicates that you entered all of the connector information correctly.

To aid troubleshooting your connector, the dialog remains open until you explicitly close it by using the **X** button. If the test fails, you can select the button from the same row to review and correct issues.

The connector status is updated every five (5) minutes. A successful test clears the connector status, but if issues persist, the status reverts to failed after a minute.


Repeat the test as needed.

Display sample messages...


Success !



Failure with summary of issue:



Show More example detail:



If the test fails, the common HTTP status error codes are as follows:

HTTP Error Code	HTTP Standard Error Name	Explanation	Recommendation
400	Bad Request	This error occurs when there is an error in the connector configuration.	Did you configure the connector correctly?
401	Unauthorized	This error occurs when an authentication credential is invalid or when a user does not have sufficient privileges to access a specific API.	Did you enter your credentials correctly? Are your credentials expired? Are your credentials entitled or licensed for that specific resource?
403	Forbidden	This error occurs when the permission or scope is not correct in a valid credential.	Did you enter your credentials correctly? Do you have the required role or permissions for that credential?
404	Not Found	This error occurs when a URL path does not resolve to an entity.	Did you enter your API URL correctly?
429	Too Many Requests	This error occurs when the API server receives too much traffic or if a user's license or entitlement quota is exceeded.	The server or user license/quota will eventually recover. The connector will periodically retry the query. If this occurs unexpectedly or too often, work with your API provider to investigate the server limits, user licensing, or quotas.

For a full list of codes, refer to HTTP response status codes.

Verifying Ingestion

To verify ingestion:

1. Select **Threat Hunting**.

   The **Interflow Search** tab appears.

2. Change the **Indices** to **Syslog** if you set **MalOp** as a content type. Use the **Assets**, **Syslog**, and **Sensor Monitoring** indices for the **Sensor** content type.

   The table immediately updates to show ingested Interflow records.

You can also find assets from Cybereason **Sensor** content reported in the **Assets | Asset Analytics | IP Identified Assets** view.

If you configured the connector Respond actions, refer to **External Actions: Contain Host** to understand how to work with the Contain Host feature.

© 2026 Stellar Cyber . All rights reserved.